



CUDA Driver API

API Reference Manual

Table of Contents

Chapter 1. Difference between the driver and runtime APIs.....	1
Chapter 2. API synchronization behavior.....	3
Chapter 3. Stream synchronization behavior.....	5
Chapter 4. Graph object thread safety.....	7
Chapter 5. Rules for version mixing.....	8
Chapter 6. Modules.....	9
6.1. Data types used by CUDA driver.....	10
CUaccessPolicyWindow_v1.....	11
CUarrayMapInfo_v1.....	11
CUDA_ARRAY3D_DESCRIPTOR_v2.....	11
CUDA_ARRAY_DESCRIPTOR_v2.....	11
CUDA_ARRAY_SPARSE_PROPERTIES_v1.....	11
CUDA_EXT_SEM_SIGNAL_NODE_PARAMS_v1.....	11
CUDA_EXT_SEM_WAIT_NODE_PARAMS_v1.....	11
CUDA_EXTERNAL_MEMORY_BUFFER_DESC_v1.....	11
CUDA_EXTERNAL_MEMORY_HANDLE_DESC_v1.....	11
CUDA_EXTERNAL_MEMORY_MIPMAPPED_ARRAY_DESC_v1.....	11
CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC_v1.....	11
CUDA_EXTERNAL_SEMAPHORE_SIGNAL_PARAMS_v1.....	11
CUDA_EXTERNAL_SEMAPHORE_WAIT_PARAMS_v1.....	11
CUDA_HOST_NODE_PARAMS_v1.....	12
CUDA_KERNEL_NODE_PARAMS_v1.....	12
CUDA_LAUNCH_PARAMS_v1.....	12
CUDA_MEMCPY2D_v2.....	12
CUDA_MEMCPY3D_PEER_v1.....	12
CUDA_MEMCPY3D_v2.....	12
CUDA_MEMSET_NODE_PARAMS_v1.....	12
CUDA_POINTER_ATTRIBUTE_P2P_TOKENS_v1.....	12
CUDA_RESOURCE_DESC_v1.....	12
CUDA_RESOURCE_VIEW_DESC_v1.....	12
CUDA_TEXTURE_DESC_v1.....	12
CUdevprop_v1.....	12
CUeglFrame_v1.....	12
CUipcEventHandle_v1.....	12

CUipcMemHandle_v1.....	12
CUkernelNodeAttrValue_v1.....	12
CUmемAccessDesc_v1.....	12
CUmемAllocationProp_v1.....	13
CUmемLocation_v1.....	13
CUmемPoolProps_v1.....	13
CUmемPoolPtrExportData_v1.....	13
CUstreamAttrValue_v1.....	13
CUstreamBatchMemOpParams_v1.....	13
CUaccessProperty.....	13
CUaddress_mode.....	13
CUarray_cubemap_face.....	14
CUarray_format.....	14
CUarraySparseSubresourceType.....	15
CUcomputemode.....	15
CUctx_flags.....	15
CUDA_POINTER_ATTRIBUTE_ACCESS_FLAGS.....	16
CUdevice_attribute.....	16
CUdevice_P2PAttribute.....	22
CUdriverProcAddress_flags.....	23
CUeglColorFormat.....	23
CUeglFrameType.....	28
CUeglResourceLocationFlags.....	29
CUevent_flags.....	29
CUevent_record_flags.....	29
CUevent_wait_flags.....	30
CUexternalMemoryHandleType.....	30
CUexternalSemaphoreHandleType.....	30
CUfilter_mode.....	31
CUflushGPUDirectRDMAWritesOptions.....	31
CUflushGPUDirectRDMAWritesScope.....	32
CUflushGPUDirectRDMAWritesTarget.....	32
CUfunc_cache.....	32
CUfunction_attribute.....	32
CUGPUDirectRDMAWritesOrdering.....	33
CUgraphDebugDot_flags.....	34
CUgraphicsMapResourceFlags.....	34
CUgraphicsRegisterFlags.....	35

CUgraphNodeType.....	35
CUipcMem_flags.....	35
CUjit_cacheMode.....	36
CUjit_fallback.....	36
CUjit_option.....	36
CUjit_target.....	38
CUjitInputType.....	39
CUkernelNodeAttrID.....	40
CULimit.....	40
CUMem_advise.....	40
CUMemAccess_flags.....	41
CUMemAllocationCompType.....	41
CUMemAllocationGranularity_flags.....	41
CUMemAllocationHandleType.....	42
CUMemAllocationType.....	42
CUMemAttach_flags.....	42
CUMemHandleType.....	42
CUMemLocationType.....	43
CUMemOperationType.....	43
CUMemorytype.....	43
CUoccupancy_flags.....	43
CUpointer_attribute.....	44
CUresourcetype.....	45
CUresourceViewFormat.....	45
CUresult.....	47
CUshared_carveout.....	53
CUsharedconfig.....	53
CUstream_flags.....	53
CUstreamAttrID.....	54
CUstreamBatchMemOpType.....	54
CUstreamCaptureMode.....	54
CUstreamCaptureStatus.....	54
CUstreamUpdateCaptureDependencies_flags.....	55
CUstreamWaitValue_flags.....	55
CUstreamWriteValue_flags.....	56
CUUserObject_flags.....	56
CUUserObjectRetain_flags.....	56
CUarray.....	56

CUcontext.....	56
CUdevice.....	56
CUdevice_v1.....	57
CUdeviceptr.....	57
CUdeviceptr_v2.....	57
CUeglStreamConnection.....	57
CUevent.....	57
CUexternalMemory.....	57
CUexternalSemaphore.....	57
CUfunction.....	57
CUgraph.....	57
CUgraphExec.....	57
CUgraphicsResource.....	58
CUGraphNode.....	58
CUhostFn.....	58
CUmemoryPool.....	58
CUmipmappedArray.....	58
CUmodule.....	58
CUoccupancyB2DSize.....	58
CUstream.....	58
CUstreamCallback.....	58
CUsurfObject.....	59
CUsurfObject_v1.....	59
CUsurfref.....	59
CUtexObject.....	59
CUtexObject_v1.....	59
CUtexref.....	59
CUuserObject.....	59
CU_ARRAY_SPARSE_PROPERTIES_SINGLE_MIPTAIL.....	59
CU_DEVICE_CPU.....	59
CU_DEVICE_INVALID.....	59
CU_IPC_HANDLE_SIZE.....	60
CU_LAUNCH_PARAM_BUFFER_POINTER.....	60
CU_LAUNCH_PARAM_BUFFER_SIZE.....	60
CU_LAUNCH_PARAM_END.....	60
CU_MEM_CREATE_USAGE_TILE_POOL.....	60
CU_MEMHOSTALLOC_DEVICEMAP.....	60
CU_MEMHOSTALLOC_PORTABLE.....	60

CU_MEMHOSTALLOC_WRITECOMBINED.....	61
CU_MEMHOSTREGISTER_DEVICEMAP.....	61
CU_MEMHOSTREGISTER_IOMEMORY.....	61
CU_MEMHOSTREGISTER_PORTABLE.....	61
CU_MEMHOSTREGISTER_READ_ONLY.....	61
CU_PARAM_TR_DEFAULT.....	61
CU_STREAM_LEGACY.....	62
CU_STREAM_PER_THREAD.....	62
CU_TRSA_OVERRIDE_FORMAT.....	62
CU_TRSF_DISABLE_TRILINEAR_OPTIMIZATION.....	62
CU_TRSF_NORMALIZED_COORDINATES.....	62
CU_TRSF_READ_AS_INTEGER.....	62
CU_TRSF_SRGB.....	62
CUDA_ARRAY3D_2DARRAY.....	63
CUDA_ARRAY3D_COLOR_ATTACHMENT.....	63
CUDA_ARRAY3D_CUBEMAP.....	63
CUDA_ARRAY3D_DEPTH_TEXTURE.....	63
CUDA_ARRAY3D_LAYERED.....	63
CUDA_ARRAY3D_SPARSE.....	63
CUDA_ARRAY3D_SURFACE_LDST.....	63
CUDA_ARRAY3D_TEXTURE_GATHER.....	63
CUDA_COOPERATIVE_LAUNCH_MULTI_DEVICE_NO_POST_LAUNCH_SYNC.....	64
CUDA_COOPERATIVE_LAUNCH_MULTI_DEVICE_NO_PRE_LAUNCH_SYNC.....	64
CUDA_EGL_INFINITE_TIMEOUT.....	64
CUDA_EXTERNAL_MEMORY_DEDICATED.....	64
CUDA_EXTERNAL_SEMAPHORE_SIGNAL_SKIP_NVSCIBUF_MEMSYNC.....	64
CUDA_EXTERNAL_SEMAPHORE_WAIT_SKIP_NVSCIBUF_MEMSYNC.....	65
CUDA_NVSCISYNC_ATTR_SIGNAL.....	65
CUDA_NVSCISYNC_ATTR_WAIT.....	65
CUDA_VERSION.....	65
MAX_PLANES.....	65
6.2. Error Handling.....	65
cuGetErrorName.....	66
cuGetErrorString.....	66
6.3. Initialization.....	67
cuInit.....	67
6.4. Version Management.....	67
cuDriverGetVersion.....	68

6.5. Device Management.....	68
cuDeviceGet.....	68
cuDeviceGetAttribute.....	69
cuDeviceGetCount.....	75
cuDeviceGetDefaultMemPool.....	76
cuDeviceGetLuid.....	76
cuDeviceGetMemPool.....	77
cuDeviceGetName.....	77
cuDeviceGetNvSciSyncAttributes.....	78
cuDeviceGetTexture1DLinearMaxWidth.....	79
cuDeviceGetUuid.....	80
cuDeviceSetMemPool.....	81
cuDeviceTotalMem.....	81
6.6. Device Management [DEPRECATED].....	82
cuDeviceComputeCapability.....	82
cuDeviceGetProperties.....	83
6.7. Primary Context Management.....	84
cuDevicePrimaryCtxGetState.....	84
cuDevicePrimaryCtxRelease.....	85
cuDevicePrimaryCtxReset.....	86
cuDevicePrimaryCtxRetain.....	87
cuDevicePrimaryCtxSetFlags.....	88
6.8. Context Management.....	89
cuCtxCreate.....	89
cuCtxDestroy.....	91
cuCtxGetApiVersion.....	92
cuCtxGetCacheConfig.....	93
cuCtxGetCurrent.....	94
cuCtxGetDevice.....	94
cuCtxGetFlags.....	95
cuCtxGetLimit.....	95
cuCtxGetSharedMemConfig.....	96
cuCtxGetStreamPriorityRange.....	97
cuCtxPopCurrent.....	98
cuCtxPushCurrent.....	99
cuCtxResetPersistingL2Cache.....	100
cuCtxSetCacheConfig.....	100
cuCtxSetCurrent.....	101

cuCtxSetLimit.....	102
cuCtxSetSharedMemConfig.....	104
cuCtxSynchronize.....	105
6.9. Context Management [DEPRECATED].....	105
cuCtxAttach.....	105
cuCtxDetach.....	106
6.10. Module Management.....	107
cuLinkAddData.....	107
cuLinkAddFile.....	108
cuLinkComplete.....	109
cuLinkCreate.....	110
cuLinkDestroy.....	111
cuModuleGetFunction.....	111
cuModuleGetGlobal.....	112
cuModuleGetSurfRef.....	113
cuModuleGetTexRef.....	113
cuModuleLoad.....	114
cuModuleLoadData.....	115
cuModuleLoadDataEx.....	116
cuModuleLoadFatBinary.....	117
cuModuleUnload.....	118
6.11. Memory Management.....	119
cuArray3DCreate.....	119
cuArray3DGetDescriptor.....	122
cuArrayCreate.....	123
cuArrayDestroy.....	125
cuArrayGetDescriptor.....	126
cuArrayGetPlane.....	127
cuArrayGetSparseProperties.....	128
cuDeviceGetByPCIBusId.....	129
cuDeviceGetPCIBusId.....	129
culpcCloseMemHandle.....	130
culpcGetEventHandle.....	131
culpcGetMemHandle.....	132
culpcOpenEventHandle.....	132
culpcOpenMemHandle.....	133
cuMemAlloc.....	134
cuMemAllocHost.....	135

cuMemAllocManaged.....	136
cuMemAllocPitch.....	139
cuMemcpy.....	140
cuMemcpy2D.....	142
cuMemcpy2DAsync.....	144
cuMemcpy2DUnaligned.....	147
cuMemcpy3D.....	150
cuMemcpy3DAsync.....	152
cuMemcpy3DPeer.....	155
cuMemcpy3DPeerAsync.....	156
cuMemcpyAsync.....	157
cuMemcpyAtoA.....	158
cuMemcpyAtoD.....	159
cuMemcpyAtoH.....	160
cuMemcpyAtoHAsync.....	161
cuMemcpyDtoA.....	162
cuMemcpyDtoD.....	163
cuMemcpyDtoDAsync.....	164
cuMemcpyDtoH.....	166
cuMemcpyDtoHAsync.....	167
cuMemcpyHtoA.....	168
cuMemcpyHtoAAsync.....	169
cuMemcpyHtoD.....	170
cuMemcpyHtoDAsync.....	171
cuMemcpyPeer.....	173
cuMemcpyPeerAsync.....	174
cuMemFree.....	175
cuMemFreeHost.....	175
cuMemGetAddressRange.....	176
cuMemGetInfo.....	177
cuMemHostAlloc.....	178
cuMemHostGetDevicePointer.....	180
cuMemHostGetFlags.....	181
cuMemHostRegister.....	182
cuMemHostUnregister.....	184
cuMemsetD16.....	184
cuMemsetD16Async.....	185
cuMemsetD2D16.....	186

cuMemsetD2D16Async.....	188
cuMemsetD2D32.....	189
cuMemsetD2D32Async.....	190
cuMemsetD2D8.....	191
cuMemsetD2D8Async.....	192
cuMemsetD32.....	193
cuMemsetD32Async.....	194
cuMemsetD8.....	195
cuMemsetD8Async.....	196
cuMipmappedArrayCreate.....	197
cuMipmappedArrayDestroy.....	200
cuMipmappedArrayGetLevel.....	201
cuMipmappedArrayGetSparseProperties.....	202
6.12. Virtual Memory Management.....	203
cuMemAddressFree.....	203
cuMemAddressReserve.....	204
cuMemCreate.....	205
cuMemExportToShareableHandle.....	206
cuMemGetAccess.....	207
cuMemGetAllocationGranularity.....	207
cuMemGetAllocationPropertiesFromHandle.....	208
cuMemImportFromShareableHandle.....	209
cuMemMap.....	210
cuMemMapArrayAsync.....	211
cuMemRelease.....	214
cuMemRetainAllocationHandle.....	215
cuMemSetAccess.....	215
cuMemUnmap.....	216
6.13. Stream Ordered Memory Allocator.....	217
cuMemAllocAsync.....	218
cuMemAllocFromPoolAsync.....	219
cuMemFreeAsync.....	220
cuMemPoolCreate.....	220
cuMemPoolDestroy.....	221
cuMemPoolExportPointer.....	221
cuMemPoolExportToShareableHandle.....	222
cuMemPoolGetAccess.....	223
cuMemPoolGetAttribute.....	223

cuMemPoolImportFromShareableHandle.....	225
cuMemPoolImportPointer.....	226
cuMemPoolSetAccess.....	227
cuMemPoolSetAttribute.....	227
cuMemPoolTrimTo.....	228
6.14. Unified Addressing.....	229
cuMemAdvise.....	231
cuMemPrefetchAsync.....	234
cuMemRangeGetAttribute.....	236
cuMemRangeGetAttributes.....	238
cuPointerGetAttribute.....	239
cuPointerGetAttributes.....	242
cuPointerSetAttribute.....	244
6.15. Stream Management.....	245
cuStreamAddCallback.....	245
cuStreamAttachMemAsync.....	247
cuStreamBeginCapture.....	249
cuStreamCopyAttributes.....	250
cuStreamCreate.....	250
cuStreamCreateWithPriority.....	251
cuStreamDestroy.....	252
cuStreamEndCapture.....	253
cuStreamGetAttribute.....	254
cuStreamGetCaptureInfo.....	254
cuStreamGetCaptureInfo_v2.....	255
cuStreamGetCtx.....	257
cuStreamGetFlags.....	258
cuStreamGetPriority.....	258
cuStreamIsCapturing.....	259
cuStreamQuery.....	260
cuStreamSetAttribute.....	261
cuStreamSynchronize.....	261
cuStreamUpdateCaptureDependencies.....	262
cuStreamWaitEvent.....	263
cuThreadExchangeStreamCaptureMode.....	264
6.16. Event Management.....	265
cuEventCreate.....	265
cuEventDestroy.....	266

cuEventElapsedTime.....	267
cuEventQuery.....	268
cuEventRecord.....	269
cuEventRecordWithFlags.....	270
cuEventSynchronize.....	271
6.17. External Resource Interoperability.....	271
cuDestroyExternalMemory.....	272
cuDestroyExternalSemaphore.....	272
cuExternalMemoryGetMappedBuffer.....	273
cuExternalMemoryGetMappedMipmappedArray.....	274
cuImportExternalMemory.....	276
cuImportExternalSemaphore.....	279
cuSignalExternalSemaphoresAsync.....	282
cuWaitExternalSemaphoresAsync.....	284
6.18. Stream memory operations.....	286
cuStreamBatchMemOp.....	286
cuStreamWaitValue32.....	287
cuStreamWaitValue64.....	288
cuStreamWriteValue32.....	289
cuStreamWriteValue64.....	290
6.19. Execution Control.....	291
cuFuncGetAttribute.....	291
cuFuncGetModule.....	293
cuFuncSetAttribute.....	293
cuFuncSetCacheConfig.....	295
cuFuncSetSharedMemConfig.....	296
cuLaunchCooperativeKernel.....	297
cuLaunchCooperativeKernelMultiDevice.....	299
cuLaunchHostFunc.....	302
cuLaunchKernel.....	303
6.20. Execution Control [DEPRECATED].....	306
cuFuncSetBlockShape.....	306
cuFuncSetSharedSize.....	307
cuLaunch.....	307
cuLaunchGrid.....	308
cuLaunchGridAsync.....	309
cuParamSetf.....	311
cuParamSeti.....	311

cuParamSetSize.....	312
cuParamSetTexRef.....	313
cuParamSetv.....	314
6.21. Graph Management.....	314
cuGraphAddChildGraphNode.....	315
cuGraphAddDependencies.....	316
cuGraphAddEmptyNode.....	317
cuGraphAddEventRecordNode.....	318
cuGraphAddEventWaitNode.....	319
cuGraphAddExternalSemaphoresSignalNode.....	320
cuGraphAddExternalSemaphoresWaitNode.....	321
cuGraphAddHostNode.....	323
cuGraphAddKernelNode.....	324
cuGraphAddMemcpyNode.....	326
cuGraphAddMemsetNode.....	327
cuGraphChildGraphNodeGetGraph.....	328
cuGraphClone.....	329
cuGraphCreate.....	330
cuGraphDebugDotPrint.....	331
cuGraphDestroy.....	331
cuGraphDestroyNode.....	332
cuGraphEventRecordNodeGetEvent.....	332
cuGraphEventRecordNodeSetEvent.....	333
cuGraphEventWaitNodeGetEvent.....	334
cuGraphEventWaitNodeSetEvent.....	334
cuGraphExecChildGraphNodeSetParams.....	335
cuGraphExecDestroy.....	336
cuGraphExecEventRecordNodeSetEvent.....	337
cuGraphExecEventWaitNodeSetEvent.....	338
cuGraphExecExternalSemaphoresSignalNodeSetParams.....	339
cuGraphExecExternalSemaphoresWaitNodeSetParams.....	340
cuGraphExecHostNodeSetParams.....	341
cuGraphExecKernelNodeSetParams.....	342
cuGraphExecMemcpyNodeSetParams.....	343
cuGraphExecMemsetNodeSetParams.....	344
cuGraphExecUpdate.....	346
cuGraphExternalSemaphoresSignalNodeGetParams.....	348
cuGraphExternalSemaphoresSignalNodeSetParams.....	349

cuGraphExternalSemaphoresWaitNodeGetParams.....	350
cuGraphExternalSemaphoresWaitNodeSetParams.....	351
cuGraphGetEdges.....	352
cuGraphGetNodes.....	353
cuGraphGetRootNodes.....	353
cuGraphHostNodeGetParams.....	354
cuGraphHostNodeSetParams.....	355
cuGraphInstantiate.....	356
cuGraphKernelNodeCopyAttributes.....	357
cuGraphKernelNodeGetAttribute.....	357
cuGraphKernelNodeGetParams.....	358
cuGraphKernelNodeSetAttribute.....	359
cuGraphKernelNodeSetParams.....	359
cuGraphLaunch.....	360
cuGraphMemcpyNodeGetParams.....	361
cuGraphMemcpyNodeSetParams.....	362
cuGraphMemsetNodeGetParams.....	362
cuGraphMemsetNodeSetParams.....	363
cuGraphNodeFindInClone.....	364
cuGraphNodeGetDependencies.....	365
cuGraphNodeGetDependentNodes.....	366
cuGraphNodeGetType.....	367
cuGraphReleaseUserObject.....	367
cuGraphRemoveDependencies.....	368
cuGraphRetainUserObject.....	369
cuGraphUpload.....	370
cuUserObjectCreate.....	370
cuUserObjectRelease.....	371
cuUserObjectRetain.....	372
6.22. Occupancy.....	373
cuOccupancyAvailableDynamicSMemPerBlock.....	373
cuOccupancyMaxActiveBlocksPerMultiprocessor.....	374
cuOccupancyMaxActiveBlocksPerMultiprocessorWithFlags.....	375
cuOccupancyMaxPotentialBlockSize.....	376
cuOccupancyMaxPotentialBlockSizeWithFlags.....	377
6.23. Texture Reference Management [DEPRECATED].....	379
cuTexRefCreate.....	379
cuTexRefDestroy.....	379

cuTexRefGetAddress.....	380
cuTexRefGetAddressMode.....	381
cuTexRefGetArray.....	381
cuTexRefGetBorderColor.....	382
cuTexRefGetFilterMode.....	383
cuTexRefGetFlags.....	383
cuTexRefGetFormat.....	384
cuTexRefGetMaxAnisotropy.....	385
cuTexRefGetMipmapFilterMode.....	385
cuTexRefGetMipmapLevelBias.....	386
cuTexRefGetMipmapLevelClamp.....	387
cuTexRefGetMipmappedArray.....	387
cuTexRefSetAddress.....	388
cuTexRefSetAddress2D.....	389
cuTexRefSetAddressMode.....	390
cuTexRefSetArray.....	391
cuTexRefSetBorderColor.....	392
cuTexRefSetFilterMode.....	393
cuTexRefSetFlags.....	394
cuTexRefSetFormat.....	395
cuTexRefSetMaxAnisotropy.....	395
cuTexRefSetMipmapFilterMode.....	396
cuTexRefSetMipmapLevelBias.....	397
cuTexRefSetMipmapLevelClamp.....	398
cuTexRefSetMipmappedArray.....	399
6.24. Surface Reference Management [DEPRECATED].....	399
cuSurfRefGetArray.....	400
cuSurfRefSetArray.....	400
6.25. Texture Object Management.....	401
cuTexObjectCreate.....	401
cuTexObjectDestroy.....	406
cuTexObjectGetResourceDesc.....	406
cuTexObjectGetResourceViewDesc.....	407
cuTexObjectGetTextureDesc.....	407
6.26. Surface Object Management.....	408
cuSurfObjectCreate.....	408
cuSurfObjectDestroy.....	409
cuSurfObjectGetResourceDesc.....	409

6.27. Peer Context Memory Access.....	410
cuCtxDisablePeerAccess.....	410
cuCtxEnablePeerAccess.....	411
cuDeviceCanAccessPeer.....	412
cuDeviceGetP2PAttribute.....	413
6.28. Graphics Interoperability.....	414
cuGraphicsMapResources.....	414
cuGraphicsResourceGetMappedMipmappedArray.....	415
cuGraphicsResourceGetMappedPointer.....	416
cuGraphicsResourceSetMapFlags.....	417
cuGraphicsSubResourceGetMappedArray.....	418
cuGraphicsUnmapResources.....	419
cuGraphicsUnregisterResource.....	420
6.29. Driver Entry Point Access.....	420
cuGetProcAddress.....	421
6.30. Profiler Control [DEPRECATED].....	422
cuProfilerInitialize.....	422
6.31. Profiler Control.....	423
cuProfilerStart.....	423
cuProfilerStop.....	424
6.32. OpenGL Interoperability.....	424
OpenGL Interoperability [DEPRECATED].....	424
CUGLDeviceList.....	424
cuGLGetDevices.....	425
cuGraphicsGLRegisterBuffer.....	426
cuGraphicsGLRegisterImage.....	427
cuWGLGetDevice.....	429
6.32.1. OpenGL Interoperability [DEPRECATED].....	429
CUGLmap_flags.....	429
cuGLCtxCreate.....	430
cuGLInit.....	430
cuGLMapBufferObject.....	431
cuGLMapBufferObjectAsync.....	432
cuGLRegisterBufferObject.....	433
cuGLSetBufferObjectMapFlags.....	433
cuGLUnmapBufferObject.....	434
cuGLUnmapBufferObjectAsync.....	435
cuGLUnregisterBufferObject.....	436

6.33. VDPAU Interoperability.....	437
cuGraphicsVDPAURegisterOutputSurface.....	437
cuGraphicsVDPAURegisterVideoSurface.....	438
cuVDPAUCtxCreate.....	439
cuVDPAUGetDevice.....	440
6.34. EGL Interoperability.....	441
cuEGLStreamConsumerAcquireFrame.....	441
cuEGLStreamConsumerConnect.....	442
cuEGLStreamConsumerConnectWithFlags.....	443
cuEGLStreamConsumerDisconnect.....	443
cuEGLStreamConsumerReleaseFrame.....	444
cuEGLStreamProducerConnect.....	445
cuEGLStreamProducerDisconnect.....	445
cuEGLStreamProducerPresentFrame.....	446
cuEGLStreamProducerReturnFrame.....	447
cuEventCreateFromEGLSync.....	448
cuGraphicsEGLRegisterImage.....	449
cuGraphicsResourceGetMappedEglFrame.....	450
Chapter 7. Data Structures.....	452
CUaccessPolicyWindow_v1.....	453
base_ptr.....	453
hitProp.....	453
hitRatio.....	453
missProp.....	453
num_bytes.....	453
CUarrayMapInfo_v1.....	454
deviceBitMask.....	454
extentDepth.....	454
extentHeight.....	454
extentWidth.....	454
flags.....	454
layer.....	454
level.....	454
memHandleType.....	454
memOperationType.....	454
offset.....	455
offsetX.....	455
offsetY.....	455

offsetZ.....	455
reserved.....	455
resourceType.....	455
size.....	455
subresourceType.....	455
CUDA_ARRAY3D_DESCRIPTOR_v2.....	455
Depth.....	456
Flags.....	456
Format.....	456
Height.....	456
NumChannels.....	456
Width.....	456
CUDA_ARRAY_DESCRIPTOR_v2.....	456
Format.....	456
Height.....	457
NumChannels.....	457
Width.....	457
CUDA_ARRAY_SPARSE_PROPERTIES_v1.....	457
depth.....	457
flags.....	457
height.....	457
miptailFirstLevel.....	457
miptailSize.....	458
width.....	458
CUDA_EXT_SEM_SIGNAL_NODE_PARAMS_v1.....	458
extSemArray.....	458
numExtSems.....	458
paramsArray.....	458
CUDA_EXT_SEM_WAIT_NODE_PARAMS_v1.....	458
extSemArray.....	459
numExtSems.....	459
paramsArray.....	459
CUDA_EXTERNAL_MEMORY_BUFFER_DESC_v1.....	459
flags.....	459
offset.....	459
size.....	459
CUDA_EXTERNAL_MEMORY_HANDLE_DESC_v1.....	460
fd.....	460

flags.....	460
handle.....	460
name.....	460
nvSciBufObject.....	460
size.....	460
type.....	461
win32.....	461
CUDA_EXTERNAL_MEMORY_MIPMAPPED_ARRAY_DESC_v1.....	461
arrayDesc.....	461
numLevels.....	461
offset.....	462
CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC_v1.....	462
fd.....	462
flags.....	462
handle.....	462
name.....	462
nvSciSyncObj.....	462
type.....	463
win32.....	463
CUDA_EXTERNAL_SEMAPHORE_SIGNAL_PARAMS_v1.....	463
fence.....	463
fence.....	463
flags.....	464
key.....	464
keyedMutex.....	464
value.....	464
CUDA_EXTERNAL_SEMAPHORE_WAIT_PARAMS_v1.....	464
fence.....	464
flags.....	465
key.....	465
keyedMutex.....	465
nvSciSync.....	465
timeoutMs.....	465
value.....	465
CUDA_HOST_NODE_PARAMS_v1.....	466
fn.....	466
userData.....	466
CUDA_KERNEL_NODE_PARAMS_v1.....	466

blockDimX.....	466
blockDimY.....	466
blockDimZ.....	466
extra.....	466
func.....	467
gridDimX.....	467
gridDimY.....	467
gridDimZ.....	467
kernelParams.....	467
sharedMemBytes.....	467
CUDA_LAUNCH_PARAMS_v1.....	467
blockDimX.....	467
blockDimY.....	468
blockDimZ.....	468
function.....	468
gridDimX.....	468
gridDimY.....	468
gridDimZ.....	468
hStream.....	468
kernelParams.....	468
sharedMemBytes.....	468
CUDA_MEMCPY2D_v2.....	469
dstArray.....	469
dstDevice.....	469
dstHost.....	469
dstMemoryType.....	469
dstPitch.....	469
dstXInBytes.....	469
dstY.....	469
Height.....	469
srcArray.....	469
srcDevice.....	470
srcHost.....	470
srcMemoryType.....	470
srcPitch.....	470
srcXInBytes.....	470
srcY.....	470
WidthInBytes.....	470

CUDA_MEMCPY3D_PEER_v1.....	470
Depth.....	470
dstArray.....	470
dstContext.....	471
dstDevice.....	471
dstHeight.....	471
dstHost.....	471
dstLOD.....	471
dstMemoryType.....	471
dstPitch.....	471
dstXInBytes.....	471
dstY.....	471
dstZ.....	471
Height.....	472
srcArray.....	472
srcContext.....	472
srcDevice.....	472
srcHeight.....	472
srcHost.....	472
srcLOD.....	472
srcMemoryType.....	472
srcPitch.....	472
srcXInBytes.....	472
srcY.....	473
srcZ.....	473
WidthInBytes.....	473
CUDA_MEMCPY3D_v2.....	473
Depth.....	473
dstArray.....	473
dstDevice.....	473
dstHeight.....	473
dstHost.....	473
dstLOD.....	473
dstMemoryType.....	474
dstPitch.....	474
dstXInBytes.....	474
dstY.....	474
dstZ.....	474

Height.....	474
reserved0.....	474
reserved1.....	474
srcArray.....	474
srcDevice.....	474
srcHeight.....	475
srcHost.....	475
srcLOD.....	475
srcMemoryType.....	475
srcPitch.....	475
srcXInBytes.....	475
srcY.....	475
srcZ.....	475
WidthInBytes.....	475
CUDA_MEMSET_NODE_PARAMS_v1.....	475
dst.....	476
elementSize.....	476
height.....	476
pitch.....	476
value.....	476
width.....	476
CUDA_POINTER_ATTRIBUTE_P2P_TOKENS_v1.....	476
CUDA_RESOURCE_DESC_v1.....	476
devPtr.....	477
flags.....	477
format.....	477
hArray.....	477
height.....	477
hMipmappedArray.....	477
numChannels.....	477
pitchInBytes.....	477
resType.....	477
sizeInBytes.....	477
width.....	478
CUDA_RESOURCE_VIEW_DESC_v1.....	478
depth.....	478
firstLayer.....	478
firstMipmapLevel.....	478

format.....	478
height.....	478
lastLayer.....	478
lastMipmapLevel.....	479
width.....	479
CUDA_TEXTURE_DESC_v1.....	479
addressMode.....	479
borderColor.....	479
filterMode.....	479
flags.....	479
maxAnisotropy.....	479
maxMipmapLevelClamp.....	480
minMipmapLevelClamp.....	480
mipmapFilterMode.....	480
mipmapLevelBias.....	480
CUdevprop_v1.....	480
clockRate.....	480
maxGridSize.....	480
maxThreadsDim.....	480
maxThreadsPerBlock.....	480
memPitch.....	481
regsPerBlock.....	481
sharedMemPerBlock.....	481
SIMDWidth.....	481
textureAlign.....	481
totalConstantMemory.....	481
CUeglFrame_v1.....	481
cuFormat.....	481
depth.....	481
eglColorFormat.....	481
frameType.....	482
height.....	482
numChannels.....	482
pArray.....	482
pitch.....	482
planeCount.....	482
pPitch.....	482
width.....	482

CUipcEventHandle_v1.....	482
CUipcMemHandle_v1.....	483
CUkernelNodeAttrValue_v1.....	483
accessPolicyWindow.....	483
cooperative.....	483
CUmemAccessDesc_v1.....	483
flags.....	483
location.....	483
CUmemAllocationProp_v1.....	484
compressionType.....	484
location.....	484
requestedHandleTypes.....	484
type.....	484
usage.....	484
win32HandleMetaData.....	485
CUmemLocation_v1.....	485
id.....	485
type.....	485
CUmemPoolProps_v1.....	485
allocType.....	485
handleTypes.....	485
location.....	486
reserved.....	486
win32SecurityAttributes.....	486
CUmemPoolPtrExportData_v1.....	486
CUstreamAttrValue_v1.....	486
accessPolicyWindow.....	486
syncPolicy.....	486
CUstreamBatchMemOpParams_v1.....	487
Chapter 8. Data Fields.....	488
Chapter 9. Deprecated List.....	499

Chapter 1. Difference between the driver and runtime APIs

The driver and runtime APIs are very similar and can for the most part be used interchangeably. However, there are some key differences worth noting between the two.

Complexity vs. control

The runtime API eases device code management by providing implicit initialization, context management, and module management. This leads to simpler code, but it also lacks the level of control that the driver API has.

In comparison, the driver API offers more fine-grained control, especially over contexts and module loading. Kernel launches are much more complex to implement, as the execution configuration and kernel parameters must be specified with explicit function calls. However, unlike the runtime, where all the kernels are automatically loaded during initialization and stay loaded for as long as the program runs, with the driver API it is possible to only keep the modules that are currently needed loaded, or even dynamically reload modules. The driver API is also language-independent as it only deals with cubin objects.

Context management

Context management can be done through the driver API, but is not exposed in the runtime API. Instead, the runtime API decides itself which context to use for a thread: if a context has been made current to the calling thread through the driver API, the runtime will use that, but if there is no such context, it uses a "primary context." Primary contexts are created as needed, one per device per process, are reference-counted, and are then destroyed when there are no more references to them. Within one process, all users of the runtime API will share the primary context, unless a context has been made current to each thread. The context that the runtime uses, i.e, either the current context or primary context, can be synchronized with `cudaDeviceSynchronize()`, and destroyed with `cudaDeviceReset()`.

Using the runtime API with primary contexts has its tradeoffs, however. It can cause trouble for users writing plug-ins for larger software packages, for example, because if all plug-ins run in the same process, they will all share a context but will likely have no way to communicate with each other. So, if one of them calls `cudaDeviceReset()` after finishing all its CUDA work, the other plug-ins will fail because the context they were using was destroyed

without their knowledge. To avoid this issue, CUDA clients can use the driver API to create and set the current context, and then use the runtime API to work with it. However, contexts may consume significant resources, such as device memory, extra host threads, and performance costs of context switching on the device. This runtime-driver context sharing is important when using the driver API in conjunction with libraries built on the runtime API, such as cuBLAS or cuFFT.

Chapter 2. API synchronization behavior

The API provides memcopy/memset functions in both synchronous and asynchronous forms, the latter having an "Async" suffix. This is a misnomer as each function may exhibit synchronous or asynchronous behavior depending on the arguments passed to the function.

Memcopy

In the reference documentation, each memcopy function is categorized as synchronous or asynchronous, corresponding to the definitions below.

Synchronous

1. All transfers involving Unified Memory regions are fully synchronous with respect to the host.
2. For transfers from pageable host memory to device memory, a stream sync is performed before the copy is initiated. The function will return once the pageable buffer has been copied to the staging memory for DMA transfer to device memory, but the DMA to final destination may not have completed.
3. For transfers from pinned host memory to device memory, the function is synchronous with respect to the host.
4. For transfers from device to either pageable or pinned host memory, the function returns only once the copy has completed.
5. For transfers from device memory to device memory, no host-side synchronization is performed.
6. For transfers from any host memory to any host memory, the function is fully synchronous with respect to the host.

Asynchronous

1. For transfers from device memory to pageable host memory, the function will return only once the copy has completed.
2. For transfers from any host memory to any host memory, the function is fully synchronous with respect to the host.

3. For all other transfers, the function is fully asynchronous. If pageable memory must first be staged to pinned memory, this will be handled asynchronously with a worker thread.

Memset

The synchronous memset functions are asynchronous with respect to the host except when the target is pinned host memory or a Unified Memory region, in which case they are fully synchronous. The Async versions are always asynchronous with respect to the host.

Kernel Launches

Kernel launches are asynchronous with respect to the host. Details of concurrent kernel execution and data transfers can be found in the CUDA Programmers Guide.

Chapter 3. Stream synchronization behavior

Default stream

The default stream, used when 0 is passed as a `cudaStream_t` or by APIs that operate on a stream implicitly, can be configured to have either [legacy](#) or [per-thread](#) synchronization behavior as described below.

The behavior can be controlled per compilation unit with the `--default-stream` `nvcc` option. Alternatively, per-thread behavior can be enabled by defining the `CUDA_API_PER_THREAD_DEFAULT_STREAM` macro before including any CUDA headers. Either way, the `CUDA_API_PER_THREAD_DEFAULT_STREAM` macro will be defined in compilation units using per-thread synchronization behavior.

Legacy default stream

The legacy default stream is an implicit stream which synchronizes with all other streams in the same `CUcontext` except for non-blocking streams, described below. (For applications using the runtime APIs only, there will be one context per device.) When an action is taken in the legacy stream such as a kernel launch or `cudaStreamWaitEvent()`, the legacy stream first waits on all blocking streams, the action is queued in the legacy stream, and then all blocking streams wait on the legacy stream.

For example, the following code launches a kernel `k_1` in stream `s`, then `k_2` in the legacy stream, then `k_3` in stream `s`:

```
k_1<<<1, 1, 0, s>>>();  
k_2<<<1, 1>>>();  
k_3<<<1, 1, 0, s>>>();
```

The resulting behavior is that `k_2` will block on `k_1` and `k_3` will block on `k_2`.

Non-blocking streams which do not synchronize with the legacy stream can be created using the `cudaStreamNonBlocking` flag with the stream creation APIs.

The legacy default stream can be used explicitly with the `CUstream(cudaStream_t)` handle `CU_STREAM_LEGACY(cudaStreamLegacy)`.

Per-thread default stream

The per-thread default stream is an implicit stream local to both the thread and the `CUcontext`, and which does not synchronize with other streams (just like explicitly created streams). The per-thread default stream is not a non-blocking stream and will synchronize with the legacy default stream if both are used in a program.

The per-thread default stream can be used explicitly with the `CUstream` (`cudaStream_t`) handle `CU_STREAM_PER_THREAD` (`cudaStreamPerThread`).

Chapter 4. Graph object thread safety

Graph objects (`cudaGraph_t`, `CUgraph`) are not internally synchronized and must not be accessed concurrently from multiple threads. API calls accessing the same graph object must be serialized externally.

Note that **this includes APIs which may appear to be read-only**, such as `cudaGraphClone()` (`cuGraphClone()`) and `cudaGraphInstantiate()` (`cuGraphInstantiate()`). No API or pair of APIs is guaranteed to be safe to call on the same graph object from two different threads without serialization.

Chapter 5. Rules for version mixing

1. Starting with CUDA 11.0, the ABI version for the CUDA runtime is bumped every major release. CUDA-defined types, whether opaque handles or structures like `cudaDeviceProp`, have their ABI tied to the major release of the CUDA runtime. It is unsafe to pass them from function A to function B if those functions have been compiled with different major versions of the toolkit and linked together into the same device executable.
2. The CUDA Driver API has a per-function ABI denoted with a `_v*` extension. CUDA-defined types (e.g structs) should not be passed across different ABI versions. For example, an application calling `cuMemcpy2D_v2(const CUDA_MEMCPY2D_v2 *pCopy)` and using the older version of the struct `CUDA_MEMCPY2D_v1` instead of `CUDA_MEMCPY2D_v2`.
3. Users should not arbitrarily mix different API versions during the lifetime of a resource. These resources include IPC handles, memory, streams, contexts, events, etc. For example, a user who wants to allocate CUDA memory using `cuMemAlloc_v2` should free the memory using `cuMemFree_v2` and not `cuMemFree`.

Chapter 6. Modules

Here is a list of all modules:

- ▶ [Data types used by CUDA driver](#)
- ▶ [Error Handling](#)
- ▶ [Initialization](#)
- ▶ [Version Management](#)
- ▶ [Device Management](#)
- ▶ [Device Management \[DEPRECATED\]](#)
- ▶ [Primary Context Management](#)
- ▶ [Context Management](#)
- ▶ [Context Management \[DEPRECATED\]](#)
- ▶ [Module Management](#)
- ▶ [Memory Management](#)
- ▶ [Virtual Memory Management](#)
- ▶ [Stream Ordered Memory Allocator](#)
- ▶ [Unified Addressing](#)
- ▶ [Stream Management](#)
- ▶ [Event Management](#)
- ▶ [External Resource Interoperability](#)
- ▶ [Stream memory operations](#)
- ▶ [Execution Control](#)
- ▶ [Execution Control \[DEPRECATED\]](#)
- ▶ [Graph Management](#)
- ▶ [Occupancy](#)
- ▶ [Texture Reference Management \[DEPRECATED\]](#)
- ▶ [Surface Reference Management \[DEPRECATED\]](#)
- ▶ [Texture Object Management](#)
- ▶ [Surface Object Management](#)

- ▶ [Peer Context Memory Access](#)
- ▶ [Graphics Interoperability](#)
- ▶ [Driver Entry Point Access](#)
- ▶ [Profiler Control \[DEPRECATED\]](#)
- ▶ [Profiler Control](#)
- ▶ [OpenGL Interoperability](#)
 - ▶ [OpenGL Interoperability \[DEPRECATED\]](#)
- ▶ [VDPAU Interoperability](#)
- ▶ [EGL Interoperability](#)

6.1. Data types used by CUDA driver

```
struct CUaccessPolicyWindow_v1
struct CUarrayMapInfo_v1
struct CUDA_ARRAY3D_DESCRIPTOR_v2
struct CUDA_ARRAY_DESCRIPTOR_v2
struct CUDA_ARRAY_SPARSE_PROPERTIES_v1
struct CUDA_EXT_SEM_SIGNAL_NODE_PARAMS_v1
struct CUDA_EXT_SEM_WAIT_NODE_PARAMS_v1
struct
CUDA_EXTERNAL_MEMORY_BUFFER_DESC_v1
struct
CUDA_EXTERNAL_MEMORY_HANDLE_DESC_v1
struct
CUDA_EXTERNAL_MEMORY_MIPMAPPED_ARRAY_DESC_v1
struct
CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC_v1
struct
CUDA_EXTERNAL_SEMAPHORE_SIGNAL_PARAMS_v1
struct
CUDA_EXTERNAL_SEMAPHORE_WAIT_PARAMS_v1
```

```
struct CUDA_HOST_NODE_PARAMS_v1
struct CUDA_KERNEL_NODE_PARAMS_v1
struct CUDA_LAUNCH_PARAMS_v1
struct CUDA_MEMCPY2D_v2
struct CUDA_MEMCPY3D_PEER_v1
struct CUDA_MEMCPY3D_v2
struct CUDA_MEMSET_NODE_PARAMS_v1
struct CUDA_POINTER_ATTRIBUTE_P2P_TOKENS_v1
struct CUDA_RESOURCE_DESC_v1
struct CUDA_RESOURCE_VIEW_DESC_v1
struct CUDA_TEXTURE_DESC_v1
struct CUdevprop_v1
struct CUeglFrame_v1
struct CUipcEventHandle_v1
struct CUipcMemHandle_v1
union CUkernelNodeAttrValue_v1
struct CUmemAccessDesc_v1
```

struct CUmemAllocationProp_v1

struct CUmemLocation_v1

struct CUmemPoolProps_v1

struct CUmemPoolPtrExportData_v1

union CUstreamAttrValue_v1

union CUstreamBatchMemOpParams_v1

enum CUaccessProperty

Specifies performance hint with CUaccessPolicyWindow for hitProp and missProp members.

Values

CU_ACCESS_PROPERTY_NORMAL = 0

Normal cache persistence.

CU_ACCESS_PROPERTY_STREAMING = 1

Streaming access is less likely to persist from cache.

CU_ACCESS_PROPERTY_PERSISTING = 2

Persisting access is more likely to persist in cache.

enum CUaddress_mode

Texture reference addressing modes

Values

CU_TR_ADDRESS_MODE_WRAP = 0

Wrapping address mode

CU_TR_ADDRESS_MODE_CLAMP = 1

Clamp to edge address mode

CU_TR_ADDRESS_MODE_MIRROR = 2

Mirror address mode

CU_TR_ADDRESS_MODE_BORDER = 3

Border address mode

enum CUarray_cubemap_face

Array indices for cube faces

Values

CU_CUBEMAP_FACE_POSITIVE_X = 0x00

Positive X face of cubemap

CU_CUBEMAP_FACE_NEGATIVE_X = 0x01

Negative X face of cubemap

CU_CUBEMAP_FACE_POSITIVE_Y = 0x02

Positive Y face of cubemap

CU_CUBEMAP_FACE_NEGATIVE_Y = 0x03

Negative Y face of cubemap

CU_CUBEMAP_FACE_POSITIVE_Z = 0x04

Positive Z face of cubemap

CU_CUBEMAP_FACE_NEGATIVE_Z = 0x05

Negative Z face of cubemap

enum CUarray_format

Array formats

Values

CU_AD_FORMAT_UNSIGNED_INT8 = 0x01

Unsigned 8-bit integers

CU_AD_FORMAT_UNSIGNED_INT16 = 0x02

Unsigned 16-bit integers

CU_AD_FORMAT_UNSIGNED_INT32 = 0x03

Unsigned 32-bit integers

CU_AD_FORMAT_SIGNED_INT8 = 0x08

Signed 8-bit integers

CU_AD_FORMAT_SIGNED_INT16 = 0x09

Signed 16-bit integers

CU_AD_FORMAT_SIGNED_INT32 = 0x0a

Signed 32-bit integers

CU_AD_FORMAT_HALF = 0x10

16-bit floating point

CU_AD_FORMAT_FLOAT = 0x20

32-bit floating point

CU_AD_FORMAT_NV12 = 0xb0

8-bit YUV planar format, with 4:2:0 sampling

enum CUarraySparseSubresourceType

Sparse subresource types

Values

CU_ARRAY_SPARSE_SUBRESOURCE_TYPE_SPARSE_LEVEL = 0

CU_ARRAY_SPARSE_SUBRESOURCE_TYPE_MIPTAIL = 1

enum CUcomputemode

Compute Modes

Values

CU_COMPUTEMODE_DEFAULT = 0

Default compute mode (Multiple contexts allowed per device)

CU_COMPUTEMODE_PROHIBITED = 2

Compute-prohibited mode (No contexts can be created on this device at this time)

CU_COMPUTEMODE_EXCLUSIVE_PROCESS = 3

Compute-exclusive-process mode (Only one context used by a single process can be present on this device at a time)

enum CUctx_flags

Context creation flags

Values

CU_CTX_SCHED_AUTO = 0x00

Automatic scheduling

CU_CTX_SCHED_SPIN = 0x01

Set spin as default scheduling

CU_CTX_SCHED_YIELD = 0x02

Set yield as default scheduling

CU_CTX_SCHED_BLOCKING_SYNC = 0x04

Set blocking synchronization as default scheduling

CU_CTX_BLOCKING_SYNC = 0x04

Set blocking synchronization as default scheduling [Deprecated](#) This flag was deprecated as of CUDA 4.0 and was replaced with [CU_CTX_SCHED_BLOCKING_SYNC](#).

CU_CTX_SCHED_MASK = 0x07

CU_CTX_MAP_HOST = 0x08

[Deprecated](#) This flag was deprecated as of CUDA 11.0 and it no longer has any effect. All contexts as of CUDA 3.2 behave as though the flag is enabled.

CU_CTX_LMEM_RESIZE_TO_MAX = 0x10

Keep local memory allocation after launch

CU_CTX_FLAGS_MASK = 0x1f

enum CUDA_POINTER_ATTRIBUTE_ACCESS_FLAGS

Access flags that specify the level of access the current context's device has on the memory referenced.

Values

CU_POINTER_ATTRIBUTE_ACCESS_FLAG_NONE = 0x0

No access, meaning the device cannot access this memory at all, thus must be staged through accessible memory in order to complete certain operations

CU_POINTER_ATTRIBUTE_ACCESS_FLAG_READ = 0x1

Read-only access, meaning writes to this memory are considered invalid accesses and thus return error in that case.

CU_POINTER_ATTRIBUTE_ACCESS_FLAG_READWRITE = 0x3

Read-write access, the device has full read-write access to the memory

enum CUdevice_attribute

Device properties

Values

CU_DEVICE_ATTRIBUTE_MAX_THREADS_PER_BLOCK = 1

Maximum number of threads per block

CU_DEVICE_ATTRIBUTE_MAX_BLOCK_DIM_X = 2

Maximum block dimension X

CU_DEVICE_ATTRIBUTE_MAX_BLOCK_DIM_Y = 3

Maximum block dimension Y

CU_DEVICE_ATTRIBUTE_MAX_BLOCK_DIM_Z = 4

Maximum block dimension Z

CU_DEVICE_ATTRIBUTE_MAX_GRID_DIM_X = 5

Maximum grid dimension X

CU_DEVICE_ATTRIBUTE_MAX_GRID_DIM_Y = 6

Maximum grid dimension Y

CU_DEVICE_ATTRIBUTE_MAX_GRID_DIM_Z = 7

Maximum grid dimension Z

CU_DEVICE_ATTRIBUTE_MAX_SHARED_MEMORY_PER_BLOCK = 8

Maximum shared memory available per block in bytes

CU_DEVICE_ATTRIBUTE_SHARED_MEMORY_PER_BLOCK = 8

Deprecated, use CU_DEVICE_ATTRIBUTE_MAX_SHARED_MEMORY_PER_BLOCK

CU_DEVICE_ATTRIBUTE_TOTAL_CONSTANT_MEMORY = 9

Memory available on device for `__constant__` variables in a CUDA C kernel in bytes

CU_DEVICE_ATTRIBUTE_WARP_SIZE = 10

Warp size in threads

CU_DEVICE_ATTRIBUTE_MAX_PITCH = 11

Maximum pitch in bytes allowed by memory copies

CU_DEVICE_ATTRIBUTE_MAX_REGISTERS_PER_BLOCK = 12

Maximum number of 32-bit registers available per block

CU_DEVICE_ATTRIBUTE_REGISTERS_PER_BLOCK = 12

Deprecated, use CU_DEVICE_ATTRIBUTE_MAX_REGISTERS_PER_BLOCK

CU_DEVICE_ATTRIBUTE_CLOCK_RATE = 13

Typical clock frequency in kilohertz

CU_DEVICE_ATTRIBUTE_TEXTURE_ALIGNMENT = 14

Alignment requirement for textures

CU_DEVICE_ATTRIBUTE_GPU_OVERLAP = 15

Device can possibly copy memory and execute a kernel concurrently. Deprecated. Use instead CU_DEVICE_ATTRIBUTE_ASYNC_ENGINE_COUNT.

CU_DEVICE_ATTRIBUTE_MULTIPROCESSOR_COUNT = 16

Number of multiprocessors on device

CU_DEVICE_ATTRIBUTE_KERNEL_EXEC_TIMEOUT = 17

Specifies whether there is a run time limit on kernels

CU_DEVICE_ATTRIBUTE_INTEGRATED = 18

Device is integrated with host memory

CU_DEVICE_ATTRIBUTE_CAN_MAP_HOST_MEMORY = 19

Device can map host memory into CUDA address space

CU_DEVICE_ATTRIBUTE_COMPUTE_MODE = 20Compute mode (See [CUcomputemode](#) for details)**CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE1D_WIDTH = 21**

Maximum 1D texture width

CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_WIDTH = 22

Maximum 2D texture width

CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_HEIGHT = 23

Maximum 2D texture height

CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE3D_WIDTH = 24

Maximum 3D texture width

CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE3D_HEIGHT = 25

Maximum 3D texture height

CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE3D_DEPTH = 26

Maximum 3D texture depth

CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_LAYERED_WIDTH = 27

Maximum 2D layered texture width

CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_LAYERED_HEIGHT = 28

Maximum 2D layered texture height

CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_LAYERED_LAYERS = 29

Maximum layers in a 2D layered texture

CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_ARRAY_WIDTH = 27

Deprecated, use CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_LAYERED_WIDTH

CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_ARRAY_HEIGHT = 28

Deprecated, use CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_LAYERED_HEIGHT

CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_ARRAY_NUMSLICES = 29

Deprecated, use CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_LAYERED_LAYERS

CU_DEVICE_ATTRIBUTE_SURFACE_ALIGNMENT = 30

Alignment requirement for surfaces

CU_DEVICE_ATTRIBUTE_CONCURRENT_KERNELS = 31

Device can possibly execute multiple kernels concurrently

CU_DEVICE_ATTRIBUTE_ECC_ENABLED = 32

Device has ECC support enabled

CU_DEVICE_ATTRIBUTE_PCI_BUS_ID = 33

PCI bus ID of the device

CU_DEVICE_ATTRIBUTE_PCI_DEVICE_ID = 34

PCI device ID of the device

CU_DEVICE_ATTRIBUTE_TCC_DRIVER = 35

Device is using TCC driver model

CU_DEVICE_ATTRIBUTE_MEMORY_CLOCK_RATE = 36

Peak memory clock frequency in kilohertz

CU_DEVICE_ATTRIBUTE_GLOBAL_MEMORY_BUS_WIDTH = 37

Global memory bus width in bits

CU_DEVICE_ATTRIBUTE_L2_CACHE_SIZE = 38

Size of L2 cache in bytes

CU_DEVICE_ATTRIBUTE_MAX_THREADS_PER_MULTIPROCESSOR = 39

Maximum resident threads per multiprocessor

CU_DEVICE_ATTRIBUTE_ASYNC_ENGINE_COUNT = 40

Number of asynchronous engines

CU_DEVICE_ATTRIBUTE_UNIFIED_ADDRESSING = 41

Device shares a unified address space with the host

CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE1D_LAYERED_WIDTH = 42

Maximum 1D layered texture width

CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE1D_LAYERED_LAYERS = 43

Maximum layers in a 1D layered texture

CU_DEVICE_ATTRIBUTE_CAN_TEX2D_GATHER = 44

Deprecated, do not use.

CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_GATHER_WIDTH = 45

Maximum 2D texture width if CUDA_ARRAY3D_TEXTURE_GATHER is set

CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_GATHER_HEIGHT = 46

Maximum 2D texture height if CUDA_ARRAY3D_TEXTURE_GATHER is set

CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE3D_WIDTH_ALTERNATE = 47

Alternate maximum 3D texture width

CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE3D_HEIGHT_ALTERNATE = 48

Alternate maximum 3D texture height

CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE3D_DEPTH_ALTERNATE = 49

Alternate maximum 3D texture depth

CU_DEVICE_ATTRIBUTE_PCI_DOMAIN_ID = 50

PCI domain ID of the device

CU_DEVICE_ATTRIBUTE_TEXTURE_PITCH_ALIGNMENT = 51

Pitch alignment requirement for textures

CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURECUBEMAP_WIDTH = 52

Maximum cubemap texture width/height

CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURECUBEMAP_LAYERED_WIDTH = 53

Maximum cubemap layered texture width/height

CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURECUBEMAP_LAYERED_LAYERS = 54

Maximum layers in a cubemap layered texture

CU_DEVICE_ATTRIBUTE_MAXIMUM_SURFACE1D_WIDTH = 55

Maximum 1D surface width

CU_DEVICE_ATTRIBUTE_MAXIMUM_SURFACE2D_WIDTH = 56

Maximum 2D surface width

CU_DEVICE_ATTRIBUTE_MAXIMUM_SURFACE2D_HEIGHT = 57

Maximum 2D surface height

CU_DEVICE_ATTRIBUTE_MAXIMUM_SURFACE3D_WIDTH = 58

Maximum 3D surface width

CU_DEVICE_ATTRIBUTE_MAXIMUM_SURFACE3D_HEIGHT = 59

Maximum 3D surface height

CU_DEVICE_ATTRIBUTE_MAXIMUM_SURFACE3D_DEPTH = 60

Maximum 3D surface depth

CU_DEVICE_ATTRIBUTE_MAXIMUM_SURFACE1D_LAYERED_WIDTH = 61

Maximum 1D layered surface width

CU_DEVICE_ATTRIBUTE_MAXIMUM_SURFACE1D_LAYERED_LAYERS = 62

Maximum layers in a 1D layered surface

CU_DEVICE_ATTRIBUTE_MAXIMUM_SURFACE2D_LAYERED_WIDTH = 63

Maximum 2D layered surface width

CU_DEVICE_ATTRIBUTE_MAXIMUM_SURFACE2D_LAYERED_HEIGHT = 64

Maximum 2D layered surface height

CU_DEVICE_ATTRIBUTE_MAXIMUM_SURFACE2D_LAYERED_LAYERS = 65

Maximum layers in a 2D layered surface

CU_DEVICE_ATTRIBUTE_MAXIMUM_SURFACECUBEMAP_WIDTH = 66

Maximum cubemap surface width

CU_DEVICE_ATTRIBUTE_MAXIMUM_SURFACECUBEMAP_LAYERED_WIDTH = 67

Maximum cubemap layered surface width

CU_DEVICE_ATTRIBUTE_MAXIMUM_SURFACECUBEMAP_LAYERED_LAYERS = 68

Maximum layers in a cubemap layered surface

CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE1D_LINEAR_WIDTH = 69

Deprecated, do not use. Use [cudaDeviceGetTexture1DLinearMaxWidth\(\)](#) or [cuDeviceGetTexture1DLinearMaxWidth\(\)](#) instead.

CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_LINEAR_WIDTH = 70

Maximum 2D linear texture width

CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_LINEAR_HEIGHT = 71

Maximum 2D linear texture height

CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_LINEAR_PITCH = 72

Maximum 2D linear texture pitch in bytes

CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_MIPMAPPED_WIDTH = 73

Maximum mipmapped 2D texture width

CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_MIPMAPPED_HEIGHT = 74

Maximum mipmapped 2D texture height

CU_DEVICE_ATTRIBUTE_COMPUTE_CAPABILITY_MAJOR = 75

Major compute capability version number

CU_DEVICE_ATTRIBUTE_COMPUTE_CAPABILITY_MINOR = 76

Minor compute capability version number

CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE1D_MIPMAPPED_WIDTH = 77

Maximum mipmapped 1D texture width

CU_DEVICE_ATTRIBUTE_STREAM_PRIORITIES_SUPPORTED = 78

Device supports stream priorities

CU_DEVICE_ATTRIBUTE_GLOBAL_L1_CACHE_SUPPORTED = 79

Device supports caching globals in L1

CU_DEVICE_ATTRIBUTE_LOCAL_L1_CACHE_SUPPORTED = 80

Device supports caching locals in L1

CU_DEVICE_ATTRIBUTE_MAX_SHARED_MEMORY_PER_MULTIPROCESSOR = 81

Maximum shared memory available per multiprocessor in bytes

CU_DEVICE_ATTRIBUTE_MAX_REGISTERS_PER_MULTIPROCESSOR = 82

Maximum number of 32-bit registers available per multiprocessor

CU_DEVICE_ATTRIBUTE_MANAGED_MEMORY = 83

Device can allocate managed memory on this system

CU_DEVICE_ATTRIBUTE_MULTI_GPU_BOARD = 84

Device is on a multi-GPU board

CU_DEVICE_ATTRIBUTE_MULTI_GPU_BOARD_GROUP_ID = 85

Unique id for a group of devices on the same multi-GPU board

CU_DEVICE_ATTRIBUTE_HOST_NATIVE_ATOMIC_SUPPORTED = 86

Link between the device and the host supports native atomic operations (this is a placeholder attribute, and is not supported on any current hardware)

CU_DEVICE_ATTRIBUTE_SINGLE_TO_DOUBLE_PRECISION_PERF_RATIO = 87

Ratio of single precision performance (in floating-point operations per second) to double precision performance

CU_DEVICE_ATTRIBUTE_PAGEABLE_MEMORY_ACCESS = 88

Device supports coherently accessing pageable memory without calling `cudaHostRegister` on it

CU_DEVICE_ATTRIBUTE_CONCURRENT_MANAGED_ACCESS = 89

Device can coherently access managed memory concurrently with the CPU

CU_DEVICE_ATTRIBUTE_COMPUTE_PREEMPTION_SUPPORTED = 90

Device supports compute preemption.

CU_DEVICE_ATTRIBUTE_CAN_USE_HOST_POINTER_FOR_REGISTERED_MEM = 91

Device can access host registered memory at the same virtual address as the CPU

CU_DEVICE_ATTRIBUTE_CAN_USE_STREAM_MEM_OPS = 92

[cuStreamBatchMemOp](#) and related APIs are supported.

CU_DEVICE_ATTRIBUTE_CAN_USE_64_BIT_STREAM_MEM_OPS = 93

64-bit operations are supported in [cuStreamBatchMemOp](#) and related APIs.

CU_DEVICE_ATTRIBUTE_CAN_USE_STREAM_WAIT_VALUE_NOR = 94

[CU_STREAM_WAIT_VALUE_NOR](#) is supported.

CU_DEVICE_ATTRIBUTE_COOPERATIVE_LAUNCH = 95

Device supports launching cooperative kernels via [cuLaunchCooperativeKernel](#)

CU_DEVICE_ATTRIBUTE_COOPERATIVE_MULTI_DEVICE_LAUNCH = 96

Deprecated, [cuLaunchCooperativeKernelMultiDevice](#) is deprecated.

CU_DEVICE_ATTRIBUTE_MAX_SHARED_MEMORY_PER_BLOCK_OPTIN = 97

Maximum optin shared memory per block

CU_DEVICE_ATTRIBUTE_CAN_FLUSH_REMOTE_WRITES = 98

The [CU_STREAM_WAIT_VALUE_FLUSH](#) flag and the

[CU_STREAM_MEM_OP_FLUSH_REMOTE_WRITES](#) MemOp are supported on the device.

See [Stream memory operations](#) for additional details.

CU_DEVICE_ATTRIBUTE_HOST_REGISTER_SUPPORTED = 99

Device supports host memory registration via [cudaHostRegister](#).

CU_DEVICE_ATTRIBUTE_PAGEABLE_MEMORY_ACCESS_USES_HOST_PAGE_TABLES = 100

Device accesses pageable memory via the host's page tables.

CU_DEVICE_ATTRIBUTE_DIRECT_MANAGED_MEM_ACCESS_FROM_HOST = 101

The host can directly access managed memory on the device without migration.

CU_DEVICE_ATTRIBUTE_VIRTUAL_ADDRESS_MANAGEMENT_SUPPORTED = 102

Deprecated, Use

[CU_DEVICE_ATTRIBUTE_VIRTUAL_MEMORY_MANAGEMENT_SUPPORTED](#)

CU_DEVICE_ATTRIBUTE_VIRTUAL_MEMORY_MANAGEMENT_SUPPORTED = 102

Device supports virtual memory management APIs like [cuMemAddressReserve](#),

[cuMemCreate](#), [cuMemMap](#) and related APIs

CU_DEVICE_ATTRIBUTE_HANDLE_TYPE_POSIX_FILE_DESCRIPTOR_SUPPORTED = 103

Device supports exporting memory to a posix file descriptor with

[cuMemExportToShareableHandle](#), if requested via [cuMemCreate](#)

CU_DEVICE_ATTRIBUTE_HANDLE_TYPE_WIN32_HANDLE_SUPPORTED = 104

Device supports exporting memory to a Win32 NT handle with

[cuMemExportToShareableHandle](#), if requested via [cuMemCreate](#)

CU_DEVICE_ATTRIBUTE_HANDLE_TYPE_WIN32_KMT_HANDLE_SUPPORTED = 105

Device supports exporting memory to a Win32 KMT handle with

[cuMemExportToShareableHandle](#), if requested [cuMemCreate](#)

CU_DEVICE_ATTRIBUTE_MAX_BLOCKS_PER_MULTIPROCESSOR = 106

Maximum number of blocks per multiprocessor

CU_DEVICE_ATTRIBUTE_GENERIC_COMPRESSION_SUPPORTED = 107

Device supports compression of memory

CU_DEVICE_ATTRIBUTE_MAX_PERSISTING_L2_CACHE_SIZE = 108

Maximum L2 persisting lines capacity setting in bytes.

CU_DEVICE_ATTRIBUTE_MAX_ACCESS_POLICY_WINDOW_SIZE = 109

Maximum value of [CUaccessPolicyWindow::num_bytes](#).

CU_DEVICE_ATTRIBUTE_GPU_DIRECT_RDMA_WITH_CUDA_VMM_SUPPORTED = 110

Device supports specifying the GPUDirect RDMA flag with [cuMemCreate](#)

CU_DEVICE_ATTRIBUTE_RESERVED_SHARED_MEMORY_PER_BLOCK = 111

Shared memory reserved by CUDA driver per block in bytes

CU_DEVICE_ATTRIBUTE_SPARSE_CUDA_ARRAY_SUPPORTED = 112

Device supports sparse CUDA arrays and sparse CUDA mipmapped arrays

CU_DEVICE_ATTRIBUTE_READ_ONLY_HOST_REGISTER_SUPPORTED = 113

Device supports using the [cuMemHostRegister](#) flag `CU_MEMHOSTREGISTER_READ_ONLY` to register memory that must be mapped as read-only to the GPU

CU_DEVICE_ATTRIBUTE_TIMELINE_SEMAPHORE_INTEROP_SUPPORTED = 114

External timeline semaphore interop is supported on the device

CU_DEVICE_ATTRIBUTE_MEMORY_POOLS_SUPPORTED = 115

Device supports using the [cuMemAllocAsync](#) and `cuMemPool` family of APIs

CU_DEVICE_ATTRIBUTE_GPU_DIRECT_RDMA_SUPPORTED = 116

Device supports GPUDirect RDMA APIs, like `nvidia_p2p_get_pages` (see <https://docs.nvidia.com/cuda/gpudirect-rdma> for more information)

CU_DEVICE_ATTRIBUTE_GPU_DIRECT_RDMA_FLUSH_WRITES_OPTIONS = 117

The returned attribute shall be interpreted as a bitmask, where the individual bits are described by the [CUflushGPUDirectRDMAWritesOptions](#) enum

CU_DEVICE_ATTRIBUTE_GPU_DIRECT_RDMA_WRITES_ORDERING = 118

GPUDirect RDMA writes to the device do not need to be flushed for consumers within the scope indicated by the returned attribute. See [CUGPUDirectRDMAWritesOrdering](#) for the numerical values returned here.

CU_DEVICE_ATTRIBUTE_MEMPOOL_SUPPORTED_HANDLE_TYPES = 119

Handle types supported with mempool based IPC

CU_DEVICE_ATTRIBUTE_MAX

enum CUdevice_P2PAttribute

P2P Attributes

Values

CU_DEVICE_P2P_ATTRIBUTE_PERFORMANCE_RANK = 0x01

A relative value indicating the performance of the link between two devices

CU_DEVICE_P2P_ATTRIBUTE_ACCESS_SUPPORTED = 0x02

P2P Access is enable

CU_DEVICE_P2P_ATTRIBUTE_NATIVE_ATOMIC_SUPPORTED = 0x03

Atomic operation over the link supported

CU_DEVICE_P2P_ATTRIBUTE_ACCESS_ACCESS_SUPPORTED = 0x04

[Deprecated](#) use CU_DEVICE_P2P_ATTRIBUTE_CUDA_ARRAY_ACCESS_SUPPORTED instead

CU_DEVICE_P2P_ATTRIBUTE_CUDA_ARRAY_ACCESS_SUPPORTED = 0x04

Accessing CUDA arrays over the link supported

enum CUdriverProcAddress_flags

Flags to specify search options. For more details see [cuGetProcAddress](#)

Values

CU_GET_PROC_ADDRESS_DEFAULT = 0

Default search mode for driver symbols.

CU_GET_PROC_ADDRESS_LEGACY_STREAM = 1<<0

Search for legacy versions of driver symbols.

CU_GET_PROC_ADDRESS_PER_THREAD_DEFAULT_STREAM = 1<<1

Search for per-thread versions of driver symbols.

enum CUeglColorFormat

CUDA EGL Color Format - The different planar and multiplanar formats currently supported for CUDA_EGL interops. Three channel formats are currently not supported for [CU_EGL_FRAME_TYPE_ARRAY](#)

Values

CU_EGL_COLOR_FORMAT_YUV420_PLANAR = 0x00

Y, U, V in three surfaces, each in a separate surface, U/V width = 1/2 Y width, U/V height = 1/2 Y height.

CU_EGL_COLOR_FORMAT_YUV420_SEMIPLANAR = 0x01

Y, UV in two surfaces (UV as one surface) with VU byte ordering, width, height ratio same as YUV420Planar.

CU_EGL_COLOR_FORMAT_YUV422_PLANAR = 0x02

Y, U, V each in a separate surface, U/V width = 1/2 Y width, U/V height = Y height.

CU_EGL_COLOR_FORMAT_YUV422_SEMIPLANAR = 0x03

Y, UV in two surfaces with VU byte ordering, width, height ratio same as YUV422Planar.

CU_EGL_COLOR_FORMAT_RGB = 0x04

R/G/B three channels in one surface with BGR byte ordering. Only pitch linear format supported.

CU_EGL_COLOR_FORMAT_BGR = 0x05

R/G/B three channels in one surface with RGB byte ordering. Only pitch linear format supported.

CU_EGL_COLOR_FORMAT_ARGB = 0x06

R/G/B/A four channels in one surface with BGRA byte ordering.

CU_EGL_COLOR_FORMAT_RGBA = 0x07

R/G/B/A four channels in one surface with ABGR byte ordering.

CU_EGL_COLOR_FORMAT_L = 0x08

single luminance channel in one surface.

CU_EGL_COLOR_FORMAT_R = 0x09

single color channel in one surface.

CU_EGL_COLOR_FORMAT_YUV444_PLANAR = 0x0A

Y, U, V in three surfaces, each in a separate surface, U/V width = Y width, U/V height = Y height.

CU_EGL_COLOR_FORMAT_YUV444_SEMIPLANAR = 0x0B

Y, UV in two surfaces (UV as one surface) with VU byte ordering, width, height ratio same as YUV444Planar.

CU_EGL_COLOR_FORMAT_YUYV_422 = 0x0C

Y, U, V in one surface, interleaved as UYYV.

CU_EGL_COLOR_FORMAT_UYVY_422 = 0x0D

Y, U, V in one surface, interleaved as YUYV.

CU_EGL_COLOR_FORMAT_ABGR = 0x0E

R/G/B/A four channels in one surface with RGBA byte ordering.

CU_EGL_COLOR_FORMAT_BGRA = 0x0F

R/G/B/A four channels in one surface with ARGB byte ordering.

CU_EGL_COLOR_FORMAT_A = 0x10

Alpha color format - one channel in one surface.

CU_EGL_COLOR_FORMAT_RG = 0x11

R/G color format - two channels in one surface with GR byte ordering

CU_EGL_COLOR_FORMAT_AYUV = 0x12

Y, U, V, A four channels in one surface, interleaved as VUYA.

CU_EGL_COLOR_FORMAT_YVU444_SEMIPLANAR = 0x13

Y, VU in two surfaces (VU as one surface) with UV byte ordering, U/V width = Y width, U/V height = Y height.

CU_EGL_COLOR_FORMAT_YVU422_SEMIPLANAR = 0x14

Y, VU in two surfaces (VU as one surface) with UV byte ordering, U/V width = 1/2 Y width, U/V height = Y height.

CU_EGL_COLOR_FORMAT_YVU420_SEMIPLANAR = 0x15

Y, VU in two surfaces (VU as one surface) with UV byte ordering, U/V width = 1/2 Y width, U/V height = 1/2 Y height.

CU_EGL_COLOR_FORMAT_Y10V10U10_444_SEMIPLANAR = 0x16

Y10, V10U10 in two surfaces (VU as one surface) with UV byte ordering, U/V width = Y width, U/V height = Y height.

CU_EGL_COLOR_FORMAT_Y10V10U10_420_SEMIPLANAR = 0x17

Y10, V10U10 in two surfaces (VU as one surface) with UV byte ordering, U/V width = 1/2 Y width, U/V height = 1/2 Y height.

CU_EGL_COLOR_FORMAT_Y12V12U12_444_SEMIPLANAR = 0x18

Y12, V12U12 in two surfaces (VU as one surface) with UV byte ordering, U/V width = Y width, U/V height = Y height.

CU_EGL_COLOR_FORMAT_Y12V12U12_420_SEMIPLANAR = 0x19

Y12, V12U12 in two surfaces (VU as one surface) with UV byte ordering, U/V width = 1/2 Y width, U/V height = 1/2 Y height.

CU_EGL_COLOR_FORMAT_VYUY_ER = 0x1A

Extended Range Y, U, V in one surface, interleaved as VYU.

CU_EGL_COLOR_FORMAT_UYVY_ER = 0x1B

Extended Range Y, U, V in one surface, interleaved as YUYV.

CU_EGL_COLOR_FORMAT_YUYV_ER = 0x1C

Extended Range Y, U, V in one surface, interleaved as UYVY.

CU_EGL_COLOR_FORMAT_YVYU_ER = 0x1D

Extended Range Y, U, V in one surface, interleaved as VYU.

CU_EGL_COLOR_FORMAT_YUV_ER = 0x1E

Extended Range Y, U, V three channels in one surface, interleaved as VUY. Only pitch linear format supported.

CU_EGL_COLOR_FORMAT_YUVA_ER = 0x1F

Extended Range Y, U, V, A four channels in one surface, interleaved as AVUY.

CU_EGL_COLOR_FORMAT_AYUV_ER = 0x20

Extended Range Y, U, V, A four channels in one surface, interleaved as VUYA.

CU_EGL_COLOR_FORMAT_YUV444_PLANAR_ER = 0x21

Extended Range Y, U, V in three surfaces, U/V width = Y width, U/V height = Y height.

CU_EGL_COLOR_FORMAT_YUV422_PLANAR_ER = 0x22

Extended Range Y, U, V in three surfaces, U/V width = 1/2 Y width, U/V height = Y height.

CU_EGL_COLOR_FORMAT_YUV420_PLANAR_ER = 0x23

Extended Range Y, U, V in three surfaces, U/V width = 1/2 Y width, U/V height = 1/2 Y height.

CU_EGL_COLOR_FORMAT_YUV444_SEMIPLANAR_ER = 0x24

Extended Range Y, UV in two surfaces (UV as one surface) with VU byte ordering, U/V width = Y width, U/V height = Y height.

CU_EGL_COLOR_FORMAT_YUV422_SEMIPLANAR_ER = 0x25

Extended Range Y, UV in two surfaces (UV as one surface) with VU byte ordering, U/V width = 1/2 Y width, U/V height = Y height.

CU_EGL_COLOR_FORMAT_YUV420_SEMIPLANAR_ER = 0x26

Extended Range Y, UV in two surfaces (UV as one surface) with VU byte ordering, U/V width = 1/2 Y width, U/V height = 1/2 Y height.

CU_EGL_COLOR_FORMAT_YVU444_PLANAR_ER = 0x27

Extended Range Y, V, U in three surfaces, U/V width = Y width, U/V height = Y height.

CU_EGL_COLOR_FORMAT_YVU422_PLANAR_ER = 0x28

Extended Range Y, V, U in three surfaces, U/V width = 1/2 Y width, U/V height = Y height.

CU_EGL_COLOR_FORMAT_YVU420_PLANAR_ER = 0x29

Extended Range Y, V, U in three surfaces, U/V width = 1/2 Y width, U/V height = 1/2 Y height.

CU_EGL_COLOR_FORMAT_YVU444_SEMIPLANAR_ER = 0x2A

Extended Range Y, VU in two surfaces (VU as one surface) with UV byte ordering, U/V width = Y width, U/V height = Y height.

CU_EGL_COLOR_FORMAT_YVU422_SEMIPLANAR_ER = 0x2B

Extended Range Y, VU in two surfaces (VU as one surface) with UV byte ordering, U/V width = 1/2 Y width, U/V height = Y height.

CU_EGL_COLOR_FORMAT_YVU420_SEMIPLANAR_ER = 0x2C

Extended Range Y, VU in two surfaces (VU as one surface) with UV byte ordering, U/V width = 1/2 Y width, U/V height = 1/2 Y height.

CU_EGL_COLOR_FORMAT_BAYER_RGGB = 0x2D

Bayer format - one channel in one surface with interleaved RGGB ordering.

CU_EGL_COLOR_FORMAT_BAYER_BGGR = 0x2E

Bayer format - one channel in one surface with interleaved BGGR ordering.

CU_EGL_COLOR_FORMAT_BAYER_GRGB = 0x2F

Bayer format - one channel in one surface with interleaved GRGB ordering.

CU_EGL_COLOR_FORMAT_BAYER_GBRG = 0x30

Bayer format - one channel in one surface with interleaved GBRG ordering.

CU_EGL_COLOR_FORMAT_BAYER10_RGGB = 0x31

Bayer10 format - one channel in one surface with interleaved RGGB ordering. Out of 16 bits, 10 bits used 6 bits No-op.

CU_EGL_COLOR_FORMAT_BAYER10_BGGR = 0x32

Bayer10 format - one channel in one surface with interleaved BGGR ordering. Out of 16 bits, 10 bits used 6 bits No-op.

CU_EGL_COLOR_FORMAT_BAYER10_GRGB = 0x33

Bayer10 format - one channel in one surface with interleaved GRGB ordering. Out of 16 bits, 10 bits used 6 bits No-op.

CU_EGL_COLOR_FORMAT_BAYER10_GBRG = 0x34

Bayer10 format - one channel in one surface with interleaved GBRG ordering. Out of 16 bits, 10 bits used 6 bits No-op.

CU_EGL_COLOR_FORMAT_BAYER12_RGGB = 0x35

Bayer12 format - one channel in one surface with interleaved RGGB ordering. Out of 16 bits, 12 bits used 4 bits No-op.

CU_EGL_COLOR_FORMAT_BAYER12_BGGR = 0x36

Bayer12 format - one channel in one surface with interleaved BGGR ordering. Out of 16 bits, 12 bits used 4 bits No-op.

CU_EGL_COLOR_FORMAT_BAYER12_GRGB = 0x37

Bayer12 format - one channel in one surface with interleaved GRGB ordering. Out of 16 bits, 12 bits used 4 bits No-op.

CU_EGL_COLOR_FORMAT_BAYER12_GBRG = 0x38

Bayer12 format - one channel in one surface with interleaved GBRG ordering. Out of 16 bits, 12 bits used 4 bits No-op.

CU_EGL_COLOR_FORMAT_BAYER14_RGGB = 0x39

Bayer14 format - one channel in one surface with interleaved RGGB ordering. Out of 16 bits, 14 bits used 2 bits No-op.

CU_EGL_COLOR_FORMAT_BAYER14_BGGR = 0x3A

Bayer14 format - one channel in one surface with interleaved BGGR ordering. Out of 16 bits, 14 bits used 2 bits No-op.

CU_EGL_COLOR_FORMAT_BAYER14_GRBG = 0x3B

Bayer14 format - one channel in one surface with interleaved GRBG ordering. Out of 16 bits, 14 bits used 2 bits No-op.

CU_EGL_COLOR_FORMAT_BAYER14_GBRG = 0x3C

Bayer14 format - one channel in one surface with interleaved GBRG ordering. Out of 16 bits, 14 bits used 2 bits No-op.

CU_EGL_COLOR_FORMAT_BAYER20_RGGB = 0x3D

Bayer20 format - one channel in one surface with interleaved RGGB ordering. Out of 32 bits, 20 bits used 12 bits No-op.

CU_EGL_COLOR_FORMAT_BAYER20_BGGR = 0x3E

Bayer20 format - one channel in one surface with interleaved BGGR ordering. Out of 32 bits, 20 bits used 12 bits No-op.

CU_EGL_COLOR_FORMAT_BAYER20_GRBG = 0x3F

Bayer20 format - one channel in one surface with interleaved GRBG ordering. Out of 32 bits, 20 bits used 12 bits No-op.

CU_EGL_COLOR_FORMAT_BAYER20_GBRG = 0x40

Bayer20 format - one channel in one surface with interleaved GBRG ordering. Out of 32 bits, 20 bits used 12 bits No-op.

CU_EGL_COLOR_FORMAT_YVU444_PLANAR = 0x41

Y, V, U in three surfaces, each in a separate surface, U/V width = Y width, U/V height = Y height.

CU_EGL_COLOR_FORMAT_YVU422_PLANAR = 0x42

Y, V, U in three surfaces, each in a separate surface, U/V width = 1/2 Y width, U/V height = Y height.

CU_EGL_COLOR_FORMAT_YVU420_PLANAR = 0x43

Y, V, U in three surfaces, each in a separate surface, U/V width = 1/2 Y width, U/V height = 1/2 Y height.

CU_EGL_COLOR_FORMAT_BAYER_ISP_RGGB = 0x44

Nvidia proprietary Bayer ISP format - one channel in one surface with interleaved RGGB ordering and mapped to opaque integer datatype.

CU_EGL_COLOR_FORMAT_BAYER_ISP_BGGR = 0x45

Nvidia proprietary Bayer ISP format - one channel in one surface with interleaved BGGR ordering and mapped to opaque integer datatype.

CU_EGL_COLOR_FORMAT_BAYER_ISP_GRBG = 0x46

Nvidia proprietary Bayer ISP format - one channel in one surface with interleaved GRBG ordering and mapped to opaque integer datatype.

CU_EGL_COLOR_FORMAT_BAYER_ISP_GBRG = 0x47

Nvidia proprietary Bayer ISP format - one channel in one surface with interleaved GBRG ordering and mapped to opaque integer datatype.

CU_EGL_COLOR_FORMAT_BAYER_BCCR = 0x48

Bayer format - one channel in one surface with interleaved BCCR ordering.

CU_EGL_COLOR_FORMAT_BAYER_RCCB = 0x49

Bayer format - one channel in one surface with interleaved RCCB ordering.

CU_EGL_COLOR_FORMAT_BAYER_CRBC = 0x4A

Bayer format - one channel in one surface with interleaved CRBC ordering.

CU_EGL_COLOR_FORMAT_BAYER_CBRC = 0x4B

Bayer format - one channel in one surface with interleaved CBRC ordering.

CU_EGL_COLOR_FORMAT_BAYER10_CCCC = 0x4C

Bayer10 format - one channel in one surface with interleaved CCCC ordering. Out of 16 bits, 10 bits used 6 bits No-op.

CU_EGL_COLOR_FORMAT_BAYER12_BCCR = 0x4D

Bayer12 format - one channel in one surface with interleaved BCCR ordering. Out of 16 bits, 12 bits used 4 bits No-op.

CU_EGL_COLOR_FORMAT_BAYER12_RCCB = 0x4E

Bayer12 format - one channel in one surface with interleaved RCCB ordering. Out of 16 bits, 12 bits used 4 bits No-op.

CU_EGL_COLOR_FORMAT_BAYER12_CRBC = 0x4F

Bayer12 format - one channel in one surface with interleaved CRBC ordering. Out of 16 bits, 12 bits used 4 bits No-op.

CU_EGL_COLOR_FORMAT_BAYER12_CBRC = 0x50

Bayer12 format - one channel in one surface with interleaved CBRC ordering. Out of 16 bits, 12 bits used 4 bits No-op.

CU_EGL_COLOR_FORMAT_BAYER12_CCCC = 0x51

Bayer12 format - one channel in one surface with interleaved CCCC ordering. Out of 16 bits, 12 bits used 4 bits No-op.

CU_EGL_COLOR_FORMAT_Y = 0x52

Color format for single Y plane.

CU_EGL_COLOR_FORMAT_MAX

enum CUeglFrameType

CUDA EglFrame type - array or pointer

Values

CU_EGL_FRAME_TYPE_ARRAY = 0

Frame type CUDA array

CU_EGL_FRAME_TYPE_PITCH = 1

Frame type pointer

enum CUeglResourceLocationFlags

Resource location flags- systemem or vidmem

For CUDA context on iGPU, since video and system memory are equivalent - these flags will not have an effect on the execution.

For CUDA context on dGPU, applications can use the flag [CUeglResourceLocationFlags](#) to give a hint about the desired location.

[CU_EGL_RESOURCE_LOCATION_SYSTEMEM](#) - the frame data is made resident on the system memory to be accessed by CUDA.

[CU_EGL_RESOURCE_LOCATION_VIDMEM](#) - the frame data is made resident on the dedicated video memory to be accessed by CUDA.

There may be an additional latency due to new allocation and data migration, if the frame is produced on a different memory.

Values

CU_EGL_RESOURCE_LOCATION_SYSTEMEM = 0x00

Resource location systemem

CU_EGL_RESOURCE_LOCATION_VIDMEM = 0x01

Resource location vidmem

enum CUevent_flags

Event creation flags

Values

CU_EVENT_DEFAULT = 0x0

Default event flag

CU_EVENT_BLOCKING_SYNC = 0x1

Event uses blocking synchronization

CU_EVENT_DISABLE_TIMING = 0x2

Event will not record timing data

CU_EVENT_INTERPROCESS = 0x4

Event is suitable for interprocess use. CU_EVENT_DISABLE_TIMING must be set

enum CUevent_record_flags

Event record flags

Values

CU_EVENT_RECORD_DEFAULT = 0x0

Default event record flag

CU_EVENT_RECORD_EXTERNAL = 0x1

When using stream capture, create an event record node instead of the default behavior.

This flag is invalid when used outside of capture.

enum CUevent_wait_flags

Event wait flags

Values

CU_EVENT_WAIT_DEFAULT = 0x0

Default event wait flag

CU_EVENT_WAIT_EXTERNAL = 0x1

When using stream capture, create an event wait node instead of the default behavior. This

flag is invalid when used outside of capture.

enum CUexternalMemoryHandleType

External memory handle types

Values

CU_EXTERNAL_MEMORY_HANDLE_TYPE_OPAQUE_FD = 1

Handle is an opaque file descriptor

CU_EXTERNAL_MEMORY_HANDLE_TYPE_OPAQUE_WIN32 = 2

Handle is an opaque shared NT handle

CU_EXTERNAL_MEMORY_HANDLE_TYPE_OPAQUE_WIN32_KMT = 3

Handle is an opaque, globally shared handle

CU_EXTERNAL_MEMORY_HANDLE_TYPE_D3D12_HEAP = 4

Handle is a D3D12 heap object

CU_EXTERNAL_MEMORY_HANDLE_TYPE_D3D12_RESOURCE = 5

Handle is a D3D12 committed resource

CU_EXTERNAL_MEMORY_HANDLE_TYPE_D3D11_RESOURCE = 6

Handle is a shared NT handle to a D3D11 resource

CU_EXTERNAL_MEMORY_HANDLE_TYPE_D3D11_RESOURCE_KMT = 7

Handle is a globally shared handle to a D3D11 resource

CU_EXTERNAL_MEMORY_HANDLE_TYPE_NVSCIBUF = 8

Handle is an NvSciBuf object

enum CUexternalSemaphoreHandleType

External semaphore handle types

Values

CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_OPAQUE_FD = 1

Handle is an opaque file descriptor

CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_OPAQUE_WIN32 = 2

Handle is an opaque shared NT handle

CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_OPAQUE_WIN32_KMT = 3

Handle is an opaque, globally shared handle

CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_D3D12_FENCE = 4

Handle is a shared NT handle referencing a D3D12 fence object

CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_D3D11_FENCE = 5

Handle is a shared NT handle referencing a D3D11 fence object

CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_NVSCISYNC = 6

Opaque handle to NvSciSync Object

CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_D3D11_KEYED_MUTEX = 7

Handle is a shared NT handle referencing a D3D11 keyed mutex object

CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_D3D11_KEYED_MUTEX_KMT = 8

Handle is a globally shared handle referencing a D3D11 keyed mutex object

CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_TIMELINE_SEMAPHORE_FD = 9

Handle is an opaque file descriptor referencing a timeline semaphore

CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_TIMELINE_SEMAPHORE_WIN32 = 10

Handle is an opaque shared NT handle referencing a timeline semaphore

enum CUfilter_mode

Texture reference filtering modes

Values

CU_TR_FILTER_MODE_POINT = 0

Point filter mode

CU_TR_FILTER_MODE_LINEAR = 1

Linear filter mode

enum CUflushGPUDirectRDMAWritesOptions

Bitmasks for [CU_DEVICE_ATTRIBUTE_GPU_DIRECT_RDMA_FLUSH_WRITES_OPTIONS](#)

Values

CU_FLUSH_GPU_DIRECT_RDMA_WRITES_OPTION_HOST = 1<<0

cuFlushGPUDirectRDMAWrites() and its CUDA Runtime API counterpart are supported on the device.

CU_FLUSH_GPU_DIRECT_RDMA_WRITES_OPTION_MEMOPS = 1<<1

The `CU_STREAM_WAIT_VALUE_FLUSH` flag and the `CU_STREAM_MEM_OP_FLUSH_REMOTE_WRITES` MemOp are supported on the device.

enum CUflushGPUDirectRDMAWritesScope

The scopes for `cuFlushGPUDirectRDMAWrites`

Values

CU_FLUSH_GPU_DIRECT_RDMA_WRITES_TO_OWNER = 100

Blocks until remote writes are visible to the CUDA device context owning the data.

CU_FLUSH_GPU_DIRECT_RDMA_WRITES_TO_ALL_DEVICES = 200

Blocks until remote writes are visible to all CUDA device contexts.

enum CUflushGPUDirectRDMAWritesTarget

The targets for `cuFlushGPUDirectRDMAWrites`

Values

CU_FLUSH_GPU_DIRECT_RDMA_WRITES_TARGET_CURRENT_CTX = 0

Sets the target for `cuFlushGPUDirectRDMAWrites()` to the currently active CUDA device context.

enum CUfunc_cache

Function cache configurations

Values

CU_FUNC_CACHE_PREFER_NONE = 0x00

no preference for shared memory or L1 (default)

CU_FUNC_CACHE_PREFER_SHARED = 0x01

prefer larger shared memory and smaller L1 cache

CU_FUNC_CACHE_PREFER_L1 = 0x02

prefer larger L1 cache and smaller shared memory

CU_FUNC_CACHE_PREFER_EQUAL = 0x03

prefer equal sized L1 cache and shared memory

enum CUfunction_attribute

Function properties

Values

CU_FUNC_ATTRIBUTE_MAX_THREADS_PER_BLOCK = 0

The maximum number of threads per block, beyond which a launch of the function would fail. This number depends on both the function and the device on which the function is currently loaded.

CU_FUNC_ATTRIBUTE_SHARED_SIZE_BYTES = 1

The size in bytes of statically-allocated shared memory required by this function. This does not include dynamically-allocated shared memory requested by the user at runtime.

CU_FUNC_ATTRIBUTE_CONST_SIZE_BYTES = 2

The size in bytes of user-allocated constant memory required by this function.

CU_FUNC_ATTRIBUTE_LOCAL_SIZE_BYTES = 3

The size in bytes of local memory used by each thread of this function.

CU_FUNC_ATTRIBUTE_NUM_REGS = 4

The number of registers used by each thread of this function.

CU_FUNC_ATTRIBUTE_PTX_VERSION = 5

The PTX virtual architecture version for which the function was compiled. This value is the major PTX version * 10 + the minor PTX version, so a PTX version 1.3 function would return the value 13. Note that this may return the undefined value of 0 for cubins compiled prior to CUDA 3.0.

CU_FUNC_ATTRIBUTE_BINARY_VERSION = 6

The binary architecture version for which the function was compiled. This value is the major binary version * 10 + the minor binary version, so a binary version 1.3 function would return the value 13. Note that this will return a value of 10 for legacy cubins that do not have a properly-encoded binary architecture version.

CU_FUNC_ATTRIBUTE_CACHE_MODE_CA = 7

The attribute to indicate whether the function has been compiled with user specified option "-Xptxas --dlcm=ca" set .

CU_FUNC_ATTRIBUTE_MAX_DYNAMIC_SHARED_SIZE_BYTES = 8

The maximum size in bytes of dynamically-allocated shared memory that can be used by this function. If the user-specified dynamic shared memory size is larger than this value, the launch will fail. See [cuFuncSetAttribute](#)

CU_FUNC_ATTRIBUTE_PREFERRED_SHARED_MEMORY_CARVEOUT = 9

On devices where the L1 cache and shared memory use the same hardware resources, this sets the shared memory carveout preference, in percent of the total shared memory. Refer to [CU_DEVICE_ATTRIBUTE_MAX_SHARED_MEMORY_PER_MULTIPROCESSOR](#). This is only a hint, and the driver can choose a different ratio if required to execute the function. See [cuFuncSetAttribute](#)

CU_FUNC_ATTRIBUTE_MAX

enum CUGPUDirectRDMAWritesOrdering

Platform native ordering for GPUDirect RDMA writes

Values

CU_GPU_DIRECT_RDMA_WRITES_ORDERING_NONE = 0

The device does not natively support ordering of remote writes.

`cuFlushGPUDirectRDMAWrites()` can be leveraged if supported.

CU_GPU_DIRECT_RDMA_WRITES_ORDERING_OWNER = 100

Natively, the device can consistently consume remote writes, although other CUDA devices may not.

CU_GPU_DIRECT_RDMA_WRITES_ORDERING_ALL_DEVICES = 200

Any CUDA device in the system can consistently consume remote writes to this device.

enum CUgraphDebugDot_flags

The additional write options for [cuGraphDebugDotPrint](#)

Values

CU_GRAPH_DEBUG_DOT_FLAGS_VERBOSE = 1<<0

CU_GRAPH_DEBUG_DOT_FLAGS_RUNTIME_TYPES = 1<<1

Output all debug data as if every debug flag is enabled

CU_GRAPH_DEBUG_DOT_FLAGS_KERNEL_NODE_PARAMS = 1<<2

Use CUDA Runtime structures for output

CU_GRAPH_DEBUG_DOT_FLAGS_MEMCPY_NODE_PARAMS = 1<<3

Adds CUDA_KERNEL_NODE_PARAMS values to output

CU_GRAPH_DEBUG_DOT_FLAGS_MEMSET_NODE_PARAMS = 1<<4

Adds CUDA_MEMCPY3D values to output

CU_GRAPH_DEBUG_DOT_FLAGS_HOST_NODE_PARAMS = 1<<5

Adds CUDA_MEMSET_NODE_PARAMS values to output

CU_GRAPH_DEBUG_DOT_FLAGS_EVENT_NODE_PARAMS = 1<<6

Adds CUDA_HOST_NODE_PARAMS values to output

CU_GRAPH_DEBUG_DOT_FLAGS_EXT_SEMAS_SIGNAL_NODE_PARAMS = 1<<7

Adds CUevent handle from record and wait nodes to output

CU_GRAPH_DEBUG_DOT_FLAGS_EXT_SEMAS_WAIT_NODE_PARAMS = 1<<8

Adds CUDA_EXT_SEM_SIGNAL_NODE_PARAMS values to output

CU_GRAPH_DEBUG_DOT_FLAGS_KERNEL_NODE_ATTRIBUTES = 1<<9

Adds CUDA_EXT_SEM_WAIT_NODE_PARAMS values to output

CU_GRAPH_DEBUG_DOT_FLAGS_HANDLES = 1<<10

Adds CUkernelNodeAttrValue values to output

enum CUgraphicsMapResourceFlags

Flags for mapping and unmapping interop resources

Values

CU_GRAPHICS_MAP_RESOURCE_FLAGS_NONE = 0x00

CU_GRAPHICS_MAP_RESOURCE_FLAGS_READ_ONLY = 0x01

CU_GRAPHICS_MAP_RESOURCE_FLAGS_WRITE_DISCARD = 0x02

enum CUgraphicsRegisterFlags

Flags to register a graphics resource

Values

CU_GRAPHICS_REGISTER_FLAGS_NONE = 0x00
CU_GRAPHICS_REGISTER_FLAGS_READ_ONLY = 0x01
CU_GRAPHICS_REGISTER_FLAGS_WRITE_DISCARD = 0x02
CU_GRAPHICS_REGISTER_FLAGS_SURFACE_LDST = 0x04
CU_GRAPHICS_REGISTER_FLAGS_TEXTURE_GATHER = 0x08

enum CUgraphNodeType

Graph node types

Values

CU_GRAPH_NODE_TYPE_KERNEL = 0
GPU kernel node
CU_GRAPH_NODE_TYPE_MEMCPY = 1
Memcpy node
CU_GRAPH_NODE_TYPE_MEMSET = 2
Memset node
CU_GRAPH_NODE_TYPE_HOST = 3
Host (executable) node
CU_GRAPH_NODE_TYPE_GRAPH = 4
Node which executes an embedded graph
CU_GRAPH_NODE_TYPE_EMPTY = 5
Empty (no-op) node
CU_GRAPH_NODE_TYPE_WAIT_EVENT = 6
External event wait node
CU_GRAPH_NODE_TYPE_EVENT_RECORD = 7
External event record node
CU_GRAPH_NODE_TYPE_EXT_SEMAS_SIGNAL = 8
External semaphore signal node
CU_GRAPH_NODE_TYPE_EXT_SEMAS_WAIT = 9
External semaphore wait node

enum CUipcMem_flags

CUDA Ipc Mem Flags

Values

CU_IPC_MEM_LAZY_ENABLE_PEER_ACCESS = 0x1

Automatically enable peer access between remote devices as needed

enum CUjit_cacheMode

Caching modes for dlcm

Values

CU_JIT_CACHE_OPTION_NONE = 0

Compile with no -dlcm flag specified

CU_JIT_CACHE_OPTION_CG

Compile with L1 cache disabled

CU_JIT_CACHE_OPTION_CA

Compile with L1 cache enabled

enum CUjit_fallback

Cubin matching fallback strategies

Values

CU_PREFER_PTX = 0

Prefer to compile ptx if exact binary match not found

CU_PREFER_BINARY

Prefer to fall back to compatible binary code if exact match not found

enum CUjit_option

Online compiler and linker options

Values

CU_JIT_MAX_REGISTERS = 0

Max number of registers that a thread may use. Option type: unsigned int Applies to: compiler only

CU_JIT_THREADS_PER_BLOCK

IN: Specifies minimum number of threads per block to target compilation for OUT: Returns the number of threads the compiler actually targeted. This restricts the resource utilization for the compiler (e.g. max registers) such that a block with the given number of threads should be able to launch based on register limitations. Note, this option does not currently take into account any other resource limitations, such as shared memory utilization.

Cannot be combined with [CU_JIT_TARGET](#). Option type: unsigned int Applies to: compiler only

CU_JIT_WALL_TIME

Overwrites the option value with the total wall clock time, in milliseconds, spent in the compiler and linker Option type: float Applies to: compiler and linker

CU_JIT_INFO_LOG_BUFFER

Pointer to a buffer in which to print any log messages that are informational in nature (the buffer size is specified via option [CU_JIT_INFO_LOG_BUFFER_SIZE_BYTES](#)) Option type: char * Applies to: compiler and linker

CU_JIT_INFO_LOG_BUFFER_SIZE_BYTES

IN: Log buffer size in bytes. Log messages will be capped at this size (including null terminator) OUT: Amount of log buffer filled with messages Option type: unsigned int Applies to: compiler and linker

CU_JIT_ERROR_LOG_BUFFER

Pointer to a buffer in which to print any log messages that reflect errors (the buffer size is specified via option [CU_JIT_ERROR_LOG_BUFFER_SIZE_BYTES](#)) Option type: char * Applies to: compiler and linker

CU_JIT_ERROR_LOG_BUFFER_SIZE_BYTES

IN: Log buffer size in bytes. Log messages will be capped at this size (including null terminator) OUT: Amount of log buffer filled with messages Option type: unsigned int Applies to: compiler and linker

CU_JIT_OPTIMIZATION_LEVEL

Level of optimizations to apply to generated code (0 - 4), with 4 being the default and highest level of optimizations. Option type: unsigned int Applies to: compiler only

CU_JIT_TARGET_FROM_CUCONTEXT

No option value required. Determines the target based on the current attached context (default) Option type: No option value needed Applies to: compiler and linker

CU_JIT_TARGET

Target is chosen based on supplied [CUjit_target](#). Cannot be combined with [CU_JIT_THREADS_PER_BLOCK](#). Option type: unsigned int for enumerated type [CUjit_target](#) Applies to: compiler and linker

CU_JIT_FALLBACK_STRATEGY

Specifies choice of fallback strategy if matching cubin is not found. Choice is based on supplied [CUjit_fallback](#). This option cannot be used with cuLink* APIs as the linker requires exact matches. Option type: unsigned int for enumerated type [CUjit_fallback](#) Applies to: compiler only

CU_JIT_GENERATE_DEBUG_INFO

Specifies whether to create debug information in output (-g) (0: false, default) Option type: int Applies to: compiler and linker

CU_JIT_LOG_VERBOSE

Generate verbose log messages (0: false, default) Option type: int Applies to: compiler and linker

CU_JIT_GENERATE_LINE_INFO

Generate line number information (-lineinfo) (0: false, default) Option type: int Applies to: compiler only

CU_JIT_CACHE_MODE

Specifies whether to enable caching explicitly (-dlcm) Choice is based on supplied CUjit_cacheMode_enum. Option type: unsigned int for enumerated type CUjit_cacheMode_enum Applies to: compiler only

CU_JIT_NEW_SM3X_OPT

The below jit options are used for internal purposes only, in this version of CUDA

CU_JIT_FAST_COMPILE**CU_JIT_GLOBAL_SYMBOL_NAMES**

Array of device symbol names that will be relocated to the corresponding host addresses stored in [CU_JIT_GLOBAL_SYMBOL_ADDRESSES](#). Must contain [CU_JIT_GLOBAL_SYMBOL_COUNT](#) entries. When loading a device module, driver will relocate all encountered unresolved symbols to the host addresses. It is only allowed to register symbols that correspond to unresolved global variables. It is illegal to register the same device symbol at multiple addresses. Option type: const char ** Applies to: dynamic linker only

CU_JIT_GLOBAL_SYMBOL_ADDRESSES

Array of host addresses that will be used to relocate corresponding device symbols stored in [CU_JIT_GLOBAL_SYMBOL_NAMES](#). Must contain [CU_JIT_GLOBAL_SYMBOL_COUNT](#) entries. Option type: void ** Applies to: dynamic linker only

CU_JIT_GLOBAL_SYMBOL_COUNT

Number of entries in [CU_JIT_GLOBAL_SYMBOL_NAMES](#) and [CU_JIT_GLOBAL_SYMBOL_ADDRESSES](#) arrays. Option type: unsigned int Applies to: dynamic linker only

CU_JIT_NUM_OPTIONS

enum CUjit_target

Online compilation targets

Values

CU_TARGET_COMPUTE_20 = 20

Compute device class 2.0

CU_TARGET_COMPUTE_21 = 21

Compute device class 2.1

CU_TARGET_COMPUTE_30 = 30

Compute device class 3.0

CU_TARGET_COMPUTE_32 = 32

Compute device class 3.2

CU_TARGET_COMPUTE_35 = 35

Compute device class 3.5

CU_TARGET_COMPUTE_37 = 37

Compute device class 3.7

CU_TARGET_COMPUTE_50 = 50

Compute device class 5.0

CU_TARGET_COMPUTE_52 = 52

Compute device class 5.2

CU_TARGET_COMPUTE_53 = 53

Compute device class 5.3

CU_TARGET_COMPUTE_60 = 60

Compute device class 6.0.

CU_TARGET_COMPUTE_61 = 61

Compute device class 6.1.

CU_TARGET_COMPUTE_62 = 62

Compute device class 6.2.

CU_TARGET_COMPUTE_70 = 70

Compute device class 7.0.

CU_TARGET_COMPUTE_72 = 72

Compute device class 7.2.

CU_TARGET_COMPUTE_75 = 75

Compute device class 7.5.

CU_TARGET_COMPUTE_80 = 80

Compute device class 8.0.

CU_TARGET_COMPUTE_86 = 86

Compute device class 8.6.

enum CUjitInputType

Device code formats

Values

CU_JIT_INPUT_CUBIN = 0

Compiled device-class-specific device code Applicable options: none

CU_JIT_INPUT_PTX

PTX source code Applicable options: PTX compiler options

CU_JIT_INPUT_FATBINARY

Bundle of multiple cubins and/or PTX of some device code Applicable options: PTX compiler options, [CU_JIT_FALLBACK_STRATEGY](#)

CU_JIT_INPUT_OBJECT

Host object with embedded device code Applicable options: PTX compiler options, [CU_JIT_FALLBACK_STRATEGY](#)

CU_JIT_INPUT_LIBRARY

Archive of host objects with embedded device code Applicable options: PTX compiler options, [CU_JIT_FALLBACK_STRATEGY](#)

CU_JIT_NUM_INPUT_TYPES

enum CUkernelNodeAttrID

Graph kernel node Attributes

Values

CU_KERNEL_NODE_ATTRIBUTE_ACCESS_POLICY_WINDOW = 1

Identifier for [CUkernelNodeAttrValue::accessPolicyWindow](#).

CU_KERNEL_NODE_ATTRIBUTE_COOPERATIVE = 2

Allows a kernel node to be cooperative (see [cuLaunchCooperativeKernel](#)).

enum CUlimit

Limits

Values

CU_LIMIT_STACK_SIZE = 0x00

GPU thread stack size

CU_LIMIT_PRINTF_FIFO_SIZE = 0x01

GPU printf FIFO size

CU_LIMIT_MALLOC_HEAP_SIZE = 0x02

GPU malloc heap size

CU_LIMIT_DEV_RUNTIME_SYNC_DEPTH = 0x03

GPU device runtime launch synchronize depth

CU_LIMIT_DEV_RUNTIME_PENDING_LAUNCH_COUNT = 0x04

GPU device runtime pending launch count

CU_LIMIT_MAX_L2_FETCH_GRANULARITY = 0x05

A value between 0 and 128 that indicates the maximum fetch granularity of L2 (in Bytes).

This is a hint

CU_LIMIT_PERSISTING_L2_CACHE_SIZE = 0x06

A size in bytes for L2 persisting lines cache size

CU_LIMIT_MAX

enum CUmem_advise

Memory advise values

Values

CU_MEM_ADVISE_SET_READ_MOSTLY = 1

Data will mostly be read and only occasionally be written to

CU_MEM_ADVISE_UNSET_READ_MOSTLY = 2

Undo the effect of [CU_MEM_ADVISE_SET_READ_MOSTLY](#)

CU_MEM_ADVISE_SET_PREFERRED_LOCATION = 3

Set the preferred location for the data as the specified device

CU_MEM_ADVISE_UNSET_PREFERRED_LOCATION = 4

Clear the preferred location for the data

CU_MEM_ADVISE_SET_ACCESSED_BY = 5

Data will be accessed by the specified device, so prevent page faults as much as possible

CU_MEM_ADVISE_UNSET_ACCESSED_BY = 6

Let the Unified Memory subsystem decide on the page faulting policy for the specified device

enum CUmemAccess_flags

Specifies the memory protection flags for mapping.

Values

CU_MEM_ACCESS_FLAGS_PROT_NONE = 0x0

Default, make the address range not accessible

CU_MEM_ACCESS_FLAGS_PROT_READ = 0x1

Make the address range read accessible

CU_MEM_ACCESS_FLAGS_PROT_READWRITE = 0x3

Make the address range read-write accessible

CU_MEM_ACCESS_FLAGS_PROT_MAX = 0x7FFFFFFF

enum CUmemAllocationCompType

Specifies compression attribute for an allocation.

Values

CU_MEM_ALLOCATION_COMP_NONE = 0x0

Allocating non-compressible memory

CU_MEM_ALLOCATION_COMP_GENERIC = 0x1

Allocating compressible memory

enum CUmemAllocationGranularity_flags

Flag for requesting different optimal and required granularities for an allocation.

Values

CU_MEM_ALLOC_GRANULARITY_MINIMUM = 0x0

Minimum required granularity for allocation

CU_MEM_ALLOC_GRANULARITY_RECOMMENDED = 0x1

Recommended granularity for allocation for best performance

enum CUmemAllocationHandleType

Flags for specifying particular handle types

Values

CU_MEM_HANDLE_TYPE_NONE = 0x0

Does not allow any export mechanism. >

CU_MEM_HANDLE_TYPE_POSIX_FILE_DESCRIPTOR = 0x1

Allows a file descriptor to be used for exporting. Permitted only on POSIX systems. (int)

CU_MEM_HANDLE_TYPE_WIN32 = 0x2

Allows a Win32 NT handle to be used for exporting. (HANDLE)

CU_MEM_HANDLE_TYPE_WIN32_KMT = 0x4

Allows a Win32 KMT handle to be used for exporting. (D3DKMT_HANDLE)

CU_MEM_HANDLE_TYPE_MAX = 0x7FFFFFFF

enum CUmemAllocationType

Defines the allocation types available

Values

CU_MEM_ALLOCATION_TYPE_INVALID = 0x0

CU_MEM_ALLOCATION_TYPE_PINNED = 0x1

This allocation type is 'pinned', i.e. cannot migrate from its current location while the application is actively using it

CU_MEM_ALLOCATION_TYPE_MAX = 0x7FFFFFFF

enum CUmemAttach_flags

CUDA Mem Attach Flags

Values

CU_MEM_ATTACH_GLOBAL = 0x1

Memory can be accessed by any stream on any device

CU_MEM_ATTACH_HOST = 0x2

Memory cannot be accessed by any stream on any device

CU_MEM_ATTACH_SINGLE = 0x4

Memory can only be accessed by a single stream on the associated device

enum CUmemHandleType

Memory handle types

Values

CU_MEM_HANDLE_TYPE_GENERIC = 0

enum CUmemLocationType

Specifies the type of location

Values

CU_MEM_LOCATION_TYPE_INVALID = 0x0

CU_MEM_LOCATION_TYPE_DEVICE = 0x1

Location is a device location, thus id is a device ordinal

CU_MEM_LOCATION_TYPE_MAX = 0x7FFFFFFF

enum CUmemOperationType

Memory operation types

Values

CU_MEM_OPERATION_TYPE_MAP = 1

CU_MEM_OPERATION_TYPE_UNMAP = 2

enum CUmemorytype

Memory types

Values

CU_MEMORYTYPE_HOST = 0x01

Host memory

CU_MEMORYTYPE_DEVICE = 0x02

Device memory

CU_MEMORYTYPE_ARRAY = 0x03

Array memory

CU_MEMORYTYPE_UNIFIED = 0x04

Unified device or host memory

enum CUoccupancy_flags

Occupancy calculator flag

Values

CU_OCCUPANCY_DEFAULT = 0x0

Default behavior

CU_OCCUPANCY_DISABLE_CACHING_OVERRIDE = 0x1

Assume global caching is enabled and cannot be automatically turned off

enum CUpointer_attribute

Pointer information

Values

CU_POINTER_ATTRIBUTE_CONTEXT = 1

The [CUcontext](#) on which a pointer was allocated or registered

CU_POINTER_ATTRIBUTE_MEMORY_TYPE = 2

The [CUmemorytype](#) describing the physical location of a pointer

CU_POINTER_ATTRIBUTE_DEVICE_POINTER = 3

The address at which a pointer's memory may be accessed on the device

CU_POINTER_ATTRIBUTE_HOST_POINTER = 4

The address at which a pointer's memory may be accessed on the host

CU_POINTER_ATTRIBUTE_P2P_TOKENS = 5

A pair of tokens for use with the nv-p2p.h Linux kernel interface

CU_POINTER_ATTRIBUTE_SYNC_MEMOPS = 6

Synchronize every synchronous memory operation initiated on this region

CU_POINTER_ATTRIBUTE_BUFFER_ID = 7

A process-wide unique ID for an allocated memory region

CU_POINTER_ATTRIBUTE_IS_MANAGED = 8

Indicates if the pointer points to managed memory

CU_POINTER_ATTRIBUTE_DEVICE_ORDINAL = 9

A device ordinal of a device on which a pointer was allocated or registered

CU_POINTER_ATTRIBUTE_IS_LEGACY_CUDA_IPC_CAPABLE = 10

1 if this pointer maps to an allocation that is suitable for [cudaIpcGetMemHandle](#), 0 otherwise

CU_POINTER_ATTRIBUTE_RANGE_START_ADDR = 11

Starting address for this requested pointer

CU_POINTER_ATTRIBUTE_RANGE_SIZE = 12

Size of the address range for this requested pointer

CU_POINTER_ATTRIBUTE_MAPPED = 13

1 if this pointer is in a valid address range that is mapped to a backing allocation, 0 otherwise

CU_POINTER_ATTRIBUTE_ALLOWED_HANDLE_TYPES = 14

Bitmask of allowed [CUmemAllocationHandleType](#) for this allocation

CU_POINTER_ATTRIBUTE_IS_GPU_DIRECT_RDMA_CAPABLE = 15

1 if the memory this pointer is referencing can be used with the GPUDirect RDMA API

CU_POINTER_ATTRIBUTE_ACCESS_FLAGS = 16

Returns the access flags the device associated with the current context has on the corresponding memory referenced by the pointer given

CU_POINTER_ATTRIBUTE_MEMPOOL_HANDLE = 17

Returns the mempool handle for the allocation if it was allocated from a mempool.
Otherwise returns NULL.

enum CUresourcetype

Resource types

Values

CU_RESOURCE_TYPE_ARRAY = 0x00

Array resource

CU_RESOURCE_TYPE_MIPMAPPED_ARRAY = 0x01

Mipmapped array resource

CU_RESOURCE_TYPE_LINEAR = 0x02

Linear resource

CU_RESOURCE_TYPE_PITCH2D = 0x03

Pitch 2D resource

enum CUresourceViewFormat

Resource view format

Values

CU_RES_VIEW_FORMAT_NONE = 0x00

No resource view format (use underlying resource format)

CU_RES_VIEW_FORMAT_UINT_1X8 = 0x01

1 channel unsigned 8-bit integers

CU_RES_VIEW_FORMAT_UINT_2X8 = 0x02

2 channel unsigned 8-bit integers

CU_RES_VIEW_FORMAT_UINT_4X8 = 0x03

4 channel unsigned 8-bit integers

CU_RES_VIEW_FORMAT_SINT_1X8 = 0x04

1 channel signed 8-bit integers

CU_RES_VIEW_FORMAT_SINT_2X8 = 0x05

2 channel signed 8-bit integers

CU_RES_VIEW_FORMAT_SINT_4X8 = 0x06

4 channel signed 8-bit integers

CU_RES_VIEW_FORMAT_UINT_1X16 = 0x07

1 channel unsigned 16-bit integers

CU_RES_VIEW_FORMAT_UINT_2X16 = 0x08

2 channel unsigned 16-bit integers

CU_RES_VIEW_FORMAT_UINT_4X16 = 0x09

4 channel unsigned 16-bit integers

CU_RES_VIEW_FORMAT_SINT_1X16 = 0x0a
1 channel signed 16-bit integers

CU_RES_VIEW_FORMAT_SINT_2X16 = 0x0b
2 channel signed 16-bit integers

CU_RES_VIEW_FORMAT_SINT_4X16 = 0x0c
4 channel signed 16-bit integers

CU_RES_VIEW_FORMAT_UINT_1X32 = 0x0d
1 channel unsigned 32-bit integers

CU_RES_VIEW_FORMAT_UINT_2X32 = 0x0e
2 channel unsigned 32-bit integers

CU_RES_VIEW_FORMAT_UINT_4X32 = 0x0f
4 channel unsigned 32-bit integers

CU_RES_VIEW_FORMAT_SINT_1X32 = 0x10
1 channel signed 32-bit integers

CU_RES_VIEW_FORMAT_SINT_2X32 = 0x11
2 channel signed 32-bit integers

CU_RES_VIEW_FORMAT_SINT_4X32 = 0x12
4 channel signed 32-bit integers

CU_RES_VIEW_FORMAT_FLOAT_1X16 = 0x13
1 channel 16-bit floating point

CU_RES_VIEW_FORMAT_FLOAT_2X16 = 0x14
2 channel 16-bit floating point

CU_RES_VIEW_FORMAT_FLOAT_4X16 = 0x15
4 channel 16-bit floating point

CU_RES_VIEW_FORMAT_FLOAT_1X32 = 0x16
1 channel 32-bit floating point

CU_RES_VIEW_FORMAT_FLOAT_2X32 = 0x17
2 channel 32-bit floating point

CU_RES_VIEW_FORMAT_FLOAT_4X32 = 0x18
4 channel 32-bit floating point

CU_RES_VIEW_FORMAT_UNSIGNED_BC1 = 0x19
Block compressed 1

CU_RES_VIEW_FORMAT_UNSIGNED_BC2 = 0x1a
Block compressed 2

CU_RES_VIEW_FORMAT_UNSIGNED_BC3 = 0x1b
Block compressed 3

CU_RES_VIEW_FORMAT_UNSIGNED_BC4 = 0x1c
Block compressed 4 unsigned

CU_RES_VIEW_FORMAT_SIGNED_BC4 = 0x1d
Block compressed 4 signed

CU_RES_VIEW_FORMAT_UNSIGNED_BC5 = 0x1e
Block compressed 5 unsigned

CU_RES_VIEW_FORMAT_SIGNED_BC5 = 0x1f

Block compressed 5 signed

CU_RES_VIEW_FORMAT_UNSIGNED_BC6H = 0x20

Block compressed 6 unsigned half-float

CU_RES_VIEW_FORMAT_SIGNED_BC6H = 0x21

Block compressed 6 signed half-float

CU_RES_VIEW_FORMAT_UNSIGNED_BC7 = 0x22

Block compressed 7

enum CUresult

Error codes

Values

CUDA_SUCCESS = 0

The API call returned with no errors. In the case of query calls, this also means that the operation being queried is complete (see [cuEventQuery\(\)](#) and [cuStreamQuery\(\)](#)).

CUDA_ERROR_INVALID_VALUE = 1

This indicates that one or more of the parameters passed to the API call is not within an acceptable range of values.

CUDA_ERROR_OUT_OF_MEMORY = 2

The API call failed because it was unable to allocate enough memory to perform the requested operation.

CUDA_ERROR_NOT_INITIALIZED = 3

This indicates that the CUDA driver has not been initialized with [culnit\(\)](#) or that initialization has failed.

CUDA_ERROR_DEINITIALIZED = 4

This indicates that the CUDA driver is in the process of shutting down.

CUDA_ERROR_PROFILER_DISABLED = 5

This indicates profiler is not initialized for this run. This can happen when the application is running with external profiling tools like visual profiler.

CUDA_ERROR_PROFILER_NOT_INITIALIZED = 6

Deprecated This error return is deprecated as of CUDA 5.0. It is no longer an error to attempt to enable/disable the profiling via [cuProfilerStart](#) or [cuProfilerStop](#) without initialization.

CUDA_ERROR_PROFILER_ALREADY_STARTED = 7

Deprecated This error return is deprecated as of CUDA 5.0. It is no longer an error to call [cuProfilerStart\(\)](#) when profiling is already enabled.

CUDA_ERROR_PROFILER_ALREADY_STOPPED = 8

Deprecated This error return is deprecated as of CUDA 5.0. It is no longer an error to call [cuProfilerStop\(\)](#) when profiling is already disabled.

CUDA_ERROR_STUB_LIBRARY = 34

This indicates that the CUDA driver that the application has loaded is a stub library.

Applications that run with the stub rather than a real driver loaded will result in CUDA API returning this error.

CUDA_ERROR_NO_DEVICE = 100

This indicates that no CUDA-capable devices were detected by the installed CUDA driver.

CUDA_ERROR_INVALID_DEVICE = 101

This indicates that the device ordinal supplied by the user does not correspond to a valid CUDA device.

CUDA_ERROR_DEVICE_NOT_LICENSED = 102

This error indicates that the Grid license is not applied.

CUDA_ERROR_INVALID_IMAGE = 200

This indicates that the device kernel image is invalid. This can also indicate an invalid CUDA module.

CUDA_ERROR_INVALID_CONTEXT = 201

This most frequently indicates that there is no context bound to the current thread. This can also be returned if the context passed to an API call is not a valid handle (such as a context that has had [cuCtxDestroy\(\)](#) invoked on it). This can also be returned if a user mixes different API versions (i.e. 3010 context with 3020 API calls). See [cuCtxGetApiVersion\(\)](#) for more details.

CUDA_ERROR_CONTEXT_ALREADY_CURRENT = 202

This indicated that the context being supplied as a parameter to the API call was already the active context. [Deprecated](#) This error return is deprecated as of CUDA 3.2. It is no longer an error to attempt to push the active context via [cuCtxPushCurrent\(\)](#).

CUDA_ERROR_MAP_FAILED = 205

This indicates that a map or register operation has failed.

CUDA_ERROR_UNMAP_FAILED = 206

This indicates that an unmap or unregister operation has failed.

CUDA_ERROR_ARRAY_IS_MAPPED = 207

This indicates that the specified array is currently mapped and thus cannot be destroyed.

CUDA_ERROR_ALREADY_MAPPED = 208

This indicates that the resource is already mapped.

CUDA_ERROR_NO_BINARY_FOR_GPU = 209

This indicates that there is no kernel image available that is suitable for the device. This can occur when a user specifies code generation options for a particular CUDA source file that do not include the corresponding device configuration.

CUDA_ERROR_ALREADY_ACQUIRED = 210

This indicates that a resource has already been acquired.

CUDA_ERROR_NOT_MAPPED = 211

This indicates that a resource is not mapped.

CUDA_ERROR_NOT_MAPPED_AS_ARRAY = 212

This indicates that a mapped resource is not available for access as an array.

CUDA_ERROR_NOT_MAPPED_AS_POINTER = 213

This indicates that a mapped resource is not available for access as a pointer.

CUDA_ERROR_ECC_UNCORRECTABLE = 214

This indicates that an uncorrectable ECC error was detected during execution.

CUDA_ERROR_UNSUPPORTED_LIMIT = 215

This indicates that the [CUlimit](#) passed to the API call is not supported by the active device.

CUDA_ERROR_CONTEXT_ALREADY_IN_USE = 216

This indicates that the [CUcontext](#) passed to the API call can only be bound to a single CPU thread at a time but is already bound to a CPU thread.

CUDA_ERROR_PEER_ACCESS_UNSUPPORTED = 217

This indicates that peer access is not supported across the given devices.

CUDA_ERROR_INVALID_PTX = 218

This indicates that a PTX JIT compilation failed.

CUDA_ERROR_INVALID_GRAPHICS_CONTEXT = 219

This indicates an error with OpenGL or DirectX context.

CUDA_ERROR_NVLINK_UNCORRECTABLE = 220

This indicates that an uncorrectable NVLink error was detected during the execution.

CUDA_ERROR_JIT_COMPILER_NOT_FOUND = 221

This indicates that the PTX JIT compiler library was not found.

CUDA_ERROR_UNSUPPORTED_PTX_VERSION = 222

This indicates that the provided PTX was compiled with an unsupported toolchain.

CUDA_ERROR_JIT_COMPILATION_DISABLED = 223

This indicates that the PTX JIT compilation was disabled.

CUDA_ERROR_INVALID_SOURCE = 300

This indicates that the device kernel source is invalid.

CUDA_ERROR_FILE_NOT_FOUND = 301

This indicates that the file specified was not found.

CUDA_ERROR_SHARED_OBJECT_SYMBOL_NOT_FOUND = 302

This indicates that a link to a shared object failed to resolve.

CUDA_ERROR_SHARED_OBJECT_INIT_FAILED = 303

This indicates that initialization of a shared object failed.

CUDA_ERROR_OPERATING_SYSTEM = 304

This indicates that an OS call failed.

CUDA_ERROR_INVALID_HANDLE = 400

This indicates that a resource handle passed to the API call was not valid. Resource handles are opaque types like [CUstream](#) and [CUevent](#).

CUDA_ERROR_ILLEGAL_STATE = 401

This indicates that a resource required by the API call is not in a valid state to perform the requested operation.

CUDA_ERROR_NOT_FOUND = 500

This indicates that a named symbol was not found. Examples of symbols are global/constant variable names, driver function names, texture names, and surface names.

CUDA_ERROR_NOT_READY = 600

This indicates that asynchronous operations issued previously have not completed yet.

This result is not actually an error, but must be indicated differently than [CUDA_SUCCESS](#)

(which indicates completion). Calls that may return this value include [cuEventQuery\(\)](#) and [cuStreamQuery\(\)](#).

CUDA_ERROR_ILLEGAL_ADDRESS = 700

While executing a kernel, the device encountered a load or store instruction on an invalid memory address. This leaves the process in an inconsistent state and any further CUDA work will return the same error. To continue using CUDA, the process must be terminated and relaunched.

CUDA_ERROR_LAUNCH_OUT_OF_RESOURCES = 701

This indicates that a launch did not occur because it did not have appropriate resources. This error usually indicates that the user has attempted to pass too many arguments to the device kernel, or the kernel launch specifies too many threads for the kernel's register count. Passing arguments of the wrong size (i.e. a 64-bit pointer when a 32-bit int is expected) is equivalent to passing too many arguments and can also result in this error.

CUDA_ERROR_LAUNCH_TIMEOUT = 702

This indicates that the device kernel took too long to execute. This can only occur if timeouts are enabled - see the device attribute [CU_DEVICE_ATTRIBUTE_KERNEL_EXEC_TIMEOUT](#) for more information. This leaves the process in an inconsistent state and any further CUDA work will return the same error. To continue using CUDA, the process must be terminated and relaunched.

CUDA_ERROR_LAUNCH_INCOMPATIBLE_TEXTURING = 703

This error indicates a kernel launch that uses an incompatible texturing mode.

CUDA_ERROR_PEER_ACCESS_ALREADY_ENABLED = 704

This error indicates that a call to [cuCtxEnablePeerAccess\(\)](#) is trying to re-enable peer access to a context which has already had peer access to it enabled.

CUDA_ERROR_PEER_ACCESS_NOT_ENABLED = 705

This error indicates that [cuCtxDisablePeerAccess\(\)](#) is trying to disable peer access which has not been enabled yet via [cuCtxEnablePeerAccess\(\)](#).

CUDA_ERROR_PRIMARY_CONTEXT_ACTIVE = 708

This error indicates that the primary context for the specified device has already been initialized.

CUDA_ERROR_CONTEXT_IS_DESTROYED = 709

This error indicates that the context current to the calling thread has been destroyed using [cuCtxDestroy](#), or is a primary context which has not yet been initialized.

CUDA_ERROR_ASSERT = 710

A device-side assert triggered during kernel execution. The context cannot be used anymore, and must be destroyed. All existing device memory allocations from this context are invalid and must be reconstructed if the program is to continue using CUDA.

CUDA_ERROR_TOO_MANY_PEERS = 711

This error indicates that the hardware resources required to enable peer access have been exhausted for one or more of the devices passed to [cuCtxEnablePeerAccess\(\)](#).

CUDA_ERROR_HOST_MEMORY_ALREADY_REGISTERED = 712

This error indicates that the memory range passed to [cuMemHostRegister\(\)](#) has already been registered.

CUDA_ERROR_HOST_MEMORY_NOT_REGISTERED = 713

This error indicates that the pointer passed to [cuMemHostUnregister\(\)](#) does not correspond to any currently registered memory region.

CUDA_ERROR_HARDWARE_STACK_ERROR = 714

While executing a kernel, the device encountered a stack error. This can be due to stack corruption or exceeding the stack size limit. This leaves the process in an inconsistent state and any further CUDA work will return the same error. To continue using CUDA, the process must be terminated and relaunched.

CUDA_ERROR_ILLEGAL_INSTRUCTION = 715

While executing a kernel, the device encountered an illegal instruction. This leaves the process in an inconsistent state and any further CUDA work will return the same error. To continue using CUDA, the process must be terminated and relaunched.

CUDA_ERROR_MISALIGNED_ADDRESS = 716

While executing a kernel, the device encountered a load or store instruction on a memory address which is not aligned. This leaves the process in an inconsistent state and any further CUDA work will return the same error. To continue using CUDA, the process must be terminated and relaunched.

CUDA_ERROR_INVALID_ADDRESS_SPACE = 717

While executing a kernel, the device encountered an instruction which can only operate on memory locations in certain address spaces (global, shared, or local), but was supplied a memory address not belonging to an allowed address space. This leaves the process in an inconsistent state and any further CUDA work will return the same error. To continue using CUDA, the process must be terminated and relaunched.

CUDA_ERROR_INVALID_PC = 718

While executing a kernel, the device program counter wrapped its address space. This leaves the process in an inconsistent state and any further CUDA work will return the same error. To continue using CUDA, the process must be terminated and relaunched.

CUDA_ERROR_LAUNCH_FAILED = 719

An exception occurred on the device while executing a kernel. Common causes include dereferencing an invalid device pointer and accessing out of bounds shared memory. Less common cases can be system specific - more information about these cases can be found in the system specific user guide. This leaves the process in an inconsistent state and any further CUDA work will return the same error. To continue using CUDA, the process must be terminated and relaunched.

CUDA_ERROR_COOPERATIVE_LAUNCH_TOO_LARGE = 720

This error indicates that the number of blocks launched per grid for a kernel that was launched via either [cuLaunchCooperativeKernel](#) or [cuLaunchCooperativeKernelMultiDevice](#) exceeds the maximum number of blocks as allowed by [cuOccupancyMaxActiveBlocksPerMultiprocessor](#) or [cuOccupancyMaxActiveBlocksPerMultiprocessorWithFlags](#) times the number of multiprocessors as specified by the device attribute [CU_DEVICE_ATTRIBUTE_MULTIPROCESSOR_COUNT](#).

CUDA_ERROR_NOT_PERMITTED = 800

This error indicates that the attempted operation is not permitted.

CUDA_ERROR_NOT_SUPPORTED = 801

This error indicates that the attempted operation is not supported on the current system or device.

CUDA_ERROR_SYSTEM_NOT_READY = 802

This error indicates that the system is not yet ready to start any CUDA work. To continue using CUDA, verify the system configuration is in a valid state and all required driver daemons are actively running. More information about this error can be found in the system specific user guide.

CUDA_ERROR_SYSTEM_DRIVER_MISMATCH = 803

This error indicates that there is a mismatch between the versions of the display driver and the CUDA driver. Refer to the compatibility documentation for supported versions.

CUDA_ERROR_COMPAT_NOT_SUPPORTED_ON_DEVICE = 804

This error indicates that the system was upgraded to run with forward compatibility but the visible hardware detected by CUDA does not support this configuration. Refer to the compatibility documentation for the supported hardware matrix or ensure that only supported hardware is visible during initialization via the CUDA_VISIBLE_DEVICES environment variable.

CUDA_ERROR_STREAM_CAPTURE_UNSUPPORTED = 900

This error indicates that the operation is not permitted when the stream is capturing.

CUDA_ERROR_STREAM_CAPTURE_INVALIDATED = 901

This error indicates that the current capture sequence on the stream has been invalidated due to a previous error.

CUDA_ERROR_STREAM_CAPTURE_MERGE = 902

This error indicates that the operation would have resulted in a merge of two independent capture sequences.

CUDA_ERROR_STREAM_CAPTURE_UNMATCHED = 903

This error indicates that the capture was not initiated in this stream.

CUDA_ERROR_STREAM_CAPTURE_UNJOINED = 904

This error indicates that the capture sequence contains a fork that was not joined to the primary stream.

CUDA_ERROR_STREAM_CAPTURE_ISOLATION = 905

This error indicates that a dependency would have been created which crosses the capture sequence boundary. Only implicit in-stream ordering dependencies are allowed to cross the boundary.

CUDA_ERROR_STREAM_CAPTURE_IMPLICIT = 906

This error indicates a disallowed implicit dependency on a current capture sequence from `cudaStreamLegacy`.

CUDA_ERROR_CAPTURED_EVENT = 907

This error indicates that the operation is not permitted on an event which was last recorded in a capturing stream.

CUDA_ERROR_STREAM_CAPTURE_WRONG_THREAD = 908

A stream capture sequence not initiated with the `CU_STREAM_CAPTURE_MODE_RELAXED` argument to `cuStreamBeginCapture` was passed to `cuStreamEndCapture` in a different thread.

CUDA_ERROR_TIMEOUT = 909

This error indicates that the timeout specified for the wait operation has lapsed.

CUDA_ERROR_GRAPH_EXEC_UPDATE_FAILURE = 910

This error indicates that the graph update was not performed because it included changes which violated constraints specific to instantiated graph update.

CUDA_ERROR_UNKNOWN = 999

This indicates that an unknown internal error has occurred.

enum CUshared_carveout

Shared memory carveout configurations. These may be passed to `cuFuncSetAttribute`

Values

CU_SHARED_MEM_CARVEOUT_DEFAULT = -1

No preference for shared memory or L1 (default)

CU_SHARED_MEM_CARVEOUT_MAX_SHARED = 100

Prefer maximum available shared memory, minimum L1 cache

CU_SHARED_MEM_CARVEOUT_MAX_L1 = 0

Prefer maximum available L1 cache, minimum shared memory

enum CUsharedconfig

Shared memory configurations

Values

CU_SHARED_MEM_CONFIG_DEFAULT_BANK_SIZE = 0x00

set default shared memory bank size

CU_SHARED_MEM_CONFIG_FOUR_BYTE_BANK_SIZE = 0x01

set shared memory bank width to four bytes

CU_SHARED_MEM_CONFIG_EIGHT_BYTE_BANK_SIZE = 0x02

set shared memory bank width to eight bytes

enum CUstream_flags

Stream creation flags

Values

CU_STREAM_DEFAULT = 0x0

Default stream flag

CU_STREAM_NON_BLOCKING = 0x1

Stream does not synchronize with stream 0 (the NULL stream)

enum CUstreamAttrID

Stream Attributes

Values

CU_STREAM_ATTRIBUTE_ACCESS_POLICY_WINDOW = 1

Identifier for [CUstreamAttrValue::accessPolicyWindow](#).

CU_STREAM_ATTRIBUTE_SYNCHRONIZATION_POLICY = 3

CUsynchronizationPolicy for work queued up in this stream

enum CUstreamBatchMemOpType

Operations for [cuStreamBatchMemOp](#)

Values

CU_STREAM_MEM_OP_WAIT_VALUE_32 = 1

Represents a [cuStreamWaitValue32](#) operation

CU_STREAM_MEM_OP_WRITE_VALUE_32 = 2

Represents a [cuStreamWriteValue32](#) operation

CU_STREAM_MEM_OP_WAIT_VALUE_64 = 4

Represents a [cuStreamWaitValue64](#) operation

CU_STREAM_MEM_OP_WRITE_VALUE_64 = 5

Represents a [cuStreamWriteValue64](#) operation

CU_STREAM_MEM_OP_FLUSH_REMOTE_WRITES = 3

This has the same effect as [CU_STREAM_WAIT_VALUE_FLUSH](#), but as a standalone operation.

enum CUstreamCaptureMode

Possible modes for stream capture thread interactions. For more details see [cuStreamBeginCapture](#) and [cuThreadExchangeStreamCaptureMode](#)

Values

CU_STREAM_CAPTURE_MODE_GLOBAL = 0

CU_STREAM_CAPTURE_MODE_THREAD_LOCAL = 1

CU_STREAM_CAPTURE_MODE_RELAXED = 2

enum CUstreamCaptureStatus

Possible stream capture statuses returned by [cuStreamIsCapturing](#)

Values

CU_STREAM_CAPTURE_STATUS_NONE = 0

Stream is not capturing

CU_STREAM_CAPTURE_STATUS_ACTIVE = 1

Stream is actively capturing

CU_STREAM_CAPTURE_STATUS_INVALIDATED = 2

Stream is part of a capture sequence that has been invalidated, but not terminated

enum CUstreamUpdateCaptureDependencies_flags

Flags for [cuStreamUpdateCaptureDependencies](#)

Values

CU_STREAM_ADD_CAPTURE_DEPENDENCIES = 0x0

Add new nodes to the dependency set

CU_STREAM_SET_CAPTURE_DEPENDENCIES = 0x1

Replace the dependency set with the new nodes

enum CUstreamWaitValue_flags

Flags for [cuStreamWaitValue32](#) and [cuStreamWaitValue64](#)

Values

CU_STREAM_WAIT_VALUE_GEQ = 0x0

Wait until $(\text{int32_t})[*\text{addr} - \text{value}] \geq 0$ (or int64_t for 64 bit values). Note this is a cyclic comparison which ignores wraparound. (Default behavior.)

CU_STREAM_WAIT_VALUE_EQ = 0x1

Wait until $*\text{addr} == \text{value}$.

CU_STREAM_WAIT_VALUE_AND = 0x2

Wait until $(*\text{addr} \& \text{value}) \neq 0$.

CU_STREAM_WAIT_VALUE_NOR = 0x3

Wait until $\sim(*\text{addr} | \text{value}) \neq 0$. Support for this operation can be queried with [cuDeviceGetAttribute\(\)](#) and [CU_DEVICE_ATTRIBUTE_CAN_USE_STREAM_WAIT_VALUE_NOR](#).

CU_STREAM_WAIT_VALUE_FLUSH = 1 << 30

Follow the wait operation with a flush of outstanding remote writes. This means that, if a remote write operation is guaranteed to have reached the device before the wait can be satisfied, that write is guaranteed to be visible to downstream device work. The device is permitted to reorder remote writes internally. For example, this flag would be required if two remote writes arrive in a defined order, the wait is satisfied by the second write, and downstream work needs to observe the first write.

Support for this operation is restricted to selected platforms and can be queried with `CU_DEVICE_ATTRIBUTE_CAN_USE_WAIT_VALUE_FLUSH`.

enum CUstreamWriteValue_flags

Flags for [cuStreamWriteValue32](#)

Values

CU_STREAM_WRITE_VALUE_DEFAULT = 0x0

Default behavior

CU_STREAM_WRITE_VALUE_NO_MEMORY_BARRIER = 0x1

Permits the write to be reordered with writes which were issued before it, as a performance optimization. Normally, [cuStreamWriteValue32](#) will provide a memory fence before the write, which has similar semantics to `__threadfence_system()` but is scoped to the stream rather than a CUDA thread.

enum CUuserObject_flags

Flags for user objects for graphs

Values

CU_USER_OBJECT_NO_DESTRUCTOR_SYNC = 1

Indicates the destructor execution is not synchronized by any CUDA handle.

enum CUuserObjectRetain_flags

Flags for retaining user object references for graphs

Values

CU_GRAPH_USER_OBJECT_MOVE = 1

Transfer references from the caller rather than creating new references.

typedef struct CUarray_st *CUarray

CUDA array

typedef struct CUctx_st *CUcontext

CUDA context

typedef CUdevice

CUDA device


```
typedef int CUdevice_v1
```

CUDA device

```
typedef CUdeviceptr
```

CUDA device pointer

```
typedef unsigned int CUdeviceptr_v2
```

CUDA device pointer CUdeviceptr is defined as an unsigned integer type whose size matches the size of a pointer on the target platform.

```
typedef struct CUeglStreamConnection_st  
*CUeglStreamConnection
```

CUDA EGLSream Connection

```
typedef struct CUevent_st *CUevent
```

CUDA event

```
typedef struct CUextMemory_st *CUexternalMemory
```

CUDA external memory

```
typedef struct CUextSemaphore_st  
*CUexternalSemaphore
```

CUDA external semaphore

```
typedef struct CUfunc_st *CUfunction
```

CUDA function

```
typedef struct CUgraph_st *CUgraph
```

CUDA graph

```
typedef struct CUgraphExec_st *CUgraphExec
```

CUDA executable graph

```
typedef struct CUgraphicsResource_st  
*CUgraphicsResource
```

CUDA graphics interop resource

```
typedef struct CUgraphNode_st *CUgraphNode
```

CUDA graph node

```
typedef void (CUDA_CB *CUhostFn) (void* userData)
```

CUDA host function

```
typedef struct CUmempoolHandle_st  
*CUmemoryPool
```

CUDA memory pool

```
typedef struct CUmipmappedArray_st  
*CUmipmappedArray
```

CUDA mipmapped array

```
typedef struct CUmod_st *CUmodule
```

CUDA module

```
typedef size_t (CUDA_CB *CUoccupancyB2DSize) (int  
blockSize)
```

Block size to per-block dynamic shared memory mapping for a certain kernel

```
typedef struct CUstream_st *CUstream
```

CUDA stream

```
typedef void (CUDA_CB *CUstreamCallback)  
(CUstream hStream, CUresult status, void* userData)
```

CUDA stream callback

`typedef CUsurfObject`

An opaque value that represents a CUDA surface object

`typedef unsigned long long CUsurfObject_v1`

An opaque value that represents a CUDA surface object

`typedef struct CUsurfref_st *CUsurfref`

CUDA surface reference

`typedef CUtexObject`

An opaque value that represents a CUDA texture object

`typedef unsigned long long CUtexObject_v1`

An opaque value that represents a CUDA texture object

`typedef struct CUtexref_st *CUtexref`

CUDA texture reference

`typedef struct CUuserObject_st *CUuserObject`

CUDA user object for graphs

`#define`

`CU_ARRAY_SPARSE_PROPERTIES_SINGLE_MIPTAIL 0x1`

Indicates that the layered sparse CUDA array or CUDA mipmapped array has a single mip tail region for all layers

`#define CU_DEVICE_CPU ((CUdevice)-1)`

Device that represents the CPU

`#define CU_DEVICE_INVALID ((CUdevice)-2)`

Device that represents an invalid device

```
#define CU_IPC_HANDLE_SIZE 64
```

CUDA IPC handle size

```
#define CU_LAUNCH_PARAM_BUFFER_POINTER  
((void*)0x01)
```

Indicator that the next value in the `extra` parameter to `cuLaunchKernel` will be a pointer to a buffer containing all kernel parameters used for launching kernel \mathfrak{f} . This buffer needs to honor all alignment/padding requirements of the individual parameters. If `CU_LAUNCH_PARAM_BUFFER_SIZE` is not also specified in the `extra` array, then `CU_LAUNCH_PARAM_BUFFER_POINTER` will have no effect.

```
#define CU_LAUNCH_PARAM_BUFFER_SIZE  
((void*)0x02)
```

Indicator that the next value in the `extra` parameter to `cuLaunchKernel` will be a pointer to a `size_t` which contains the size of the buffer specified with `CU_LAUNCH_PARAM_BUFFER_POINTER`. It is required that `CU_LAUNCH_PARAM_BUFFER_POINTER` also be specified in the `extra` array if the value associated with `CU_LAUNCH_PARAM_BUFFER_SIZE` is not zero.

```
#define CU_LAUNCH_PARAM_END ((void*)0x00)
```

End of array terminator for the `extra` parameter to `cuLaunchKernel`

```
#define CU_MEM_CREATE_USAGE_TILE_POOL 0x1
```

This flag if set indicates that the memory will be used as a tile pool.

```
#define CU_MEMHOSTALLOC_DEVICEMAP 0x02
```

If set, host memory is mapped into CUDA address space and `cuMemHostGetDevicePointer()` may be called on the host pointer. Flag for `cuMemHostAlloc()`

```
#define CU_MEMHOSTALLOC_PORTABLE 0x01
```

If set, host memory is portable between CUDA contexts. Flag for `cuMemHostAlloc()`

`#define CU_MEMHOSTALLOC_WRITECOMBINED 0x04`

If set, host memory is allocated as write-combined - fast to write, faster to DMA, slow to read except via SSE4 streaming load instruction (MOVNTDQA). Flag for [cuMemHostAlloc\(\)](#)

`#define CU_MEMHOSTREGISTER_DEVICEMAP 0x02`

If set, host memory is mapped into CUDA address space and [cuMemHostGetDevicePointer\(\)](#) may be called on the host pointer. Flag for [cuMemHostRegister\(\)](#)

`#define CU_MEMHOSTREGISTER_IOMEMORY 0x04`

If set, the passed memory pointer is treated as pointing to some memory-mapped I/O space, e.g. belonging to a third-party PCIe device. On Windows the flag is a no-op. On Linux that memory is marked as non cache-coherent for the GPU and is expected to be physically contiguous. It may return `CUDA_ERROR_NOT_PERMITTED` if run as an unprivileged user, `CUDA_ERROR_NOT_SUPPORTED` on older Linux kernel versions. On all other platforms, it is not supported and `CUDA_ERROR_NOT_SUPPORTED` is returned. Flag for [cuMemHostRegister\(\)](#)

`#define CU_MEMHOSTREGISTER_PORTABLE 0x01`

If set, host memory is portable between CUDA contexts. Flag for [cuMemHostRegister\(\)](#)

`#define CU_MEMHOSTREGISTER_READ_ONLY 0x08`

If set, the passed memory pointer is treated as pointing to memory that is considered read-only by the device. On platforms without `CU_DEVICE_ATTRIBUTE_PAGEABLE_MEMORY_ACCESS_USES_HOST_PAGE_TABLES`, this flag is required in order to register memory mapped to the CPU as read-only. Support for the use of this flag can be queried from the device attribute `CU_DEVICE_ATTRIBUTE_READ_ONLY_HOST_REGISTER_SUPPORTED`. Using this flag with a current context associated with a device that does not have this attribute set will cause [cuMemHostRegister](#) to error with `CUDA_ERROR_NOT_SUPPORTED`.

`#define CU_PARAM_TR_DEFAULT -1`

For texture references loaded into the module, use default texunit from texture reference.

`#define CU_STREAM_LEGACY ((CUstream)0x1)`

Legacy stream handle

Stream handle that can be passed as a CUstream to use an implicit stream with legacy synchronization behavior.

See details of the [synchronization behavior](#).

`#define CU_STREAM_PER_THREAD ((CUstream)0x2)`

Per-thread stream handle

Stream handle that can be passed as a CUstream to use an implicit stream with per-thread synchronization behavior.

See details of the [synchronization behavior](#).

`#define CU_TRSA_OVERRIDE_FORMAT 0x01`

Override the texref format with a format inferred from the array. Flag for [cuTexRefSetArray\(\)](#)

`#define CU_TRSF_DISABLE_TRILINEAR_OPTIMIZATION 0x20`

Disable any trilinear filtering optimizations. Flag for [cuTexRefSetFlags\(\)](#) and [cuTexObjectCreate\(\)](#)

`#define CU_TRSF_NORMALIZED_COORDINATES 0x02`

Use normalized texture coordinates in the range [0,1] instead of [0,dim]. Flag for [cuTexRefSetFlags\(\)](#) and [cuTexObjectCreate\(\)](#)

`#define CU_TRSF_READ_AS_INTEGER 0x01`

Read the texture as integers rather than promoting the values to floats in the range [0,1]. Flag for [cuTexRefSetFlags\(\)](#) and [cuTexObjectCreate\(\)](#)

`#define CU_TRSF_SRGB 0x10`

Perform sRGB->linear conversion during texture read. Flag for [cuTexRefSetFlags\(\)](#) and [cuTexObjectCreate\(\)](#)

#define CUDA_ARRAY3D_2DARRAY 0x01

Deprecated, use `CUDA_ARRAY3D_LAYERED`

#define CUDA_ARRAY3D_COLOR_ATTACHMENT 0x20

This flag indicates that the CUDA array may be bound as a color target in an external graphics API

#define CUDA_ARRAY3D_CUBEMAP 0x04

If set, the CUDA array is a collection of six 2D arrays, representing faces of a cube. The width of such a CUDA array must be equal to its height, and Depth must be six. If `CUDA_ARRAY3D_LAYERED` flag is also set, then the CUDA array is a collection of cubemaps and Depth must be a multiple of six.

#define CUDA_ARRAY3D_DEPTH_TEXTURE 0x10

This flag if set indicates that the CUDA array is a `DEPTH_TEXTURE`.

#define CUDA_ARRAY3D_LAYERED 0x01

If set, the CUDA array is a collection of layers, where each layer is either a 1D or a 2D array and the Depth member of `CUDA_ARRAY3D_DESCRIPTOR` specifies the number of layers, not the depth of a 3D array.

#define CUDA_ARRAY3D_SPARSE 0x40

This flag if set indicates that the CUDA array or CUDA mipmapped array is a sparse CUDA array or CUDA mipmapped array respectively

#define CUDA_ARRAY3D_SURFACE_LDST 0x02

This flag must be set in order to bind a surface reference to the CUDA array

#define CUDA_ARRAY3D_TEXTURE_GATHER 0x08

This flag must be set in order to perform texture gather operations on a CUDA array.

```
#define
CUDA_COOPERATIVE_LAUNCH_MULTI_DEVICE_NO_POST_LA
0x02
```

If set, any subsequent work pushed in a stream that participated in a call to [cuLaunchCooperativeKernelMultiDevice](#) will only wait for the kernel launched on the GPU corresponding to that stream to complete before it begins execution.

```
#define
CUDA_COOPERATIVE_LAUNCH_MULTI_DEVICE_NO_PRE_LA
0x01
```

If set, each kernel launched as part of [cuLaunchCooperativeKernelMultiDevice](#) only waits for prior work in the stream corresponding to that GPU to complete before the kernel begins execution.

```
#define CUDA_EGL_INFINITE_TIMEOUT 0xFFFFFFFF
```

Indicates that timeout for [cuEGLStreamConsumerAcquireFrame](#) is infinite.

```
#define CUDA_EXTERNAL_MEMORY_DEDICATED 0x1
```

Indicates that the external memory object is a dedicated resource

```
#define
CUDA_EXTERNAL_SEMAPHORE_SIGNAL_SKIP_NVSCIBUF_M
0x01
```

When the /p flags parameter of [CUDA_EXTERNAL_SEMAPHORE_SIGNAL_PARAMS](#) contains this flag, it indicates that signaling an external semaphore object should skip performing appropriate memory synchronization operations over all the external memory objects that are imported as [CU_EXTERNAL_MEMORY_HANDLE_TYPE_NVSCIBUF](#), which otherwise are performed by default to ensure data coherency with other importers of the same [NvSciBuf](#) memory objects.


```
#define
CUDA_EXTERNAL_SEMAPHORE_WAIT_SKIP_NVSCIBUF_MEM
0x02
```

When the /p flags parameter of `CUDA_EXTERNAL_SEMAPHORE_WAIT_PARAMS` contains this flag, it indicates that waiting on an external semaphore object should skip performing appropriate memory synchronization operations over all the external memory objects that are imported as `CU_EXTERNAL_MEMORY_HANDLE_TYPE_NVSCIBUF`, which otherwise are performed by default to ensure data coherency with other importers of the same `NvSciBuf` memory objects.

```
#define CUDA_NVSCISYNC_ATTR_SIGNAL 0x1
```

When /p flags of `cuDeviceGetNvSciSyncAttributes` is set to this, it indicates that application needs signaler specific `NvSciSyncAttr` to be filled by `cuDeviceGetNvSciSyncAttributes`.

```
#define CUDA_NVSCISYNC_ATTR_WAIT 0x2
```

When /p flags of `cuDeviceGetNvSciSyncAttributes` is set to this, it indicates that application needs waiter specific `NvSciSyncAttr` to be filled by `cuDeviceGetNvSciSyncAttributes`.

```
#define CUDA_VERSION 11030
```

CUDA API version number

```
#define MAX_PLANES 3
```

Maximum number of planes per frame

6.2. Error Handling

This section describes the error handling functions of the low-level CUDA driver application programming interface.

CUresult cuGetErrorName (CUresult error, const char **pStr)

Gets the string representation of an error code enum name.

Parameters

error

- Error code to convert to string

pStr

- Address of the string pointer.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Sets *pStr to the address of a NULL-terminated string representation of the name of the enum error code error. If the error code is not recognized, [CUDA_ERROR_INVALID_VALUE](#) will be returned and *pStr will be set to the NULL address.

See also:

[CUresult](#), [cudaGetErrorName](#)

CUresult cuGetErrorString (CUresult error, const char **pStr)

Gets the string description of an error code.

Parameters

error

- Error code to convert to string

pStr

- Address of the string pointer.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Sets *pStr to the address of a NULL-terminated string description of the error code error. If the error code is not recognized, [CUDA_ERROR_INVALID_VALUE](#) will be returned and *pStr will be set to the NULL address.

See also:

[CUresult](#), [cudaGetErrorString](#)

6.3. Initialization

This section describes the initialization functions of the low-level CUDA driver application programming interface.

CUresult `culnit` (unsigned int `Flags`)

Initialize the CUDA driver API.

Parameters

Flags

- Initialization flag for CUDA.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_DEVICE](#),
[CUDA_ERROR_SYSTEM_DRIVER_MISMATCH](#),
[CUDA_ERROR_COMPAT_NOT_SUPPORTED_ON_DEVICE](#)

Description

Initializes the driver API and must be called before any other function from the driver API. Currently, the `Flags` parameter must be 0. If `culnit()` has not been called, any function from the driver API will return [CUDA_ERROR_NOT_INITIALIZED](#).

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

6.4. Version Management

This section describes the version management functions of the low-level CUDA driver application programming interface.

CUresult cuDriverGetVersion (int *driverVersion)

Returns the latest CUDA version supported by driver.

Parameters

driverVersion

- Returns the CUDA driver version

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Returns in *driverVersion the version of CUDA supported by the driver. The version is returned as (1000 major + 10 minor). For example, CUDA 9.2 would be represented by 9020.

This function automatically returns [CUDA_ERROR_INVALID_VALUE](#) if driverVersion is NULL.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cudaDriverGetVersion](#), [cudaRuntimeGetVersion](#)

6.5. Device Management

This section describes the device management functions of the low-level CUDA driver application programming interface.

CUresult cuDeviceGet (CUdevice *device, int ordinal)

Returns a handle to a compute device.

Parameters

device

- Returned device handle

ordinal

- Device number to get handle for

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_INVALID_DEVICE](#)

Description

Returns in `*device` a device handle given an ordinal in the range `[0, cuDeviceGetCount\(\)-1]`.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuDeviceGetAttribute](#), [cuDeviceGetCount](#), [cuDeviceGetName](#), [cuDeviceGetUuid](#),
[cuDeviceGetLuid](#), [cuDeviceTotalMem](#)

CUresult cuDeviceGetAttribute (int *pi, CUdevice_attribute attrib, CUdevice dev)

Returns information about the device.

Parameters

pi

- Returned device attribute value

attrib

- Device attribute to query

dev

- Device handle

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_INVALID_DEVICE](#)

Description

Returns in `*pi` the integer value of the attribute `attrib` on device `dev`. The supported attributes are:

- ▶ [CU_DEVICE_ATTRIBUTE_MAX_THREADS_PER_BLOCK](#): Maximum number of threads per block;

- ▶ [CU_DEVICE_ATTRIBUTE_MAX_BLOCK_DIM_X](#): Maximum x-dimension of a block;
- ▶ [CU_DEVICE_ATTRIBUTE_MAX_BLOCK_DIM_Y](#): Maximum y-dimension of a block;
- ▶ [CU_DEVICE_ATTRIBUTE_MAX_BLOCK_DIM_Z](#): Maximum z-dimension of a block;
- ▶ [CU_DEVICE_ATTRIBUTE_MAX_GRID_DIM_X](#): Maximum x-dimension of a grid;
- ▶ [CU_DEVICE_ATTRIBUTE_MAX_GRID_DIM_Y](#): Maximum y-dimension of a grid;
- ▶ [CU_DEVICE_ATTRIBUTE_MAX_GRID_DIM_Z](#): Maximum z-dimension of a grid;
- ▶ [CU_DEVICE_ATTRIBUTE_MAX_SHARED_MEMORY_PER_BLOCK](#): Maximum amount of shared memory available to a thread block in bytes;
- ▶ [CU_DEVICE_ATTRIBUTE_TOTAL_CONSTANT_MEMORY](#): Memory available on device for `__constant__` variables in a CUDA C kernel in bytes;
- ▶ [CU_DEVICE_ATTRIBUTE_WARP_SIZE](#): Warp size in threads;
- ▶ [CU_DEVICE_ATTRIBUTE_MAX_PITCH](#): Maximum pitch in bytes allowed by the memory copy functions that involve memory regions allocated through `cuMemAllocPitch()`;
- ▶ [CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE1D_WIDTH](#): Maximum 1D texture width;
- ▶ [CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE1D_LINEAR_WIDTH](#): Maximum width for a 1D texture bound to linear memory;
- ▶ [CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE1D_MIPMAPPED_WIDTH](#): Maximum mipmapped 1D texture width;
- ▶ [CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_WIDTH](#): Maximum 2D texture width;
- ▶ [CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_HEIGHT](#): Maximum 2D texture height;
- ▶ [CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_LINEAR_WIDTH](#): Maximum width for a 2D texture bound to linear memory;
- ▶ [CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_LINEAR_HEIGHT](#): Maximum height for a 2D texture bound to linear memory;
- ▶ [CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_LINEAR_PITCH](#): Maximum pitch in bytes for a 2D texture bound to linear memory;
- ▶ [CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_MIPMAPPED_WIDTH](#): Maximum mipmapped 2D texture width;
- ▶ [CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_MIPMAPPED_HEIGHT](#): Maximum mipmapped 2D texture height;
- ▶ [CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE3D_WIDTH](#): Maximum 3D texture width;
- ▶ [CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE3D_HEIGHT](#): Maximum 3D texture height;
- ▶ [CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE3D_DEPTH](#): Maximum 3D texture depth;
- ▶ [CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE3D_WIDTH_ALTERNATE](#): Alternate maximum 3D texture width, 0 if no alternate maximum 3D texture size is supported;
- ▶ [CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE3D_HEIGHT_ALTERNATE](#): Alternate maximum 3D texture height, 0 if no alternate maximum 3D texture size is supported;

- ▶ CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE3D_DEPTH_ALTERNATE: Alternate maximum 3D texture depth, 0 if no alternate maximum 3D texture size is supported;
- ▶ CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURECUBEMAP_WIDTH: Maximum cubemap texture width or height;
- ▶ CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE1D_LAYERED_WIDTH: Maximum 1D layered texture width;
- ▶ CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE1D_LAYERED_LAYERS: Maximum layers in a 1D layered texture;
- ▶ CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_LAYERED_WIDTH: Maximum 2D layered texture width;
- ▶ CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_LAYERED_HEIGHT: Maximum 2D layered texture height;
- ▶ CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_LAYERED_LAYERS: Maximum layers in a 2D layered texture;
- ▶ CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURECUBEMAP_LAYERED_WIDTH: Maximum cubemap layered texture width or height;
- ▶ CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURECUBEMAP_LAYERED_LAYERS: Maximum layers in a cubemap layered texture;
- ▶ CU_DEVICE_ATTRIBUTE_MAXIMUM_SURFACE1D_WIDTH: Maximum 1D surface width;
- ▶ CU_DEVICE_ATTRIBUTE_MAXIMUM_SURFACE2D_WIDTH: Maximum 2D surface width;
- ▶ CU_DEVICE_ATTRIBUTE_MAXIMUM_SURFACE2D_HEIGHT: Maximum 2D surface height;
- ▶ CU_DEVICE_ATTRIBUTE_MAXIMUM_SURFACE3D_WIDTH: Maximum 3D surface width;
- ▶ CU_DEVICE_ATTRIBUTE_MAXIMUM_SURFACE3D_HEIGHT: Maximum 3D surface height;
- ▶ CU_DEVICE_ATTRIBUTE_MAXIMUM_SURFACE3D_DEPTH: Maximum 3D surface depth;
- ▶ CU_DEVICE_ATTRIBUTE_MAXIMUM_SURFACE1D_LAYERED_WIDTH: Maximum 1D layered surface width;
- ▶ CU_DEVICE_ATTRIBUTE_MAXIMUM_SURFACE1D_LAYERED_LAYERS: Maximum layers in a 1D layered surface;
- ▶ CU_DEVICE_ATTRIBUTE_MAXIMUM_SURFACE2D_LAYERED_WIDTH: Maximum 2D layered surface width;
- ▶ CU_DEVICE_ATTRIBUTE_MAXIMUM_SURFACE2D_LAYERED_HEIGHT: Maximum 2D layered surface height;
- ▶ CU_DEVICE_ATTRIBUTE_MAXIMUM_SURFACE2D_LAYERED_LAYERS: Maximum layers in a 2D layered surface;
- ▶ CU_DEVICE_ATTRIBUTE_MAXIMUM_SURFACECUBEMAP_WIDTH: Maximum cubemap surface width;
- ▶ CU_DEVICE_ATTRIBUTE_MAXIMUM_SURFACECUBEMAP_LAYERED_WIDTH: Maximum cubemap layered surface width;

- ▶ CU_DEVICE_ATTRIBUTE_MAXIMUM_SURFACECUBEMAP_LAYERED_LAYERS: Maximum layers in a cubemap layered surface;
- ▶ CU_DEVICE_ATTRIBUTE_MAX_REGISTERS_PER_BLOCK: Maximum number of 32-bit registers available to a thread block;
- ▶ CU_DEVICE_ATTRIBUTE_CLOCK_RATE: The typical clock frequency in kilohertz;
- ▶ CU_DEVICE_ATTRIBUTE_TEXTURE_ALIGNMENT: Alignment requirement; texture base addresses aligned to textureAlign bytes do not need an offset applied to texture fetches;
- ▶ CU_DEVICE_ATTRIBUTE_TEXTURE_PITCH_ALIGNMENT: Pitch alignment requirement for 2D texture references bound to pitched memory;
- ▶ CU_DEVICE_ATTRIBUTE_GPU_OVERLAP: 1 if the device can concurrently copy memory between host and device while executing a kernel, or 0 if not;
- ▶ CU_DEVICE_ATTRIBUTE_MULTIPROCESSOR_COUNT: Number of multiprocessors on the device;
- ▶ CU_DEVICE_ATTRIBUTE_KERNEL_EXEC_TIMEOUT: 1 if there is a run time limit for kernels executed on the device, or 0 if not;
- ▶ CU_DEVICE_ATTRIBUTE_INTEGRATED: 1 if the device is integrated with the memory subsystem, or 0 if not;
- ▶ CU_DEVICE_ATTRIBUTE_CAN_MAP_HOST_MEMORY: 1 if the device can map host memory into the CUDA address space, or 0 if not;
- ▶ CU_DEVICE_ATTRIBUTE_COMPUTE_MODE: Compute mode that device is currently in. Available modes are as follows:
 - ▶ CU_COMPUTEMODE_DEFAULT: Default mode - Device is not restricted and can have multiple CUDA contexts present at a single time.
 - ▶ CU_COMPUTEMODE_PROHIBITED: Compute-prohibited mode - Device is prohibited from creating new CUDA contexts.
 - ▶ CU_COMPUTEMODE_EXCLUSIVE_PROCESS: Compute-exclusive-process mode - Device can have only one context used by a single process at a time.
- ▶ CU_DEVICE_ATTRIBUTE_CONCURRENT_KERNELS: 1 if the device supports executing multiple kernels within the same context simultaneously, or 0 if not. It is not guaranteed that multiple kernels will be resident on the device concurrently so this feature should not be relied upon for correctness;
- ▶ CU_DEVICE_ATTRIBUTE_ECC_ENABLED: 1 if error correction is enabled on the device, 0 if error correction is disabled or not supported by the device;
- ▶ CU_DEVICE_ATTRIBUTE_PCI_BUS_ID: PCI bus identifier of the device;
- ▶ CU_DEVICE_ATTRIBUTE_PCI_DEVICE_ID: PCI device (also known as slot) identifier of the device;
- ▶ CU_DEVICE_ATTRIBUTE_PCI_DOMAIN_ID: PCI domain identifier of the device
- ▶ CU_DEVICE_ATTRIBUTE_TCC_DRIVER: 1 if the device is using a TCC driver. TCC is only available on Tesla hardware running Windows Vista or later;

- ▶ CU_DEVICE_ATTRIBUTE_MEMORY_CLOCK_RATE: Peak memory clock frequency in kilohertz;
- ▶ CU_DEVICE_ATTRIBUTE_GLOBAL_MEMORY_BUS_WIDTH: Global memory bus width in bits;
- ▶ CU_DEVICE_ATTRIBUTE_L2_CACHE_SIZE: Size of L2 cache in bytes. 0 if the device doesn't have L2 cache;
- ▶ CU_DEVICE_ATTRIBUTE_MAX_THREADS_PER_MULTIPROCESSOR: Maximum resident threads per multiprocessor;
- ▶ CU_DEVICE_ATTRIBUTE_UNIFIED_ADDRESSING: 1 if the device shares a unified address space with the host, or 0 if not;
- ▶ CU_DEVICE_ATTRIBUTE_COMPUTE_CAPABILITY_MAJOR: Major compute capability version number;
- ▶ CU_DEVICE_ATTRIBUTE_COMPUTE_CAPABILITY_MINOR: Minor compute capability version number;
- ▶ CU_DEVICE_ATTRIBUTE_GLOBAL_L1_CACHE_SUPPORTED: 1 if device supports caching globals in L1 cache, 0 if caching globals in L1 cache is not supported by the device;
- ▶ CU_DEVICE_ATTRIBUTE_LOCAL_L1_CACHE_SUPPORTED: 1 if device supports caching locals in L1 cache, 0 if caching locals in L1 cache is not supported by the device;
- ▶ CU_DEVICE_ATTRIBUTE_MAX_SHARED_MEMORY_PER_MULTIPROCESSOR: Maximum amount of shared memory available to a multiprocessor in bytes; this amount is shared by all thread blocks simultaneously resident on a multiprocessor;
- ▶ CU_DEVICE_ATTRIBUTE_MAX_REGISTERS_PER_MULTIPROCESSOR: Maximum number of 32-bit registers available to a multiprocessor; this number is shared by all thread blocks simultaneously resident on a multiprocessor;
- ▶ CU_DEVICE_ATTRIBUTE_MANAGED_MEMORY: 1 if device supports allocating managed memory on this system, 0 if allocating managed memory is not supported by the device on this system.
- ▶ CU_DEVICE_ATTRIBUTE_MULTI_GPU_BOARD: 1 if device is on a multi-GPU board, 0 if not.
- ▶ CU_DEVICE_ATTRIBUTE_MULTI_GPU_BOARD_GROUP_ID: Unique identifier for a group of devices associated with the same board. Devices on the same multi-GPU board will share the same identifier.
- ▶ CU_DEVICE_ATTRIBUTE_HOST_NATIVE_ATOMIC_SUPPORTED: 1 if Link between the device and the host supports native atomic operations.
- ▶ CU_DEVICE_ATTRIBUTE_SINGLE_TO_DOUBLE_PRECISION_PERF_RATIO: Ratio of single precision performance (in floating-point operations per second) to double precision performance.
- ▶ CU_DEVICE_ATTRIBUTE_PAGEABLE_MEMORY_ACCESS: Device supports coherently accessing pageable memory without calling `cudaHostRegister` on it.

- ▶ CU_DEVICE_ATTRIBUTE_CONCURRENT_MANAGED_ACCESS: Device can coherently access managed memory concurrently with the CPU.
- ▶ CU_DEVICE_ATTRIBUTE_COMPUTE_PREEMPTION_SUPPORTED: Device supports Compute Preemption.
- ▶ CU_DEVICE_ATTRIBUTE_CAN_USE_HOST_POINTER_FOR_REGISTERED_MEM: Device can access host registered memory at the same virtual address as the CPU.
- ▶ CU_DEVICE_ATTRIBUTE_MAX_SHARED_MEMORY_PER_BLOCK_OPTIN: The maximum per block shared memory size supported on this device. This is the maximum value that can be opted into when using the `cuFuncSetAttribute()` call. For more details see CU_FUNC_ATTRIBUTE_MAX_DYNAMIC_SHARED_SIZE_BYTES
- ▶ CU_DEVICE_ATTRIBUTE_PAGEABLE_MEMORY_ACCESS_USES_HOST_PAGE_TABLES: Device accesses pageable memory via the host's page tables.
- ▶ CU_DEVICE_ATTRIBUTE_DIRECT_MANAGED_MEM_ACCESS_FROM_HOST: The host can directly access managed memory on the device without migration.
- ▶ CU_DEVICE_ATTRIBUTE_VIRTUAL_MEMORY_MANAGEMENT_SUPPORTED: Device supports virtual memory management APIs like `cuMemAddressReserve`, `cuMemCreate`, `cuMemMap` and related APIs
- ▶ CU_DEVICE_ATTRIBUTE_HANDLE_TYPE_POSIX_FILE_DESCRIPTOR_SUPPORTED: Device supports exporting memory to a posix file descriptor with `cuMemExportToShareableHandle`, if requested via `cuMemCreate`
- ▶ CU_DEVICE_ATTRIBUTE_HANDLE_TYPE_WIN32_HANDLE_SUPPORTED: Device supports exporting memory to a Win32 NT handle with `cuMemExportToShareableHandle`, if requested via `cuMemCreate`
- ▶ CU_DEVICE_ATTRIBUTE_HANDLE_TYPE_WIN32_KMT_HANDLE_SUPPORTED: Device supports exporting memory to a Win32 KMT handle with `cuMemExportToShareableHandle`, if requested `cuMemCreate`
- ▶ CU_DEVICE_ATTRIBUTE_MAX_PERSISTING_L2_CACHE_SIZE: Maximum L2 persisting lines capacity setting in bytes.
- ▶ CU_DEVICE_ATTRIBUTE_MAX_ACCESS_POLICY_WINDOW_SIZE: Maximum value of `CUaccessPolicyWindow::num_bytes`.
- ▶ CU_DEVICE_ATTRIBUTE_MAX_BLOCKS_PER_MULTIPROCESSOR: Maximum number of thread blocks that can reside on a multiprocessor.
- ▶ CU_DEVICE_ATTRIBUTE_GENERIC_COMPRESSION_SUPPORTED: Device supports compressible memory allocation via `cuMemCreate`
- ▶ CU_DEVICE_ATTRIBUTE_RESERVED_SHARED_MEMORY_PER_BLOCK: Amount of shared memory per block reserved by CUDA driver in bytes.
- ▶ CU_DEVICE_ATTRIBUTE_READ_ONLY_HOST_REGISTER_SUPPORTED: Device supports using the `cuMemHostRegister` flag `CU_MEMHOSTREGISTER_READ_ONLY` to register memory that must be mapped as read-only to the GPU

- ▶ [CU_DEVICE_ATTRIBUTE_MEMORY_POOLS_SUPPORTED](#): Device supports using the [cuMemAllocAsync](#) and [cuMemPool](#) family of APIs

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuDeviceGetCount](#), [cuDeviceGetName](#), [cuDeviceGetUuid](#), [cuDeviceGet](#), [cuDeviceTotalMem](#), [cudaDeviceGetAttribute](#), [cudaGetDeviceProperties](#)

CUresult cuDeviceGetCount (int *count)

Returns the number of compute-capable devices.

Parameters

count

- Returned number of compute-capable devices

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Returns in *count the number of devices with compute capability greater than or equal to 2.0 that are available for execution. If there is no such device, [cuDeviceGetCount\(\)](#) returns 0.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuDeviceGetAttribute](#), [cuDeviceGetName](#), [cuDeviceGetUuid](#), [cuDeviceGetLuid](#), [cuDeviceGet](#), [cuDeviceTotalMem](#), [cudaGetDeviceCount](#)

CUresult cuDeviceGetDefaultMemPool (CUmemoryPool *pool_out, CUdevice dev)

Returns the default mempool of a device.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_DEVICE](#), [CUDA_ERROR_NOT_SUPPORTED](#)

Description

The default mempool of a device contains device memory from that device.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuMemAllocAsync](#), [cuMemPoolTrimTo](#), [cuMemPoolGetAttribute](#), [cuMemPoolSetAttribute](#), [cuMemPoolSetAccess](#), [cuDeviceGetMemPool](#), [cuMemPoolCreate](#)

CUresult cuDeviceGetLuid (char *luid, unsigned int *deviceNodeMask, CUdevice dev)

Return an LUID and device node mask for the device.

Parameters

luid

- Returned LUID

deviceNodeMask

- Returned device node mask

dev

- Device to get identifier string for

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_DEVICE](#)

Description

Return identifying information (`luid` and `deviceNodeMask`) to allow matching device with graphics APIs.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuDeviceGetAttribute](#), [cuDeviceGetCount](#), [cuDeviceGetName](#), [cuDeviceGet](#), [cuDeviceTotalMem](#), [cudaGetDeviceProperties](#)

CUresult cuDeviceGetMemPool (CUmemoryPool *pool, CUdevice dev)

Gets the current mempool for a device.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Returns the last pool provided to [cuDeviceSetMemPool](#) for this device or the device's default memory pool if [cuDeviceSetMemPool](#) has never been called. By default the current mempool is the default mempool for a device. Otherwise the returned pool must have been set with [cuDeviceSetMemPool](#).

See also:

[cuDeviceGetDefaultMemPool](#), [cuMemPoolCreate](#), [cuDeviceSetMemPool](#)

CUresult cuDeviceGetName (char *name, int len, CUdevice dev)

Returns an identifier string for the device.

Parameters

name

- Returned identifier string for the device

len

- Maximum length of string to store in name

dev

- Device to get identifier string for

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_INVALID_DEVICE](#)

Description

Returns an ASCII string identifying the device `dev` in the NULL-terminated string pointed to by `name`. `len` specifies the maximum length of the string that may be returned.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuDeviceGetAttribute](#), [cuDeviceGetUuid](#), [cuDeviceGetLuid](#), [cuDeviceGetCount](#), [cuDeviceGet](#),
[cuDeviceTotalMem](#), [cudaGetDeviceProperties](#)

CUresult cuDeviceGetNvSciSyncAttributes (void *nvSciSyncAttrList, CUdevice dev, int flags)

Return NvSciSync attributes that this device can support.

Parameters**nvSciSyncAttrList**

- Return NvSciSync attributes supported.

dev

- Valid Cuda Device to get NvSciSync attributes for.

flags

- flags describing NvSciSync usage.

Description

Returns in `nvSciSyncAttrList`, the properties of NvSciSync that this CUDA device, `dev` can support. The returned `nvSciSyncAttrList` can be used to create an NvSciSync object that matches this device's capabilities.

If `NvSciSyncAttrKey_RequiredPerm` field in `nvSciSyncAttrList` is already set this API will return [CUDA_ERROR_INVALID_VALUE](#).

The applications should set `nvSciSyncAttrList` to a valid `NvSciSyncAttrList` failing which this API will return [CUDA_ERROR_INVALID_HANDLE](#).

The `flags` controls how applications intends to use the `NvSciSync` created from the `nvSciSyncAttrList`. The valid flags are:

- ▶ [CUDA_NVSCISYNC_ATTR_SIGNAL](#), specifies that the applications intends to signal an `NvSciSync` on this CUDA device.
- ▶ [CUDA_NVSCISYNC_ATTR_WAIT](#), specifies that the applications intends to wait on an `NvSciSync` on this CUDA device.

At least one of these flags must be set, failing which the API returns [CUDA_ERROR_INVALID_VALUE](#). Both the flags are orthogonal to one another: a developer may set both these flags that allows to set both wait and signal specific attributes in the same `nvSciSyncAttrList`.

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_INVALID_DEVICE](#), [CUDA_ERROR_NOT_SUPPORTED](#), [CUDA_ERROR_OUT_OF_MEMORY](#)

See also:

[cuImportExternalSemaphore](#), [cuDestroyExternalSemaphore](#), [cuSignalExternalSemaphoresAsync](#), [cuWaitExternalSemaphoresAsync](#)

CUresult cuDeviceGetTexture1DLinearMaxWidth (size_t *maxWidthInElements, CUarray_format format, unsigned numChannels, CUdevice dev)

Returns the maximum number of elements allocatable in a 1D linear texture for a given texture element size.

Parameters

maxWidthInElements

- Returned maximum number of texture elements allocatable for given `format` and `numChannels`.

format

- Texture format.

numChannels

- Number of channels per texture element.

dev

- Device handle.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_INVALID_DEVICE](#)

Description

Returns in `maxWidthInElements` the maximum number of texture elements allocatable in a 1D linear texture for given `format` and `numChannels`.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuDeviceGetAttribute](#), [cuDeviceGetCount](#), [cuDeviceGetName](#), [cuDeviceGetUuid](#), [cuDeviceGet](#),
[cudaMemGetInfo](#), [cuDeviceTotalMem](#)

CUresult cuDeviceGetUuid (CUuuid *uuid, CUdevice dev)

Return an UUID for the device.

Parameters

uuid

- Returned UUID

dev

- Device to get identifier string for

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_DEVICE](#)

Description

Returns 16-octets identifying the device `dev` in the structure pointed by the `uuid`.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuDeviceGetAttribute](#), [cuDeviceGetCount](#), [cuDeviceGetName](#), [cuDeviceGetLuid](#), [cuDeviceGet](#), [cuDeviceTotalMem](#), [cudaGetDeviceProperties](#)

CUresult cuDeviceSetMemPool (CUdevice dev, CUmemoryPool pool)

Sets the current memory pool of a device.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

The memory pool must be local to the specified device. [cuMemAllocAsync](#) allocates from the current mempool of the provided stream's device. By default, a device's current memory pool is its default memory pool.

**Note:**

Use [cuMemAllocFromPoolAsync](#) to specify asynchronous allocations from a device different than the one the stream runs on.

See also:

[cuDeviceGetDefaultMemPool](#), [cuDeviceGetMemPool](#), [cuMemPoolCreate](#), [cuMemPoolDestroy](#), [cuMemAllocFromPoolAsync](#)

CUresult cuDeviceTotalMem (size_t *bytes, CUdevice dev)

Returns the total amount of memory on the device.

Parameters**bytes**

- Returned memory available on device in bytes

dev

- Device handle

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_DEVICE](#)

Description

Returns in `*bytes` the total amount of memory available on the device `dev` in bytes.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuDeviceGetAttribute](#), [cuDeviceGetCount](#), [cuDeviceGetName](#), [cuDeviceGetUuid](#), [cuDeviceGet](#), [cudaMemGetInfo](#)

6.6. Device Management [DEPRECATED]

This section describes the device management functions of the low-level CUDA driver application programming interface.

CUresult cuDeviceComputeCapability (int *major, int *minor, CUdevice dev)

Returns the compute capability of the device.

Parameters

major

- Major revision number

minor

- Minor revision number

dev

- Device handle

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_DEVICE](#)

Description

Deprecated

This function was deprecated as of CUDA 5.0 and its functionality superseded by [cuDeviceGetAttribute\(\)](#).

Returns in `*major` and `*minor` the major and minor revision numbers that define the compute capability of the device `dev`.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuDeviceGetAttribute](#), [cuDeviceGetCount](#), [cuDeviceGetName](#), [cuDeviceGetUuid](#), [cuDeviceGet](#), [cuDeviceTotalMem](#)

CUresult cuDeviceGetProperties (CUdevprop *prop, CUdevice dev)

Returns properties for a selected device.

Parameters

prop

- Returned properties of device

dev

- Device to get properties for

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_DEVICE](#)

Description

Deprecated

This function was deprecated as of CUDA 5.0 and replaced by [cuDeviceGetAttribute\(\)](#).

Returns in `*prop` the properties of device `dev`. The `CUdevprop` structure is defined as:

```
↑
typedef struct CUdevprop_st {
    int maxThreadsPerBlock;
    int maxThreadsDim[3];
    int maxGridSize[3];
    int sharedMemPerBlock;
    int totalConstantMemory;
    int SIMDWidth;
    int memPitch;
    int regsPerBlock;
    int clockRate;
    int textureAlign
} CUdevprop;
```

where:

- ▶ `maxThreadsPerBlock` is the maximum number of threads per block;
- ▶ `maxThreadsDim[3]` is the maximum sizes of each dimension of a block;
- ▶ `maxGridSize[3]` is the maximum sizes of each dimension of a grid;
- ▶ `sharedMemPerBlock` is the total amount of shared memory available per block in bytes;
- ▶ `totalConstantMemory` is the total amount of constant memory available on the device in bytes;
- ▶ `SIMDWidth` is the warp size;
- ▶ `memPitch` is the maximum pitch allowed by the memory copy functions that involve memory regions allocated through [cuMemAllocPitch\(\)](#);
- ▶ `regsPerBlock` is the total number of registers available per block;
- ▶ `clockRate` is the clock frequency in kilohertz;
- ▶ `textureAlign` is the alignment requirement; texture base addresses that are aligned to `textureAlign` bytes do not need an offset applied to texture fetches.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuDeviceGetAttribute](#), [cuDeviceGetCount](#), [cuDeviceGetName](#), [cuDeviceGetUuid](#), [cuDeviceGet](#), [cuDeviceTotalMem](#)

6.7. Primary Context Management

This section describes the primary context management functions of the low-level CUDA driver application programming interface.

The primary context is unique per device and shared with the CUDA runtime API. These functions allow integration with other libraries using CUDA.

`CUresult cuDevicePrimaryCtxGetState (CUdevice dev, unsigned int *flags, int *active)`

Get the state of the primary context.

Parameters

dev

- Device to get primary context flags for

flags

- Pointer to store flags

active

- Pointer to store context state; 0 = inactive, 1 = active

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_DEVICE](#), [CUDA_ERROR_INVALID_VALUE](#),

Description

Returns in `*flags` the flags for the primary context of `dev`, and in `*active` whether it is active. See [cuDevicePrimaryCtxSetFlags](#) for flag values.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuDevicePrimaryCtxSetFlags](#), [cuCtxGetFlags](#), [cudaGetDeviceFlags](#)

CUresult cuDevicePrimaryCtxRelease (CUdevice dev)

Release the primary context on the GPU.

Parameters**dev**

- Device which primary context is released

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_DEVICE](#), [CUDA_ERROR_INVALID_CONTEXT](#)

Description

Releases the primary context interop on the device. A retained context should always be released once the user is done using it. The context is automatically reset once the last reference to it is released. This behavior is different when the primary context was retained by the CUDA runtime from CUDA 4.0 and earlier. In this case, the primary context remains always active.

Releasing a primary context that has not been previously retained will fail with [CUDA_ERROR_INVALID_CONTEXT](#).

Please note that unlike [cuCtxDestroy\(\)](#) this method does not pop the context from stack in any circumstances.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuDevicePrimaryCtxRetain](#), [cuCtxDestroy](#), [cuCtxGetApiVersion](#), [cuCtxGetCacheConfig](#), [cuCtxGetDevice](#), [cuCtxGetFlags](#), [cuCtxGetLimit](#), [cuCtxPopCurrent](#), [cuCtxPushCurrent](#), [cuCtxSetCacheConfig](#), [cuCtxSetLimit](#), [cuCtxSynchronize](#)

CUresult cuDevicePrimaryCtxReset (CUdevice dev)

Destroy all allocations and reset all state on the primary context.

Parameters

dev

- Device for which primary context is destroyed

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_DEVICE](#), [CUDA_ERROR_PRIMARY_CONTEXT_ACTIVE](#)

Description

Explicitly destroys and cleans up all resources associated with the current device in the current process.

Note that it is responsibility of the calling function to ensure that no other module in the process is using the device any more. For that reason it is recommended to use [cuDevicePrimaryCtxRelease\(\)](#) in most cases. However it is safe for other modules to call [cuDevicePrimaryCtxRelease\(\)](#) even after resetting the device. Resetting the primary context does not release it, an application that has retained the primary context should explicitly release its usage.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuDevicePrimaryCtxRetain](#), [cuDevicePrimaryCtxRelease](#), [cuCtxGetApiVersion](#),
[cuCtxGetCacheConfig](#), [cuCtxGetDevice](#), [cuCtxGetFlags](#), [cuCtxGetLimit](#), [cuCtxPopCurrent](#),
[cuCtxPushCurrent](#), [cuCtxSetCacheConfig](#), [cuCtxSetLimit](#), [cuCtxSynchronize](#), [cudaDeviceReset](#)

CUresult cuDevicePrimaryCtxRetain (CUcontext *pctx, CUdevice dev)

Retain the primary context on the GPU.

Parameters

pctx

- Returned context handle of the new context

dev

- Device for which primary context is requested

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_DEVICE](#),
[CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_OUT_OF_MEMORY](#),
[CUDA_ERROR_UNKNOWN](#)

Description

Retains the primary context on the device. Once the user successfully retains the primary context, the primary context will be active and available to the user until the user releases it with [cuDevicePrimaryCtxRelease\(\)](#) or resets it with [cuDevicePrimaryCtxReset\(\)](#). Unlike [cuCtxCreate\(\)](#) the newly retained context is not pushed onto the stack.

Retaining the primary context for the first time will fail with [CUDA_ERROR_UNKNOWN](#) if the compute mode of the device is [CU_COMPUTEMODE_PROHIBITED](#). The function [cuDeviceGetAttribute\(\)](#) can be used with [CU_DEVICE_ATTRIBUTE_COMPUTE_MODE](#) to determine the compute mode of the device. The nvidia-smi tool can be used to set the compute mode for devices. Documentation for nvidia-smi can be obtained by passing a -h option to it.

Please note that the primary context always supports pinned allocations. Other flags can be specified by [cuDevicePrimaryCtxSetFlags\(\)](#).



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuDevicePrimaryCtxRelease](#), [cuDevicePrimaryCtxSetFlags](#), [cuCtxCreate](#), [cuCtxGetApiVersion](#), [cuCtxGetCacheConfig](#), [cuCtxGetDevice](#), [cuCtxGetFlags](#), [cuCtxGetLimit](#), [cuCtxPopCurrent](#), [cuCtxPushCurrent](#), [cuCtxSetCacheConfig](#), [cuCtxSetLimit](#), [cuCtxSynchronize](#)

CUresult cuDevicePrimaryCtxSetFlags (CUdevice dev, unsigned int flags)

Set flags for the primary context.

Parameters

dev

- Device for which the primary context flags are set

flags

- New flags for the device

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_DEVICE](#), [CUDA_ERROR_INVALID_VALUE](#),

Description

Sets the flags for the primary context on the device overwriting perviously set ones.

The three LSBs of the `flags` parameter can be used to control how the OS thread, which owns the CUDA context at the time of an API call, interacts with the OS scheduler when waiting for results from the GPU. Only one of the scheduling flags can be set when creating a context.

- ▶ [CU_CTX_SCHED_SPIN](#): Instruct CUDA to actively spin when waiting for results from the GPU. This can decrease latency when waiting for the GPU, but may lower the performance of CPU threads if they are performing work in parallel with the CUDA thread.
- ▶ [CU_CTX_SCHED_YIELD](#): Instruct CUDA to yield its thread when waiting for results from the GPU. This can increase latency when waiting for the GPU, but can increase the performance of CPU threads performing work in parallel with the GPU.
- ▶ [CU_CTX_SCHED_BLOCKING_SYNC](#): Instruct CUDA to block the CPU thread on a synchronization primitive when waiting for the GPU to finish work.
- ▶ [CU_CTX_BLOCKING_SYNC](#): Instruct CUDA to block the CPU thread on a synchronization primitive when waiting for the GPU to finish work.

Deprecated: This flag was deprecated as of CUDA 4.0 and was replaced with [CU_CTX_SCHED_BLOCKING_SYNC](#).

- ▶ [CU_CTX_SCHED_AUTO](#): The default value if the `flags` parameter is zero, uses a heuristic based on the number of active CUDA contexts in the process C and the number of logical

processors in the system P . If $C > P$, then CUDA will yield to other OS threads when waiting for the GPU ([CU_CTX_SCHED_YIELD](#)), otherwise CUDA will not yield while waiting for results and actively spin on the processor ([CU_CTX_SCHED_SPIN](#)). Additionally, on Tegra devices, [CU_CTX_SCHED_AUTO](#) uses a heuristic based on the power profile of the platform and may choose [CU_CTX_SCHED_BLOCKING_SYNC](#) for low-powered devices.

- ▶ [CU_CTX_LMEM_RESIZE_TO_MAX](#): Instruct CUDA to not reduce local memory after resizing local memory for a kernel. This can prevent thrashing by local memory allocations when launching many kernels with high local memory usage at the cost of potentially increased memory usage.

Deprecated: This flag is deprecated and the behavior enabled by this flag is now the default and cannot be disabled.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuDevicePrimaryCtxRetain](#), [cuDevicePrimaryCtxGetState](#), [cuCtxCreate](#), [cuCtxGetFlags](#), [cudaSetDeviceFlags](#)

6.8. Context Management

This section describes the context management functions of the low-level CUDA driver application programming interface.

Please note that some functions are described in [Primary Context Management](#) section.

CUresult cuCtxCreate (CUcontext *pctx, unsigned int flags, CUdevice dev)

Create a CUDA context.

Parameters

pctx

- Returned context handle of the new context

flags

- Context creation flags

dev

- Device to create context on

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_DEVICE](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_OUT_OF_MEMORY](#), [CUDA_ERROR_UNKNOWN](#)

Description



Note:

In most cases it is recommended to use [cuDevicePrimaryCtxRetain](#).

Creates a new CUDA context and associates it with the calling thread. The `flags` parameter is described below. The context is created with a usage count of 1 and the caller of [cuCtxCreate\(\)](#) must call [cuCtxDestroy\(\)](#) or when done using the context. If a context is already current to the thread, it is supplanted by the newly created context and may be restored by a subsequent call to [cuCtxPopCurrent\(\)](#).

The three LSBs of the `flags` parameter can be used to control how the OS thread, which owns the CUDA context at the time of an API call, interacts with the OS scheduler when waiting for results from the GPU. Only one of the scheduling flags can be set when creating a context.

- ▶ [CU_CTX_SCHED_SPIN](#): Instruct CUDA to actively spin when waiting for results from the GPU. This can decrease latency when waiting for the GPU, but may lower the performance of CPU threads if they are performing work in parallel with the CUDA thread.
- ▶ [CU_CTX_SCHED_YIELD](#): Instruct CUDA to yield its thread when waiting for results from the GPU. This can increase latency when waiting for the GPU, but can increase the performance of CPU threads performing work in parallel with the GPU.
- ▶ [CU_CTX_SCHED_BLOCKING_SYNC](#): Instruct CUDA to block the CPU thread on a synchronization primitive when waiting for the GPU to finish work.
- ▶ [CU_CTX_BLOCKING_SYNC](#): Instruct CUDA to block the CPU thread on a synchronization primitive when waiting for the GPU to finish work.


Deprecated: This flag was deprecated as of CUDA 4.0 and was replaced with [CU_CTX_SCHED_BLOCKING_SYNC](#).

- ▶ [CU_CTX_SCHED_AUTO](#): The default value if the `flags` parameter is zero, uses a heuristic based on the number of active CUDA contexts in the process C and the number of logical processors in the system P . If $C > P$, then CUDA will yield to other OS threads when waiting for the GPU ([CU_CTX_SCHED_YIELD](#)), otherwise CUDA will not yield while waiting for results and actively spin on the processor ([CU_CTX_SCHED_SPIN](#)). Additionally, on Tegra devices, [CU_CTX_SCHED_AUTO](#) uses a heuristic based on the power profile of the platform and may choose [CU_CTX_SCHED_BLOCKING_SYNC](#) for low-powered devices.

- ▶ [CU_CTX_MAP_HOST](#): Instruct CUDA to support mapped pinned allocations. This flag must be set in order to allocate pinned host memory that is accessible to the GPU.
- ▶ [CU_CTX_LMEM_RESIZE_TO_MAX](#): Instruct CUDA to not reduce local memory after resizing local memory for a kernel. This can prevent thrashing by local memory allocations when launching many kernels with high local memory usage at the cost of potentially increased memory usage.

Deprecated: This flag is deprecated and the behavior enabled by this flag is now the default and cannot be disabled. Instead, the per-thread stack size can be controlled with [cuCtxSetLimit\(\)](#).

Context creation will fail with [CUDA_ERROR_UNKNOWN](#) if the compute mode of the device is [CU_COMPUTEMODE_PROHIBITED](#). The function [cuDeviceGetAttribute\(\)](#) can be used with [CU_DEVICE_ATTRIBUTE_COMPUTE_MODE](#) to determine the compute mode of the device. The `nvidia-smi` tool can be used to set the compute mode for * devices. Documentation for `nvidia-smi` can be obtained by passing a `-h` option to it.



Note:
Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuCtxDestroy](#), [cuCtxGetApiVersion](#), [cuCtxGetCacheConfig](#), [cuCtxGetDevice](#), [cuCtxGetFlags](#), [cuCtxGetLimit](#), [cuCtxPopCurrent](#), [cuCtxPushCurrent](#), [cuCtxSetCacheConfig](#), [cuCtxSetLimit](#), [cuCtxSynchronize](#)

CUresult cuCtxDestroy (CUcontext ctx)

Destroy a CUDA context.

Parameters

ctx

- Context to destroy

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Destroys the CUDA context specified by `ctx`. The context `ctx` will be destroyed regardless of how many threads it is current to. It is the responsibility of the calling function to ensure that no API call issues using `ctx` while [cuCtxDestroy\(\)](#) is executing.

If `ctx` is current to the calling thread then `ctx` will also be popped from the current thread's context stack (as though [cuCtxPopCurrent\(\)](#) were called). If `ctx` is current to other threads, then `ctx` will remain current to those threads, and attempting to access `ctx` from those threads will result in the error [CUDA_ERROR_CONTEXT_IS_DESTROYED](#).

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuCtxCreate](#), [cuCtxGetApiVersion](#), [cuCtxGetCacheConfig](#), [cuCtxGetDevice](#), [cuCtxGetFlags](#), [cuCtxGetLimit](#), [cuCtxPopCurrent](#), [cuCtxPushCurrent](#), [cuCtxSetCacheConfig](#), [cuCtxSetLimit](#), [cuCtxSynchronize](#)

CUresult cuCtxGetApiVersion (CUcontext ctx, unsigned int *version)

Gets the context's API version.

Parameters

ctx

- Context to check

version

- Pointer to version

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_UNKNOWN](#)

Description

Returns a version number in `version` corresponding to the capabilities of the context (e.g. 3010 or 3020), which library developers can use to direct callers to a specific API version. If `ctx` is NULL, returns the API version used to create the currently bound context.

Note that new API versions are only introduced when context capabilities are changed that break binary compatibility, so the API version and driver version may be different. For example, it is valid for the API version to be 3020 while the driver version is 4020.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuCtxCreate](#), [cuCtxDestroy](#), [cuCtxGetDevice](#), [cuCtxGetFlags](#), [cuCtxGetLimit](#), [cuCtxPopCurrent](#), [cuCtxPushCurrent](#), [cuCtxSetCacheConfig](#), [cuCtxSetLimit](#), [cuCtxSynchronize](#)

CUresult cuCtxGetCacheConfig (CUfunc_cache *pconfig)

Returns the preferred cache configuration for the current context.

Parameters

pconfig

- Returned cache configuration

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

On devices where the L1 cache and shared memory use the same hardware resources, this function returns through `pconfig` the preferred cache configuration for the current context. This is only a preference. The driver will use the requested configuration if possible, but it is free to choose a different configuration if required to execute functions.

This will return a `pconfig` of [CU_FUNC_CACHE_PREFER_NONE](#) on devices where the size of the L1 cache and shared memory are fixed.

The supported cache configurations are:

- ▶ [CU_FUNC_CACHE_PREFER_NONE](#): no preference for shared memory or L1 (default)
- ▶ [CU_FUNC_CACHE_PREFER_SHARED](#): prefer larger shared memory and smaller L1 cache
- ▶ [CU_FUNC_CACHE_PREFER_L1](#): prefer larger L1 cache and smaller shared memory
- ▶ [CU_FUNC_CACHE_PREFER_EQUAL](#): prefer equal sized L1 cache and shared memory



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuCtxCreate](#), [cuCtxDestroy](#), [cuCtxGetApiVersion](#), [cuCtxGetDevice](#), [cuCtxGetFlags](#), [cuCtxGetLimit](#), [cuCtxPopCurrent](#), [cuCtxPushCurrent](#), [cuCtxSetCacheConfig](#), [cuCtxSetLimit](#), [cuCtxSynchronize](#), [cuFuncSetCacheConfig](#), [cudaDeviceGetCacheConfig](#)

CUresult cuCtxGetCurrent (CUcontext *pctx)

Returns the CUDA context bound to the calling CPU thread.

Parameters

pctx

- Returned context handle

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),

Description

Returns in *pctx the CUDA context bound to the calling CPU thread. If no context is bound to the calling CPU thread then *pctx is set to NULL and [CUDA_SUCCESS](#) is returned.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuCtxSetCurrent](#), [cuCtxCreate](#), [cuCtxDestroy](#), [cudaGetDevice](#)

CUresult cuCtxGetDevice (CUdevice *device)

Returns the device ID for the current context.

Parameters

device

- Returned device ID for the current context

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),

Description

Returns in *device the ordinal of the current context's device.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuCtxCreate](#), [cuCtxDestroy](#), [cuCtxGetApiVersion](#), [cuCtxGetCacheConfig](#), [cuCtxGetFlags](#), [cuCtxGetLimit](#), [cuCtxPopCurrent](#), [cuCtxPushCurrent](#), [cuCtxSetCacheConfig](#), [cuCtxSetLimit](#), [cuCtxSynchronize](#), [cudaGetDevice](#)

CUresult cuCtxGetFlags (unsigned int *flags)

Returns the flags for the current context.

Parameters

flags

- Pointer to store flags of current context

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),

Description

Returns in *flags the flags of the current context. See [cuCtxCreate](#) for flag values.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuCtxCreate](#), [cuCtxGetApiVersion](#), [cuCtxGetCacheConfig](#), [cuCtxGetCurrent](#), [cuCtxGetDevice](#), [cuCtxGetLimit](#), [cuCtxGetSharedMemConfig](#), [cuCtxGetStreamPriorityRange](#), [cudaGetDeviceFlags](#)

CUresult cuCtxGetLimit (size_t *pvalue, CUlimit limit)

Returns resource limits.

Parameters

pvalue

- Returned size of limit

limit

- Limit to query

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_UNSUPPORTED_LIMIT](#)

Description

Returns in `*pvalue` the current size of `limit`. The supported [CUlimit](#) values are:

- ▶ [CU_LIMIT_STACK_SIZE](#): stack size in bytes of each GPU thread.
- ▶ [CU_LIMIT_PRINTF_FIFO_SIZE](#): size in bytes of the FIFO used by the `printf()` device system call.
- ▶ [CU_LIMIT_MALLOC_HEAP_SIZE](#): size in bytes of the heap used by the `malloc()` and `free()` device system calls.
- ▶ [CU_LIMIT_DEV_RUNTIME_SYNC_DEPTH](#): maximum grid depth at which a thread can issue the device runtime call [cudaDeviceSynchronize\(\)](#) to wait on child grid launches to complete.
- ▶ [CU_LIMIT_DEV_RUNTIME_PENDING_LAUNCH_COUNT](#): maximum number of outstanding device runtime launches that can be made from this context.
- ▶ [CU_LIMIT_MAX_L2_FETCH_GRANULARITY](#): L2 cache fetch granularity.
- ▶ [CU_LIMIT_PERSISTING_L2_CACHE_SIZE](#): Persisting L2 cache size in bytes

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuCtxCreate](#), [cuCtxDestroy](#), [cuCtxGetApiVersion](#), [cuCtxGetCacheConfig](#), [cuCtxGetDevice](#), [cuCtxGetFlags](#), [cuCtxPopCurrent](#), [cuCtxPushCurrent](#), [cuCtxSetCacheConfig](#), [cuCtxSetLimit](#), [cuCtxSynchronize](#), [cudaDeviceGetLimit](#)

CUresult cuCtxGetSharedMemConfig (CUsharedconfig *pConfig)

Returns the current shared memory configuration for the current context.

Parameters**pConfig**

- returned shared memory configuration

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

This function will return in `pConfig` the current size of shared memory banks in the current context. On devices with configurable shared memory banks, [cuCtxSetSharedMemConfig](#) can be used to change this setting, so that all subsequent kernel launches will by default use the new bank size. When [cuCtxGetSharedMemConfig](#) is called on devices without configurable shared memory, it will return the fixed bank size of the hardware.

The returned bank configurations can be either:

- ▶ [CU_SHARED_MEM_CONFIG_FOUR_BYTE_BANK_SIZE](#): shared memory bank width is four bytes.
- ▶ [CU_SHARED_MEM_CONFIG_EIGHT_BYTE_BANK_SIZE](#): shared memory bank width will be eight bytes.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuCtxCreate](#), [cuCtxDestroy](#), [cuCtxGetApiVersion](#), [cuCtxGetCacheConfig](#), [cuCtxGetDevice](#),
[cuCtxGetFlags](#), [cuCtxGetLimit](#), [cuCtxPopCurrent](#), [cuCtxPushCurrent](#), [cuCtxSetLimit](#),
[cuCtxSynchronize](#), [cuCtxGetSharedMemConfig](#), [cuFuncSetCacheConfig](#),
[cudaDeviceGetSharedMemConfig](#)

CUresult cuCtxGetStreamPriorityRange (int *leastPriority, int *greatestPriority)

Returns numerical values that correspond to the least and greatest stream priorities.

Parameters

leastPriority

- Pointer to an int in which the numerical value for least stream priority is returned

greatestPriority

- Pointer to an int in which the numerical value for greatest stream priority is returned

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#),

Description

Returns in `*leastPriority` and `*greatestPriority` the numerical values that correspond to the least and greatest stream priorities respectively. Stream priorities follow a convention where lower numbers imply greater priorities. The range of meaningful stream priorities is given by `[*greatestPriority, *leastPriority]`. If the user attempts to create a stream with a priority value that is outside the meaningful range as specified by this API, the priority is automatically clamped down or up to either `*leastPriority` or `*greatestPriority` respectively. See [cuStreamCreateWithPriority](#) for details on creating a priority stream. A NULL may be passed in for `*leastPriority` or `*greatestPriority` if the value is not desired.

This function will return '0' in both `*leastPriority` and `*greatestPriority` if the current context's device does not support stream priorities (see [cuDeviceGetAttribute](#)).



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuStreamCreateWithPriority](#), [cuStreamGetPriority](#), [cuCtxGetDevice](#), [cuCtxGetFlags](#), [cuCtxSetLimit](#), [cuCtxSynchronize](#), [cudaDeviceGetStreamPriorityRange](#)

CUresult cuCtxPopCurrent (CUcontext *pctx)

Pops the current CUDA context from the current CPU thread.

Parameters

pctx

- Returned new context handle

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#)

Description

Pops the current CUDA context from the CPU thread and passes back the old context handle in `*pctx`. That context may then be made current to a different CPU thread by calling [cuCtxPushCurrent\(\)](#).

If a context was current to the CPU thread before [cuCtxCreate\(\)](#) or [cuCtxPushCurrent\(\)](#) was called, this function makes that context current to the CPU thread again.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuCtxCreate](#), [cuCtxDestroy](#), [cuCtxGetApiVersion](#), [cuCtxGetCacheConfig](#), [cuCtxGetDevice](#), [cuCtxGetFlags](#), [cuCtxGetLimit](#), [cuCtxPushCurrent](#), [cuCtxSetCacheConfig](#), [cuCtxSetLimit](#), [cuCtxSynchronize](#)

CUresult cuCtxPushCurrent (CUcontext ctx)

Pushes a context on the current CPU thread.

Parameters

ctx

- Context to push

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Pushes the given context `ctx` onto the CPU thread's stack of current contexts. The specified context becomes the CPU thread's current context, so all CUDA functions that operate on the current context are affected.

The previous current context may be made current again by calling [cuCtxDestroy\(\)](#) or [cuCtxPopCurrent\(\)](#).

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuCtxCreate](#), [cuCtxDestroy](#), [cuCtxGetApiVersion](#), [cuCtxGetCacheConfig](#), [cuCtxGetDevice](#), [cuCtxGetFlags](#), [cuCtxGetLimit](#), [cuCtxPopCurrent](#), [cuCtxSetCacheConfig](#), [cuCtxSetLimit](#), [cuCtxSynchronize](#)

CUresult cuCtxResetPersistingL2Cache (void)

Resets all persisting lines in cache to normal status.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_NOT_SUPPORTED](#)

Description

[cuCtxResetPersistingL2Cache](#) Resets all persisting lines in cache to normal status. Takes effect on function return.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[CUaccessPolicyWindow](#)

CUresult cuCtxSetCacheConfig (CUfunc_cache config)

Sets the preferred cache configuration for the current context.

Parameters

config

- Requested cache configuration

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

On devices where the L1 cache and shared memory use the same hardware resources, this sets through `config` the preferred cache configuration for the current context. This is only a preference. The driver will use the requested configuration if possible, but it is free to choose a different configuration if required to execute the function. Any function preference set via [cuFuncSetCacheConfig\(\)](#) will be preferred over this context-wide setting. Setting the context-wide cache configuration to [CU_FUNC_CACHE_PREFER_NONE](#) will cause subsequent kernel launches to prefer to not change the cache configuration unless required to launch the kernel.

This setting does nothing on devices where the size of the L1 cache and shared memory are fixed.

Launching a kernel with a different preference than the most recent preference setting may insert a device-side synchronization point.

The supported cache configurations are:

- ▶ [CU_FUNC_CACHE_PREFER_NONE](#): no preference for shared memory or L1 (default)
- ▶ [CU_FUNC_CACHE_PREFER_SHARED](#): prefer larger shared memory and smaller L1 cache
- ▶ [CU_FUNC_CACHE_PREFER_L1](#): prefer larger L1 cache and smaller shared memory
- ▶ [CU_FUNC_CACHE_PREFER_EQUAL](#): prefer equal sized L1 cache and shared memory



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuCtxCreate](#), [cuCtxDestroy](#), [cuCtxGetApiVersion](#), [cuCtxGetCacheConfig](#), [cuCtxGetDevice](#), [cuCtxGetFlags](#), [cuCtxGetLimit](#), [cuCtxPopCurrent](#), [cuCtxPushCurrent](#), [cuCtxSetLimit](#), [cuCtxSynchronize](#), [cuFuncSetCacheConfig](#), [cudaDeviceSetCacheConfig](#)

CUresult cuCtxSetCurrent (CUcontext ctx)

Binds the specified CUDA context to the calling CPU thread.

Parameters

ctx

- Context to bind to the calling CPU thread

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#)

Description

Binds the specified CUDA context to the calling CPU thread. If `ctx` is NULL then the CUDA context previously bound to the calling CPU thread is unbound and [CUDA_SUCCESS](#) is returned.

If there exists a CUDA context stack on the calling CPU thread, this will replace the top of that stack with `ctx`. If `ctx` is NULL then this will be equivalent to popping the top of the calling CPU thread's CUDA context stack (or a no-op if the calling CPU thread's CUDA context stack is empty).

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuCtxGetCurrent](#), [cuCtxCreate](#), [cuCtxDestroy](#), [cudaSetDevice](#)

CUresult cuCtxSetLimit (CUlimit limit, size_t value)

Set resource limits.

Parameters

limit

- Limit to set

value

- Size of limit

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_UNSUPPORTED_LIMIT](#), [CUDA_ERROR_OUT_OF_MEMORY](#), [CUDA_ERROR_INVALID_CONTEXT](#)

Description

Setting `limit` to `value` is a request by the application to update the current limit maintained by the context. The driver is free to modify the requested value to meet h/w requirements (this could be clamping to minimum or maximum values, rounding up to nearest element size, etc). The application can use [cuCtxGetLimit\(\)](#) to find out exactly what the limit has been set to.

Setting each [CUlimit](#) has its own specific restrictions, so each is discussed here.

- ▶ [CU_LIMIT_STACK_SIZE](#) controls the stack size in bytes of each GPU thread. The driver automatically increases the per-thread stack size for each kernel launch as needed. This size isn't reset back to the original value after each launch. Setting this value will take effect immediately, and if necessary, the device will block until all preceding requested tasks are complete.
- ▶ [CU_LIMIT_PRINTF_FIFO_SIZE](#) controls the size in bytes of the FIFO used by the `printf()` device system call. Setting [CU_LIMIT_PRINTF_FIFO_SIZE](#) must be performed before launching any kernel that uses the `printf()` device system call, otherwise [CUDA_ERROR_INVALID_VALUE](#) will be returned.
- ▶ [CU_LIMIT_MALLOC_HEAP_SIZE](#) controls the size in bytes of the heap used by the `malloc()` and `free()` device system calls. Setting [CU_LIMIT_MALLOC_HEAP_SIZE](#) must be performed before launching any kernel that uses the `malloc()` or `free()` device system calls, otherwise [CUDA_ERROR_INVALID_VALUE](#) will be returned.

- ▶ [CU_LIMIT_DEV_RUNTIME_SYNC_DEPTH](#) controls the maximum nesting depth of a grid at which a thread can safely call [cudaDeviceSynchronize\(\)](#). Setting this limit must be performed before any launch of a kernel that uses the device runtime and calls [cudaDeviceSynchronize\(\)](#) above the default sync depth, two levels of grids. Calls to [cudaDeviceSynchronize\(\)](#) will fail with error code [cudaErrorSyncDepthExceeded](#) if the limitation is violated. This limit can be set smaller than the default or up the maximum launch depth of 24. When setting this limit, keep in mind that additional levels of sync depth require the driver to reserve large amounts of device memory which can no longer be used for user allocations. If these reservations of device memory fail, [cuCtxSetLimit\(\)](#) will return [CUDA_ERROR_OUT_OF_MEMORY](#), and the limit can be reset to a lower value. This limit is only applicable to devices of compute capability 3.5 and higher. Attempting to set this limit on devices of compute capability less than 3.5 will result in the error [CUDA_ERROR_UNSUPPORTED_LIMIT](#) being returned.
- ▶ [CU_LIMIT_DEV_RUNTIME_PENDING_LAUNCH_COUNT](#) controls the maximum number of outstanding device runtime launches that can be made from the current context. A grid is outstanding from the point of launch up until the grid is known to have been completed. Device runtime launches which violate this limitation fail and return [cudaErrorLaunchPendingCountExceeded](#) when [cudaGetLastError\(\)](#) is called after launch. If more pending launches than the default (2048 launches) are needed for a module using the device runtime, this limit can be increased. Keep in mind that being able to sustain additional pending launches will require the driver to reserve larger amounts of device memory upfront which can no longer be used for allocations. If these reservations fail, [cuCtxSetLimit\(\)](#) will return [CUDA_ERROR_OUT_OF_MEMORY](#), and the limit can be reset to a lower value. This limit is only applicable to devices of compute capability 3.5 and higher. Attempting to set this limit on devices of compute capability less than 3.5 will result in the error [CUDA_ERROR_UNSUPPORTED_LIMIT](#) being returned.
- ▶ [CU_LIMIT_MAX_L2_FETCH_GRANULARITY](#) controls the L2 cache fetch granularity. Values can range from 0B to 128B. This is purely a performance hint and it can be ignored or clamped depending on the platform.
- ▶ [CU_LIMIT_PERSISTING_L2_CACHE_SIZE](#) controls size in bytes available for persisting L2 cache. This is purely a performance hint and it can be ignored or clamped depending on the platform.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuCtxCreate](#), [cuCtxDestroy](#), [cuCtxGetApiVersion](#), [cuCtxGetCacheConfig](#), [cuCtxGetDevice](#), [cuCtxGetFlags](#), [cuCtxGetLimit](#), [cuCtxPopCurrent](#), [cuCtxPushCurrent](#), [cuCtxSetCacheConfig](#), [cuCtxSynchronize](#), [cudaDeviceSetLimit](#)

CUresult cuCtxSetSharedMemConfig (CUsharedconfig config)

Sets the shared memory configuration for the current context.

Parameters

config

- requested shared memory configuration

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

On devices with configurable shared memory banks, this function will set the context's shared memory bank size which is used for subsequent kernel launches.

Changing the shared memory configuration between launches may insert a device side synchronization point between those launches.

Changing the shared memory bank size will not increase shared memory usage or affect occupancy of kernels, but may have major effects on performance. Larger bank sizes will allow for greater potential bandwidth to shared memory, but will change what kinds of accesses to shared memory will result in bank conflicts.

This function will do nothing on devices with fixed shared memory bank size.

The supported bank configurations are:

- ▶ [CU_SHARED_MEM_CONFIG_DEFAULT_BANK_SIZE](#): set bank width to the default initial setting (currently, four bytes).
- ▶ [CU_SHARED_MEM_CONFIG_FOUR_BYTE_BANK_SIZE](#): set shared memory bank width to be natively four bytes.
- ▶ [CU_SHARED_MEM_CONFIG_EIGHT_BYTE_BANK_SIZE](#): set shared memory bank width to be natively eight bytes.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuCtxCreate](#), [cuCtxDestroy](#), [cuCtxGetApiVersion](#), [cuCtxGetCacheConfig](#), [cuCtxGetDevice](#), [cuCtxGetFlags](#), [cuCtxGetLimit](#), [cuCtxPopCurrent](#), [cuCtxPushCurrent](#), [cuCtxSetLimit](#),

[cuCtxSynchronize](#), [cuCtxGetSharedMemConfig](#), [cuFuncSetCacheConfig](#),
[cudaDeviceSetSharedMemConfig](#)

CUresult cuCtxSynchronize (void)

Block for a context's tasks to complete.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#)

Description

Blocks until the device has completed all preceding requested tasks. [cuCtxSynchronize\(\)](#) returns an error if one of the preceding tasks failed. If the context was created with the [CU_CTX_SCHED_BLOCKING_SYNC](#) flag, the CPU thread will block until the GPU context has finished its work.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuCtxCreate](#), [cuCtxDestroy](#), [cuCtxGetApiVersion](#), [cuCtxGetCacheConfig](#), [cuCtxGetDevice](#),
[cuCtxGetFlags](#), [cuCtxGetLimit](#), [cuCtxPopCurrent](#), [cuCtxPushCurrent](#), [cuCtxSetCacheConfig](#),
[cuCtxSetLimit](#), [cudaDeviceSynchronize](#)

6.9. Context Management [DEPRECATED]

This section describes the deprecated context management functions of the low-level CUDA driver application programming interface.

CUresult cuCtxAttach (CUcontext *pctx, unsigned int flags)

Increment a context's usage-count.

Parameters

pctx

- Returned context handle of the current context

flags

- Context attach flags (must be 0)

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

[Deprecated](#)

Note that this function is deprecated and should not be used.

Increments the usage count of the context and passes back a context handle in `*pctx` that must be passed to [cuCtxDetach\(\)](#) when the application is done with the context. [cuCtxAttach\(\)](#) fails if there is no context current to the thread.

Currently, the `flags` parameter must be 0.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuCtxCreate](#), [cuCtxDestroy](#), [cuCtxDetach](#), [cuCtxGetApiVersion](#), [cuCtxGetCacheConfig](#), [cuCtxGetDevice](#), [cuCtxGetFlags](#), [cuCtxGetLimit](#), [cuCtxPopCurrent](#), [cuCtxPushCurrent](#), [cuCtxSetCacheConfig](#), [cuCtxSetLimit](#), [cuCtxSynchronize](#)

CUresult cuCtxDetach (CUcontext ctx)

Decrement a context's usage-count.

Parameters

ctx

- Context to destroy

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#)

Description

[Deprecated](#)

Note that this function is deprecated and should not be used.

Decrements the usage count of the context `ctx`, and destroys the context if the usage count goes to 0. The context must be a handle that was passed back by [cuCtxCreate\(\)](#) or [cuCtxAttach\(\)](#), and must be current to the calling thread.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuCtxCreate](#), [cuCtxDestroy](#), [cuCtxGetApiVersion](#), [cuCtxGetCacheConfig](#), [cuCtxGetDevice](#), [cuCtxGetFlags](#), [cuCtxGetLimit](#), [cuCtxPopCurrent](#), [cuCtxPushCurrent](#), [cuCtxSetCacheConfig](#), [cuCtxSetLimit](#), [cuCtxSynchronize](#)

6.10. Module Management

This section describes the module management functions of the low-level CUDA driver application programming interface.

CUresult cuLinkAddData (CUlinkState state, CUjitInputType type, void *data, size_t size, const char *name, unsigned int numOptions, CUjit_option *options, void **optionValues)

Add an input to a pending linker invocation.

Parameters

state

A pending linker action.

type

The type of the input data.

data

The input data. PTX must be NULL-terminated.

size

The length of the input data.

name

An optional name for this input in log messages.

numOptions

Size of options.

options

Options to be applied only for this input (overrides options from [cuLinkCreate](#)).

optionValues

Array of option values, each cast to void *.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_IMAGE](#), [CUDA_ERROR_INVALID_PTX](#), [CUDA_ERROR_UNSUPPORTED_PTX_VERSION](#), [CUDA_ERROR_OUT_OF_MEMORY](#), [CUDA_ERROR_NO_BINARY_FOR_GPU](#)

Description

Ownership of data is retained by the caller. No reference is retained to any inputs after this call returns.

This method accepts only compiler options, which are used if the data must be compiled from PTX, and does not accept any of [CU_JIT_WALL_TIME](#), [CU_JIT_INFO_LOG_BUFFER](#), [CU_JIT_ERROR_LOG_BUFFER](#), [CU_JIT_TARGET_FROM_CUCONTEXT](#), or [CU_JIT_TARGET](#).

See also:

[cuLinkCreate](#), [cuLinkAddFile](#), [cuLinkComplete](#), [cuLinkDestroy](#)

CUresult cuLinkAddFile (CUlinkState state, CUjitInputType type, const char *path, unsigned int numOptions, CUjit_option *options, void **optionValues)

Add a file input to a pending linker invocation.

Parameters

state

A pending linker action

type

The type of the input data

path

Path to the input file

numOptions

Size of options

options

Options to be applied only for this input (overrides options from [cuLinkCreate](#))

optionValues

Array of option values, each cast to void *

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_FILE_NOT_FOUND](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_IMAGE](#), [CUDA_ERROR_INVALID_PTX](#), [CUDA_ERROR_UNSUPPORTED_PTX_VERSION](#), [CUDA_ERROR_OUT_OF_MEMORY](#), [CUDA_ERROR_NO_BINARY_FOR_GPU](#)

Description

No reference is retained to any inputs after this call returns.

This method accepts only compiler options, which are used if the input must be compiled from PTX, and does not accept any of [CU_JIT_WALL_TIME](#), [CU_JIT_INFO_LOG_BUFFER](#), [CU_JIT_ERROR_LOG_BUFFER](#), [CU_JIT_TARGET_FROM_CUCONTEXT](#), or [CU_JIT_TARGET](#).

This method is equivalent to invoking [cuLinkAddData](#) on the contents of the file.

See also:

[cuLinkCreate](#), [cuLinkAddData](#), [cuLinkComplete](#), [cuLinkDestroy](#)

CUresult cuLinkComplete (CUlinkState state, void **cubinOut, size_t *sizeOut)

Complete a pending linker invocation.

Parameters

state

A pending linker invocation

cubinOut

On success, this will point to the output image

sizeOut

Optional parameter to receive the size of the generated image

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_OUT_OF_MEMORY](#)

Description

Completes the pending linker action and returns the cubin image for the linked device code, which can be used with [cuModuleLoadData](#). The cubin is owned by `state`, so it should be loaded before `state` is destroyed via [cuLinkDestroy](#). This call does not destroy `state`.

See also:

[cuLinkCreate](#), [cuLinkAddData](#), [cuLinkAddFile](#), [cuLinkDestroy](#), [cuModuleLoadData](#)

CUresult cuLinkCreate (unsigned int numOptions, CUjit_option *options, void **optionValues, CUlinkState *stateOut)

Creates a pending JIT linker invocation.

Parameters

numOptions

Size of options arrays

options

Array of linker and compiler options

optionValues

Array of option values, each cast to void *

stateOut

On success, this will contain a CUlinkState to specify and complete this action

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_OUT_OF_MEMORY](#), [CUDA_ERROR_JIT_COMPILER_NOT_FOUND](#)

Description

If the call is successful, the caller owns the returned CUlinkState, which should eventually be destroyed with [cuLinkDestroy](#). The device code machine size (32 or 64 bit) will match the calling application.

Both linker and compiler options may be specified. Compiler options will be applied to inputs to this linker action which must be compiled from PTX. The options [CU_JIT_WALL_TIME](#), [CU_JIT_INFO_LOG_BUFFER_SIZE_BYTES](#), and [CU_JIT_ERROR_LOG_BUFFER_SIZE_BYTES](#) will accumulate data until the CUlinkState is destroyed.

`optionValues` must remain valid for the life of the CUlinkState if output options are used. No other references to inputs are maintained after this call returns.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuLinkAddData](#), [cuLinkAddFile](#), [cuLinkComplete](#), [cuLinkDestroy](#)

CUresult cuLinkDestroy (CUlinkState state)

Destroys state for a JIT linker invocation.

Parameters

state

State object for the linker invocation

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_HANDLE](#)

Description

See also:

[cuLinkCreate](#)

CUresult cuModuleGetFunction (CUfunction *hfunc, CUmodule hmod, const char *name)

Returns a function handle.

Parameters

hfunc

- Returned function handle

hmod

- Module to retrieve function from

name

- Name of function to retrieve

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_NOT_FOUND](#)

Description

Returns in *hfunc the handle of the function of name name located in module hmod. If no function of that name exists, [cuModuleGetFunction\(\)](#) returns [CUDA_ERROR_NOT_FOUND](#).



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuModuleGetGlobal](#), [cuModuleGetTexRef](#), [cuModuleLoad](#), [cuModuleLoadData](#),
[cuModuleLoadDataEx](#), [cuModuleLoadFatBinary](#), [cuModuleUnload](#)

CUresult cuModuleGetGlobal (CUdeviceptr *dptr, size_t *bytes, CUmodule hmod, const char *name)

Returns a global pointer from a module.

Parameters

dptr

- Returned global device pointer

bytes

- Returned global size in bytes

hmod

- Module to retrieve global from

name

- Name of global to retrieve

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_NOT_FOUND](#)

Description

Returns in `*dptr` and `*bytes` the base pointer and size of the global of name `name` located in module `hmod`. If no variable of that name exists, [cuModuleGetGlobal\(\)](#) returns [CUDA_ERROR_NOT_FOUND](#). Both parameters `dptr` and `bytes` are optional. If one of them is NULL, it is ignored.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuModuleGetFunction](#), [cuModuleGetTexRef](#), [cuModuleLoad](#), [cuModuleLoadData](#),
[cuModuleLoadDataEx](#), [cuModuleLoadFatBinary](#), [cuModuleUnload](#), [cudaGetSymbolAddress](#),
[cudaGetSymbolSize](#)

CUresult cuModuleGetSurfRef (CUsurfref *pSurfRef, CUmodule hmod, const char *name)

Returns a handle to a surface reference.

Parameters

pSurfRef

- Returned surface reference

hmod

- Module to retrieve surface reference from

name

- Name of surface reference to retrieve

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_NOT_FOUND](#)

Description

Returns in *pSurfRef the handle of the surface reference of name name in the module hmod. If no surface reference of that name exists, [cuModuleGetSurfRef\(\)](#) returns [CUDA_ERROR_NOT_FOUND](#).



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuModuleGetFunction](#), [cuModuleGetGlobal](#), [cuModuleGetTexRef](#), [cuModuleLoad](#), [cuModuleLoadData](#), [cuModuleLoadDataEx](#), [cuModuleLoadFatBinary](#), [cuModuleUnload](#), [cudaGetSurfaceReference](#)

CUresult cuModuleGetTexRef (CUtexref *pTexRef, CUmodule hmod, const char *name)

Returns a handle to a texture reference.

Parameters

pTexRef

- Returned texture reference

hmod

- Module to retrieve texture reference from

name

- Name of texture reference to retrieve

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_NOT_FOUND](#)

Description

Returns in `*pTexRef` the handle of the texture reference of name `name` in the module `hmod`. If no texture reference of that name exists, `cuModuleGetTexRef()` returns [CUDA_ERROR_NOT_FOUND](#). This texture reference handle should not be destroyed, since it will be destroyed when the module is unloaded.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuModuleGetFunction](#), [cuModuleGetGlobal](#), [cuModuleGetSurfRef](#), [cuModuleLoad](#),
[cuModuleLoadData](#), [cuModuleLoadDataEx](#), [cuModuleLoadFatBinary](#), [cuModuleUnload](#),
[cudaGetTextureReference](#)

CUresult cuModuleLoad (CUmodule *module, const char *fname)

Loads a compute module.

Parameters**module**

- Returned module

fname

- Filename of module to load

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_INVALID_PTX](#), [CUDA_ERROR_UNSUPPORTED_PTX_VERSION](#),
[CUDA_ERROR_NOT_FOUND](#), [CUDA_ERROR_OUT_OF_MEMORY](#),

[CUDA_ERROR_FILE_NOT_FOUND](#), [CUDA_ERROR_NO_BINARY_FOR_GPU](#),
[CUDA_ERROR_SHARED_OBJECT_SYMBOL_NOT_FOUND](#),
[CUDA_ERROR_SHARED_OBJECT_INIT_FAILED](#), [CUDA_ERROR_JIT_COMPILER_NOT_FOUND](#)

Description

Takes a filename `fname` and loads the corresponding module `module` into the current context. The CUDA driver API does not attempt to lazily allocate the resources needed by a module; if the memory for functions and data (constant and global) needed by the module cannot be allocated, [cuModuleLoad\(\)](#) fails. The file should be a cubin file as output by **nvcc**, or a PTX file either as output by **nvcc** or handwritten, or a fatbin file as output by **nvcc** from toolchain 4.0 or later.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuModuleGetFunction](#), [cuModuleGetGlobal](#), [cuModuleGetTexRef](#), [cuModuleLoadData](#),
[cuModuleLoadDataEx](#), [cuModuleLoadFatBinary](#), [cuModuleUnload](#)

CUresult cuModuleLoadData (CUmodule *module, const void *image)

Load a module's data.

Parameters

module

- Returned module

image

- Module data to load

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_INVALID_PTX](#), [CUDA_ERROR_UNSUPPORTED_PTX_VERSION](#),
[CUDA_ERROR_OUT_OF_MEMORY](#), [CUDA_ERROR_NO_BINARY_FOR_GPU](#),
[CUDA_ERROR_SHARED_OBJECT_SYMBOL_NOT_FOUND](#),
[CUDA_ERROR_SHARED_OBJECT_INIT_FAILED](#), [CUDA_ERROR_JIT_COMPILER_NOT_FOUND](#)

Description

Takes a pointer `image` and loads the corresponding module `module` into the current context. The pointer may be obtained by mapping a cubin or PTX or fatbin file, passing a cubin or PTX or fatbin file as a NULL-terminated text string, or incorporating a cubin or fatbin object into the executable resources and using operating system calls such as Windows `FindResource()` to obtain the pointer.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuModuleGetFunction](#), [cuModuleGetGlobal](#), [cuModuleGetTexRef](#), [cuModuleLoad](#), [cuModuleLoadDataEx](#), [cuModuleLoadFatBinary](#), [cuModuleUnload](#)

CUresult cuModuleLoadDataEx (CUmodule *module, const void *image, unsigned int numOptions, CUjit_option *options, void **optionValues)

Load a module's data with options.

Parameters

module

- Returned module

image

- Module data to load

numOptions

- Number of options

options

- Options for JIT

optionValues

- Option values for JIT

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_PTX](#), [CUDA_ERROR_UNSUPPORTED_PTX_VERSION](#), [CUDA_ERROR_OUT_OF_MEMORY](#), [CUDA_ERROR_NO_BINARY_FOR_GPU](#), [CUDA_ERROR_SHARED_OBJECT_SYMBOL_NOT_FOUND](#), [CUDA_ERROR_SHARED_OBJECT_INIT_FAILED](#), [CUDA_ERROR_JIT_COMPILER_NOT_FOUND](#)

Description

Takes a pointer `image` and loads the corresponding module `module` into the current context. The pointer may be obtained by mapping a cubin or PTX or fatbin file, passing a cubin or PTX or fatbin file as a NULL-terminated text string, or incorporating a cubin or fatbin object into the executable resources and using operating system calls such as Windows `FindResource()` to obtain the pointer. Options are passed as an array via `options` and any corresponding parameters are passed in `optionValues`. The number of total options is supplied via `numOptions`. Any outputs will be returned via `optionValues`.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuModuleGetFunction](#), [cuModuleGetGlobal](#), [cuModuleGetTexRef](#), [cuModuleLoad](#), [cuModuleLoadData](#), [cuModuleLoadFatBinary](#), [cuModuleUnload](#)

CUresult cuModuleLoadFatBinary (CUmodule *module, const void *fatCubin)

Load a module's data.

Parameters

module

- Returned module

fatCubin

- Fat binary to load

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_PTX](#), [CUDA_ERROR_UNSUPPORTED_PTX_VERSION](#), [CUDA_ERROR_NOT_FOUND](#), [CUDA_ERROR_OUT_OF_MEMORY](#), [CUDA_ERROR_NO_BINARY_FOR_GPU](#), [CUDA_ERROR_SHARED_OBJECT_SYMBOL_NOT_FOUND](#), [CUDA_ERROR_SHARED_OBJECT_INIT_FAILED](#), [CUDA_ERROR_JIT_COMPILER_NOT_FOUND](#)

Description

Takes a pointer `fatCubin` and loads the corresponding module `module` into the current context. The pointer represents a fat binary object, which is a collection of different cubin and/

or PTX files, all representing the same device code, but compiled and optimized for different architectures.

Prior to CUDA 4.0, there was no documented API for constructing and using fat binary objects by programmers. Starting with CUDA 4.0, fat binary objects can be constructed by providing the `-fatbin` option to **nvcc**. More information can be found in the **nvcc** document.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuModuleGetFunction](#), [cuModuleGetGlobal](#), [cuModuleGetTexRef](#), [cuModuleLoad](#), [cuModuleLoadData](#), [cuModuleLoadDataEx](#), [cuModuleUnload](#)

CUresult cuModuleUnload (CUmodule hmod)

Unloads a module.

Parameters

hmod

- Module to unload

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Unloads a module `hmod` from the current context.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuModuleGetFunction](#), [cuModuleGetGlobal](#), [cuModuleGetTexRef](#), [cuModuleLoad](#), [cuModuleLoadData](#), [cuModuleLoadDataEx](#), [cuModuleLoadFatBinary](#)

6.11. Memory Management

This section describes the memory management functions of the low-level CUDA driver application programming interface.

CUresult cuArray3DCreate (CUarray *pHandle, const CUDA_ARRAY3D_DESCRIPTOR *pAllocateArray)

Creates a 3D CUDA array.

Parameters

pHandle

- Returned array

pAllocateArray

- 3D array descriptor

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_OUT_OF_MEMORY](#), [CUDA_ERROR_UNKNOWN](#)

Description

Creates a CUDA array according to the `CUDA_ARRAY3D_DESCRIPTOR` structure `pAllocateArray` and returns a handle to the new CUDA array in `*pHandle`. The `CUDA_ARRAY3D_DESCRIPTOR` is defined as:

```
typedef struct {
    unsigned int Width;
    unsigned int Height;
    unsigned int Depth;
    CUarray_format Format;
    unsigned int NumChannels;
    unsigned int Flags;
} CUDA_ARRAY3D_DESCRIPTOR;
```

where:

- ▶ `Width`, `Height`, and `Depth` are the width, height, and depth of the CUDA array (in elements); the following types of CUDA arrays can be allocated:
 - ▶ A 1D array is allocated if `Height` and `Depth` extents are both zero.
 - ▶ A 2D array is allocated if only `Depth` extent is zero.
 - ▶ A 3D array is allocated if all three extents are non-zero.

- ▶ A 1D layered CUDA array is allocated if only `Height` is zero and the `CUDA_ARRAY3D_LAYERED` flag is set. Each layer is a 1D array. The number of layers is determined by the depth extent.
- ▶ A 2D layered CUDA array is allocated if all three extents are non-zero and the `CUDA_ARRAY3D_LAYERED` flag is set. Each layer is a 2D array. The number of layers is determined by the depth extent.
- ▶ A cubemap CUDA array is allocated if all three extents are non-zero and the `CUDA_ARRAY3D_CUBEMAP` flag is set. `Width` must be equal to `Height`, and `Depth` must be six. A cubemap is a special type of 2D layered CUDA array, where the six layers represent the six faces of a cube. The order of the six layers in memory is the same as that listed in `CUarray_cubemap_face`.
- ▶ A cubemap layered CUDA array is allocated if all three extents are non-zero, and both, `CUDA_ARRAY3D_CUBEMAP` and `CUDA_ARRAY3D_LAYERED` flags are set. `Width` must be equal to `Height`, and `Depth` must be a multiple of six. A cubemap layered CUDA array is a special type of 2D layered CUDA array that consists of a collection of cubemaps. The first six layers represent the first cubemap, the next six layers form the second cubemap, and so on.
- ▶ `Format` specifies the format of the elements; `CUarray_format` is defined as:

```
↑
typedef enum CUarray_format_enum {
    CU_AD_FORMAT_UNSIGNED_INT8 = 0x01,
    CU_AD_FORMAT_UNSIGNED_INT16 = 0x02,
    CU_AD_FORMAT_UNSIGNED_INT32 = 0x03,
    CU_AD_FORMAT_SIGNED_INT8 = 0x08,
    CU_AD_FORMAT_SIGNED_INT16 = 0x09,
    CU_AD_FORMAT_SIGNED_INT32 = 0x0a,
    CU_AD_FORMAT_HALF = 0x10,
    CU_AD_FORMAT_FLOAT = 0x20
} CUarray_format;
```

- ▶ `NumChannels` specifies the number of packed components per CUDA array element; it may be 1, 2, or 4;
- ▶ Flags may be set to
 - ▶ `CUDA_ARRAY3D_LAYERED` to enable creation of layered CUDA arrays. If this flag is set, `Depth` specifies the number of layers, not the depth of a 3D array.
 - ▶ `CUDA_ARRAY3D_SURFACE_LDST` to enable surface references to be bound to the CUDA array. If this flag is not set, `cuSurfRefSetArray` will fail when attempting to bind the CUDA array to a surface reference.
 - ▶ `CUDA_ARRAY3D_CUBEMAP` to enable creation of cubemaps. If this flag is set, `Width` must be equal to `Height`, and `Depth` must be six. If the `CUDA_ARRAY3D_LAYERED` flag is also set, then `Depth` must be a multiple of six.
 - ▶ `CUDA_ARRAY3D_TEXTURE_GATHER` to indicate that the CUDA array will be used for texture gather. Texture gather can only be performed on 2D CUDA arrays.

`Width`, `Height` and `Depth` must meet certain size requirements as listed in the following table. All values are specified in elements. Note that for brevity's sake, the full name of the

device attribute is not specified. For ex., TEXTURE1D_WIDTH refers to the device attribute [CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE1D_WIDTH](#).

Note that 2D CUDA arrays have different size requirements if the [CUDA_ARRAY3D_TEXTURE_GATHER](#) flag is set. `width` and `height` must not be greater than [CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_GATHER_WIDTH](#) and [CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_GATHER_HEIGHT](#) respectively, in that case.

CUDA array type	Valid extents that must always be met {(width range in elements), (height range), (depth range)}	Valid extents with CUDA_ARRAY3D_SURFACE_LDST set {(width range in elements), (height range), (depth range)}
1D	{(1,TEXTURE1D_WIDTH), 0, 0}	{(1,SURFACE1D_WIDTH), 0, 0}
2D	{(1,TEXTURE2D_WIDTH), (1,TEXTURE2D_HEIGHT), 0}	{(1,SURFACE2D_WIDTH), (1,SURFACE2D_HEIGHT), 0}
3D	{(1,TEXTURE3D_WIDTH), (1,TEXTURE3D_HEIGHT), (1,TEXTURE3D_DEPTH)} OR {(1,TEXTURE3D_WIDTH_ALTERNATE), (1,TEXTURE3D_HEIGHT_ALTERNATE), (1,TEXTURE3D_DEPTH_ALTERNATE)}	{(1,SURFACE3D_WIDTH), (1,SURFACE3D_HEIGHT), (1,SURFACE3D_DEPTH)}
1D Layered	{(1,TEXTURE1D_LAYERED_WIDTH), 0, (1,TEXTURE1D_LAYERED_LAYERS)}	{(1,SURFACE1D_LAYERED_WIDTH), 0, (1,SURFACE1D_LAYERED_LAYERS)}
2D Layered	{(1,TEXTURE2D_LAYERED_WIDTH), (1,TEXTURE2D_LAYERED_HEIGHT), (1,TEXTURE2D_LAYERED_LAYERS)}	{(1,SURFACE2D_LAYERED_WIDTH), (1,SURFACE2D_LAYERED_HEIGHT), (1,SURFACE2D_LAYERED_LAYERS)}
Cubemap	{(1,TEXTURECUBEMAP_WIDTH), (1,TEXTURECUBEMAP_WIDTH), 6}	{(1,SURFACECUBEMAP_WIDTH), (1,SURFACECUBEMAP_WIDTH), 6}
Cubemap Layered	{(1,TEXTURECUBEMAP_LAYERED_WIDTH), (1,TEXTURECUBEMAP_LAYERED_WIDTH), (1,TEXTURECUBEMAP_LAYERED_LAYERS)}	{(1,SURFACECUBEMAP_LAYERED_WIDTH), (1,SURFACECUBEMAP_LAYERED_WIDTH), (1,SURFACECUBEMAP_LAYERED_LAYERS)}

Here are examples of CUDA array descriptions:

Description for a CUDA array of 2048 floats:

```
↑ CUDA\_ARRAY3D\_DESCRIPTOR desc;
   desc.Format = CU_AD_FORMAT_FLOAT;
   desc.NumChannels = 1;
   desc.Width = 2048;
   desc.Height = 0;
   desc.Depth = 0;
```

Description for a 64 x 64 CUDA array of floats:

```
↑ CUDA_ARRAY3D_DESCRIPTOR desc;
   desc.Format = CU_AD_FORMAT_FLOAT;
   desc.NumChannels = 1;
   desc.Width = 64;
   desc.Height = 64;
   desc.Depth = 0;
```

Description for a width x height x depth CUDA array of 64-bit, 4x16-bit float16's:

```
↑ CUDA_ARRAY3D_DESCRIPTOR desc;
   desc.FormatFlags = CU_AD_FORMAT_HALF;
   desc.NumChannels = 4;
   desc.Width = width;
   desc.Height = height;
   desc.Depth = depth;
```



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#), [cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#), [cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#), [cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#), [cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#), [cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#), [cuMemFreeHost](#), [cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#), [cuMemsetD2D8](#), [cuMemsetD2D16](#), [cuMemsetD2D32](#), [cuMemsetD8](#), [cuMemsetD16](#), [cuMemsetD32](#), [cudaMalloc3DArray](#)

CUresult cuArray3DGetDescriptor (CUDA_ARRAY3D_DESCRIPTOR *pArrayDescriptor, CUarray hArray)

Get a 3D CUDA array descriptor.

Parameters

pArrayDescriptor

- Returned 3D array descriptor

hArray

- 3D array to get descriptor of

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_CONTEXT_IS_DESTROYED](#)

Description

Returns in `*pArrayDescriptor` a descriptor containing information on the format and dimensions of the CUDA array `hArray`. It is useful for subroutines that have been passed a CUDA array, but need to know the CUDA array parameters for validation or other purposes.

This function may be called on 1D and 2D arrays, in which case the `Height` and/or `Depth` members of the descriptor struct will be set to 0.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuArray3DCreate](#), [cuArrayCreate](#), [cuArrayDestroy](#), [cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#), [cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#), [cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#), [cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#), [cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#), [cuMemFreeHost](#), [cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#), [cuMemsetD2D8](#), [cuMemsetD2D16](#), [cuMemsetD2D32](#), [cuMemsetD8](#), [cuMemsetD16](#), [cuMemsetD32](#), [cudaArrayGetInfo](#)

CUresult cuArrayCreate (CUarray *pHandle, const CUDA_ARRAY_DESCRIPTOR *pAllocateArray)

Creates a 1D or 2D CUDA array.

Parameters

pHandle

- Returned array

pAllocateArray

- Array descriptor

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_OUT_OF_MEMORY](#), [CUDA_ERROR_UNKNOWN](#)

Description

Creates a CUDA array according to the `CUDA_ARRAY_DESCRIPTOR` structure `pAllocateArray` and returns a handle to the new CUDA array in `*pHandle`. The `CUDA_ARRAY_DESCRIPTOR` is defined as:

```
↑ typedef struct {
    unsigned int Width;
    unsigned int Height;
    CUarray_format Format;
    unsigned int NumChannels;
} CUDA_ARRAY_DESCRIPTOR;
```

where:

- ▶ `Width`, and `Height` are the width, and height of the CUDA array (in elements); the CUDA array is one-dimensional if height is 0, two-dimensional otherwise;
- ▶ `Format` specifies the format of the elements; [CUarray_format](#) is defined as:

```
↑ typedef enum CUarray_format_enum {
    CU_AD_FORMAT_UNSIGNED_INT8 = 0x01,
    CU_AD_FORMAT_UNSIGNED_INT16 = 0x02,
    CU_AD_FORMAT_UNSIGNED_INT32 = 0x03,
    CU_AD_FORMAT_SIGNED_INT8 = 0x08,
    CU_AD_FORMAT_SIGNED_INT16 = 0x09,
    CU_AD_FORMAT_SIGNED_INT32 = 0x0a,
    CU_AD_FORMAT_HALF = 0x10,
    CU_AD_FORMAT_FLOAT = 0x20
} CUarray_format;
```

- ▶ `NumChannels` specifies the number of packed components per CUDA array element; it may be 1, 2, or 4;

Here are examples of CUDA array descriptions:

Description for a CUDA array of 2048 floats:

```
↑ CUDA_ARRAY_DESCRIPTOR desc;
    desc.Format = CU_AD_FORMAT_FLOAT;
    desc.NumChannels = 1;
    desc.Width = 2048;
    desc.Height = 1;
```

Description for a 64 x 64 CUDA array of floats:

```
↑ CUDA_ARRAY_DESCRIPTOR desc;
    desc.Format = CU_AD_FORMAT_FLOAT;
    desc.NumChannels = 1;
    desc.Width = 64;
    desc.Height = 64;
```

Description for a width x height CUDA array of 64-bit, 4x16-bit float16's:

```
↑ CUDA_ARRAY_DESCRIPTOR desc;
    desc.FormatFlags = CU_AD_FORMAT_HALF;
    desc.NumChannels = 4;
    desc.Width = width;
```

```
desc.Height = height;
```

Description for a width x height CUDA array of 16-bit elements, each of which is two 8-bit unsigned chars:

```
↑ CUDA_ARRAY_DESCRIPTOR arrayDesc;
  desc.FormatFlags = CU_AD_FORMAT_UNSIGNED_INT8;
  desc.NumChannels = 2;
  desc.Width = width;
  desc.Height = height;
```



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayDestroy](#), [cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#), [cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#), [cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#), [cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#), [cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#), [cuMemFreeHost](#), [cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#), [cuMemsetD2D8](#), [cuMemsetD2D16](#), [cuMemsetD2D32](#), [cuMemsetD8](#), [cuMemsetD16](#), [cuMemsetD32](#), [cudaMallocArray](#)

CUresult cuArrayDestroy (CUarray hArray)

Destroys a CUDA array.

Parameters

hArray

- Array to destroy

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_ARRAY_IS_MAPPED](#), [CUDA_ERROR_CONTEXT_IS_DESTROYED](#)

Description

Destroys the CUDA array hArray.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#), [cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#), [cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#), [cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#), [cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#), [cuMemFreeHost](#), [cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#), [cuMemsetD2D8](#), [cuMemsetD2D16](#), [cuMemsetD2D32](#), [cuMemsetD8](#), [cuMemsetD16](#), [cuMemsetD32](#), [cudaFreeArray](#)

CUresult cuArrayGetDescriptor (CUDA_ARRAY_DESCRIPTOR *pArrayDescriptor, CUarray hArray)

Get a 1D or 2D CUDA array descriptor.

Parameters

pArrayDescriptor

- Returned array descriptor

hArray

- Array to get descriptor of

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_HANDLE](#)

Description

Returns in *pArrayDescriptor a descriptor containing information on the format and dimensions of the CUDA array hArray. It is useful for subroutines that have been passed a CUDA array, but need to know the CUDA array parameters for validation or other purposes.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#), [cuMemcpy2DAsync](#),

[cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#), [cuMemcpyAtoA](#),
[cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#), [cuMemcpyDtoD](#),
[cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#), [cuMemcpyHtoA](#),
[cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#), [cuMemFreeHost](#),
[cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#),
[cuMemsetD2D8](#), [cuMemsetD2D16](#), [cuMemsetD2D32](#), [cuMemsetD8](#), [cuMemsetD16](#),
[cuMemsetD32](#), [cudaArrayGetInfo](#)

CUresult cuArrayGetPlane (CUarray *pPlaneArray, CUarray hArray, unsigned int planeIdx)

Gets a CUDA array plane from a CUDA array.

Parameters

pPlaneArray

- Returned CUDA array referenced by the `planeIdx`

hArray

- Multiplanar CUDA array

planeIdx

- Plane index

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_INVALID_HANDLE](#)

Description

Returns in `pPlaneArray` a CUDA array that represents a single format plane of the CUDA array `hArray`.

If `planeIdx` is greater than the maximum number of planes in this array or if the array does not have a multi-planar format e.g: [CU_AD_FORMAT_NV12](#), then [CUDA_ERROR_INVALID_VALUE](#) is returned.

Note that if the `hArray` has format [CU_AD_FORMAT_NV12](#), then passing in 0 for `planeIdx` returns a CUDA array of the same size as `hArray` but with one channel and [CU_AD_FORMAT_UNSIGNED_INT8](#) as its format. If 1 is passed for `planeIdx`, then the returned CUDA array has half the height and width of `hArray` with two channels and [CU_AD_FORMAT_UNSIGNED_INT8](#) as its format.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuArrayCreate](#), [cudaGetArrayPlane](#)

CUresult cuArrayGetSparseProperties (CUDA_ARRAY_SPARSE_PROPERTIES *sparseProperties, CUarray array)

Returns the layout properties of a sparse CUDA array.

Parameters**sparseProperties**

- Pointer to CUDA_ARRAY_SPARSE_PROPERTIES

array

- CUDA array to get the sparse properties of

Returns

[CUDA_SUCCESS](#) [CUDA_ERROR_INVALID_VALUE](#)

Description

Returns the layout properties of a sparse CUDA array in `sparseProperties`. If the CUDA array is not allocated with flag [CUDA_ARRAY3D_SPARSE](#) [CUDA_ERROR_INVALID_VALUE](#) will be returned.

If the returned value in [CUDA_ARRAY_SPARSE_PROPERTIES::flags](#) contains [CU_ARRAY_SPARSE_PROPERTIES_SINGLE_MIPTAIL](#), then [CUDA_ARRAY_SPARSE_PROPERTIES::mipTailSize](#) represents the total size of the array. Otherwise, it will be zero. Also, the returned value in [CUDA_ARRAY_SPARSE_PROPERTIES::mipTailFirstLevel](#) is always zero. Note that the `array` must have been allocated using [cuArrayCreate](#) or [cuArray3DCreate](#). For CUDA arrays obtained using [cuMipmappedArrayGetLevel](#), [CUDA_ERROR_INVALID_VALUE](#) will be returned. Instead, [cuMipmappedArrayGetSparseProperties](#) must be used to obtain the sparse properties of the entire CUDA mipmapped array to which `array` belongs to.

See also:

[cuMipmappedArrayGetSparseProperties](#), [cuMemMapArrayAsync](#)

CUresult cuDeviceGetByPCIBusId (CUdevice *dev, const char *pciBusId)

Returns a handle to a compute device.

Parameters

dev

- Returned device handle

pciBusId

- String in one of the following forms: [domain]:[bus]:[device].[function] [domain]:[bus]:[device] [bus]:[device].[function] where `domain`, `bus`, `device`, and `function` are all hexadecimal values

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_DEVICE](#)

Description

Returns in *device a device handle given a PCI bus ID string.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuDeviceGet](#), [cuDeviceGetAttribute](#), [cuDeviceGetPCIBusId](#), [cudaDeviceGetByPCIBusId](#)

CUresult cuDeviceGetPCIBusId (char *pciBusId, int len, CUdevice dev)

Returns a PCI Bus Id string for the device.

Parameters

pciBusId

- Returned identifier string for the device in the following format [domain]:[bus]:[device].[function] where `domain`, `bus`, `device`, and `function` are all hexadecimal values. `pciBusId` should be large enough to store 13 characters including the NULL-terminator.

len

- Maximum length of string to store in name

dev

- Device to get identifier string for

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_DEVICE](#)

Description

Returns an ASCII string identifying the device `dev` in the NULL-terminated string pointed to by `pciBusId`. `len` specifies the maximum length of the string that may be returned.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuDeviceGet](#), [cuDeviceGetAttribute](#), [cuDeviceGetByPCIBusId](#), [cudaDeviceGetPCIBusId](#)

CUresult culpcCloseMemHandle (CUdeviceptr dptr)

Attempts to close memory mapped with `culpcOpenMemHandle`.

Parameters**dptr**

- Device pointer returned by [culpcOpenMemHandle](#)

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_MAP_FAILED](#),
[CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Decrements the reference count of the memory returned by [culpcOpenMemHandle](#) by 1. When the reference count reaches 0, this API unmaps the memory. The original allocation in the exporting process as well as imported mappings in other processes will be unaffected.

Any resources used to enable peer access will be freed if this is the last mapping using them.

IPC functionality is restricted to devices with support for unified addressing on Linux and Windows operating systems. IPC functionality on Windows is restricted to GPUs in TCC mode

See also:

[cuMemAlloc](#), [cuMemFree](#), [culpcGetEventHandle](#), [culpcOpenEventHandle](#),
[culpcGetMemHandle](#), [culpcOpenMemHandle](#), [cudalpcCloseMemHandle](#)

CUresult culpcGetEventHandle (CUipcEventHandle *pHandle, CUevent event)

Gets an interprocess handle for a previously allocated event.

Parameters

pHandle

- Pointer to a user allocated CUipcEventHandle in which to return the opaque event handle

event

- Event allocated with [CU_EVENT_INTERPROCESS](#) and [CU_EVENT_DISABLE_TIMING](#) flags.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_OUT_OF_MEMORY](#),
[CUDA_ERROR_MAP_FAILED](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Takes as input a previously allocated event. This event must have been created with the [CU_EVENT_INTERPROCESS](#) and [CU_EVENT_DISABLE_TIMING](#) flags set. This opaque handle may be copied into other processes and opened with [culpcOpenEventHandle](#) to allow efficient hardware synchronization between GPU work in different processes.

After the event has been opened in the importing process, [cuEventRecord](#), [cuEventSynchronize](#), [cuStreamWaitEvent](#) and [cuEventQuery](#) may be used in either process. Performing operations on the imported event after the exported event has been freed with [cuEventDestroy](#) will result in undefined behavior.

IPC functionality is restricted to devices with support for unified addressing on Linux and Windows operating systems. IPC functionality on Windows is restricted to GPUs in TCC mode

See also:

[cuEventCreate](#), [cuEventDestroy](#), [cuEventSynchronize](#), [cuEventQuery](#), [cuStreamWaitEvent](#),
[culpcOpenEventHandle](#), [culpcGetMemHandle](#), [culpcOpenMemHandle](#), [culpcCloseMemHandle](#),
[cudalpcGetEventHandle](#)

CUresult culpcGetMemHandle (CUipcMemHandle *pHandle, CUdeviceptr dptr)

Gets an interprocess memory handle for an existing device memory allocation.

Parameters

pHandle

- Pointer to user allocated CUipcMemHandle to return the handle in.

dptr

- Base pointer to previously allocated device memory

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_OUT_OF_MEMORY](#), [CUDA_ERROR_MAP_FAILED](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Takes a pointer to the base of an existing device memory allocation created with [cuMemAlloc](#) and exports it for use in another process. This is a lightweight operation and may be called multiple times on an allocation without adverse effects.

If a region of memory is freed with [cuMemFree](#) and a subsequent call to [cuMemAlloc](#) returns memory with the same device address, [culpcGetMemHandle](#) will return a unique handle for the new memory.

IPC functionality is restricted to devices with support for unified addressing on Linux and Windows operating systems. IPC functionality on Windows is restricted to GPUs in TCC mode

See also:

[cuMemAlloc](#), [cuMemFree](#), [culpcGetEventHandle](#), [culpcOpenEventHandle](#), [culpcOpenMemHandle](#), [culpcCloseMemHandle](#), [cudalpcGetMemHandle](#)

CUresult culpcOpenEventHandle (CUevent *phEvent, CUipcEventHandle handle)

Opens an interprocess event handle for use in the current process.

Parameters

phEvent

- Returns the imported event

handle

- Interprocess handle to open

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_MAP_FAILED](#), [CUDA_ERROR_PEER_ACCESS_UNSUPPORTED](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Opens an interprocess event handle exported from another process with [culpcGetEventHandle](#). This function returns a [CUevent](#) that behaves like a locally created event with the [CU_EVENT_DISABLE_TIMING](#) flag specified. This event must be freed with [cuEventDestroy](#).

Performing operations on the imported event after the exported event has been freed with [cuEventDestroy](#) will result in undefined behavior.

IPC functionality is restricted to devices with support for unified addressing on Linux and Windows operating systems. IPC functionality on Windows is restricted to GPUs in TCC mode

See also:

[cuEventCreate](#), [cuEventDestroy](#), [cuEventSynchronize](#), [cuEventQuery](#), [cuStreamWaitEvent](#), [culpcGetEventHandle](#), [culpcGetMemHandle](#), [culpcOpenMemHandle](#), [culpcCloseMemHandle](#), [cudalpcOpenEventHandle](#)

CUresult culpcOpenMemHandle (CUdeviceptr *pdptr, CUipcMemHandle handle, unsigned int Flags)

Opens an interprocess memory handle exported from another process and returns a device pointer usable in the local process.

Parameters

pdptr

- Returned device pointer

handle

- CUipcMemHandle to open

Flags

- Flags for this operation. Must be specified as [CU_IPC_MEM_LAZY_ENABLE_PEER_ACCESS](#)

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_MAP_FAILED](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_TOO_MANY_PEERS](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Maps memory exported from another process with [culpcGetMemHandle](#) into the current device address space. For contexts on different devices [culpcOpenMemHandle](#) can attempt to enable peer access between the devices as if the user called [cuCtxEnablePeerAccess](#). This behavior is controlled by the [CU_IPC_MEM_LAZY_ENABLE_PEER_ACCESS](#) flag. [cuDeviceCanAccessPeer](#) can determine if a mapping is possible.

Contexts that may open CUipcMemHandles are restricted in the following way. CUipcMemHandles from each [CUdevice](#) in a given process may only be opened by one [CUcontext](#) per [CUdevice](#) per other process.

If the memory handle has already been opened by the current context, the reference count on the handle is incremented by 1 and the existing device pointer is returned.

Memory returned from [culpcOpenMemHandle](#) must be freed with [culpcCloseMemHandle](#).

Calling [cuMemFree](#) on an exported memory region before calling [culpcCloseMemHandle](#) in the importing context will result in undefined behavior.

IPC functionality is restricted to devices with support for unified addressing on Linux and Windows operating systems. IPC functionality on Windows is restricted to GPUs in TCC mode



Note:

No guarantees are made about the address returned in `*pdptr`. In particular, multiple processes may not receive the same address for the same handle.

See also:

[cuMemAlloc](#), [cuMemFree](#), [culpcGetEventHandle](#), [culpcOpenEventHandle](#), [culpcGetMemHandle](#), [culpcCloseMemHandle](#), [cuCtxEnablePeerAccess](#), [cuDeviceCanAccessPeer](#), [cudalpcOpenMemHandle](#)

CUresult cuMemAlloc (CUdeviceptr *dptr, size_t bytesize)

Allocates device memory.

Parameters

dptr

- Returned device pointer

bytesize

- Requested allocation size in bytes

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_OUT_OF_MEMORY](#)

Description

Allocates `bytesize` bytes of linear memory on the device and returns in `*dptr` a pointer to the allocated memory. The allocated memory is suitably aligned for any kind of variable. The memory is not cleared. If `bytesize` is 0, [cuMemAlloc\(\)](#) returns [CUDA_ERROR_INVALID_VALUE](#).



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#),
[cuArrayGetDescriptor](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#), [cuMemcpy2DAsync](#),
[cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#), [cuMemcpyAtoA](#),
[cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#), [cuMemcpyDtoD](#),
[cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#), [cuMemcpyHtoA](#),
[cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#), [cuMemFreeHost](#),
[cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#),
[cuMemsetD2D8](#), [cuMemsetD2D16](#), [cuMemsetD2D32](#), [cuMemsetD8](#), [cuMemsetD16](#),
[cuMemsetD32](#), [cudaMalloc](#)

CUresult cuMemAllocHost (void **pp, size_t bytesize)

Allocates page-locked host memory.

Parameters

pp

- Returned host pointer to page-locked memory

bytesize

- Requested allocation size in bytes

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_OUT_OF_MEMORY](#)

Description

Allocates `bytesize` bytes of host memory that is page-locked and accessible to the device. The driver tracks the virtual memory ranges allocated with this function and automatically accelerates calls to functions such as [cuMemcpy\(\)](#). Since the memory can be accessed directly by the device, it can be read or written with much higher bandwidth than pageable memory obtained with functions such as `malloc()`. Allocating excessive amounts of memory with [cuMemAllocHost\(\)](#) may degrade system performance, since it reduces the amount of memory available to the system for paging. As a result, this function is best used sparingly to allocate staging areas for data exchange between host and device.

Note all host memory allocated using [cuMemHostAlloc\(\)](#) will automatically be immediately accessible to all contexts on all devices which support unified addressing (as may be queried using `CU_DEVICE_ATTRIBUTE_UNIFIED_ADDRESSING`). The device pointer that may be used to access this host memory from those contexts is always equal to the returned host pointer `*pp`. See [Unified Addressing](#) for additional details.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#), [cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocPitch](#), [cuMemcpy2D](#), [cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#), [cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#), [cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#), [cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#), [cuMemFreeHost](#), [cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#), [cuMemsetD2D8](#), [cuMemsetD2D16](#), [cuMemsetD2D32](#), [cuMemsetD8](#), [cuMemsetD16](#), [cuMemsetD32](#), [cudaMallocHost](#)

CUresult cuMemAllocManaged (CUdeviceptr *dptr, size_t bytesize, unsigned int flags)

Allocates memory that will be automatically managed by the Unified Memory system.

Parameters

dptr

- Returned device pointer

bytesize

- Requested allocation size in bytes

flags

- Must be one of [CU_MEM_ATTACH_GLOBAL](#) or [CU_MEM_ATTACH_HOST](#)

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_NOT_SUPPORTED](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_OUT_OF_MEMORY](#)

Description

Allocates `bytesize` bytes of managed memory on the device and returns in `*dptr` a pointer to the allocated memory. If the device doesn't support allocating managed memory, [CUDA_ERROR_NOT_SUPPORTED](#) is returned. Support for managed memory can be queried using the device attribute [CU_DEVICE_ATTRIBUTE_MANAGED_MEMORY](#). The allocated memory is suitably aligned for any kind of variable. The memory is not cleared. If `bytesize` is 0, [cuMemAllocManaged](#) returns [CUDA_ERROR_INVALID_VALUE](#). The pointer is valid on the CPU and on all GPUs in the system that support managed memory. All accesses to this pointer must obey the Unified Memory programming model.

`flags` specifies the default stream association for this allocation. `flags` must be one of [CU_MEM_ATTACH_GLOBAL](#) or [CU_MEM_ATTACH_HOST](#). If [CU_MEM_ATTACH_GLOBAL](#) is specified, then this memory is accessible from any stream on any device. If [CU_MEM_ATTACH_HOST](#) is specified, then the allocation should not be accessed from devices that have a zero value for the device attribute [CU_DEVICE_ATTRIBUTE_CONCURRENT_MANAGED_ACCESS](#); an explicit call to [cuStreamAttachMemAsync](#) will be required to enable access on such devices.

If the association is later changed via [cuStreamAttachMemAsync](#) to a single stream, the default association as specified during [cuMemAllocManaged](#) is restored when that stream is destroyed. For `__managed__` variables, the default association is always [CU_MEM_ATTACH_GLOBAL](#). Note that destroying a stream is an asynchronous operation, and as a result, the change to default association won't happen until all work in the stream has completed.

Memory allocated with [cuMemAllocManaged](#) should be released with [cuMemFree](#).

Device memory oversubscription is possible for GPUs that have a non-zero value for the device attribute [CU_DEVICE_ATTRIBUTE_CONCURRENT_MANAGED_ACCESS](#). Managed memory on such GPUs may be evicted from device memory to host memory at any time by the Unified Memory driver in order to make room for other allocations.

In a multi-GPU system where all GPUs have a non-zero value for the device attribute [CU_DEVICE_ATTRIBUTE_CONCURRENT_MANAGED_ACCESS](#), managed memory may not be populated when this API returns and instead may be populated on access. In such systems, managed memory can migrate to any processor's memory at any time. The Unified Memory driver will employ heuristics to maintain data locality and prevent excessive page faults to the extent possible. The application can also guide the driver about memory usage patterns via

[cuMemAdvise](#). The application can also explicitly migrate memory to a desired processor's memory via [cuMemPrefetchAsync](#).

In a multi-GPU system where all of the GPUs have a zero value for the device attribute [CU_DEVICE_ATTRIBUTE_CONCURRENT_MANAGED_ACCESS](#) and all the GPUs have peer-to-peer support with each other, the physical storage for managed memory is created on the GPU which is active at the time [cuMemAllocManaged](#) is called. All other GPUs will reference the data at reduced bandwidth via peer mappings over the PCIe bus. The Unified Memory driver does not migrate memory among such GPUs.

In a multi-GPU system where not all GPUs have peer-to-peer support with each other and where the value of the device attribute [CU_DEVICE_ATTRIBUTE_CONCURRENT_MANAGED_ACCESS](#) is zero for at least one of those GPUs, the location chosen for physical storage of managed memory is system-dependent.

- ▶ On Linux, the location chosen will be device memory as long as the current set of active contexts are on devices that either have peer-to-peer support with each other or have a non-zero value for the device attribute [CU_DEVICE_ATTRIBUTE_CONCURRENT_MANAGED_ACCESS](#). If there is an active context on a GPU that does not have a non-zero value for that device attribute and it does not have peer-to-peer support with the other devices that have active contexts on them, then the location for physical storage will be 'zero-copy' or host memory. Note that this means that managed memory that is located in device memory is migrated to host memory if a new context is created on a GPU that doesn't have a non-zero value for the device attribute and does not support peer-to-peer with at least one of the other devices that has an active context. This in turn implies that context creation may fail if there is insufficient host memory to migrate all managed allocations.
- ▶ On Windows, the physical storage is always created in 'zero-copy' or host memory. All GPUs will reference the data at reduced bandwidth over the PCIe bus. In these circumstances, use of the environment variable `CUDA_VISIBLE_DEVICES` is recommended to restrict CUDA to only use those GPUs that have peer-to-peer support. Alternatively, users can also set `CUDA_MANAGED_FORCE_DEVICE_ALLOC` to a non-zero value to force the driver to always use device memory for physical storage. When this environment variable is set to a non-zero value, all contexts created in that process on devices that support managed memory have to be peer-to-peer compatible with each other. Context creation will fail if a context is created on a device that supports managed memory and is not peer-to-peer compatible with any of the other managed memory supporting devices on which contexts were previously created, even if those contexts have been destroyed. These environment variables are described in the CUDA programming guide under the "CUDA environment variables" section.
- ▶ On ARM, managed memory is not available on discrete gpu with Drive PX-2.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#), [cuArrayGetDescriptor](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#), [cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#), [cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#), [cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#), [cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#), [cuMemFreeHost](#), [cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#), [cuMemsetD2D8](#), [cuMemsetD2D16](#), [cuMemsetD2D32](#), [cuMemsetD8](#), [cuMemsetD16](#), [cuMemsetD32](#), [cuDeviceGetAttribute](#), [cuStreamAttachMemAsync](#), [cudaMallocManaged](#)

CUresult cuMemAllocPitch (CUdeviceptr *dptr, size_t *pPitch, size_t WidthInBytes, size_t Height, unsigned int ElementSizeBytes)

Allocates pitched device memory.

Parameters

dptr

- Returned device pointer

pPitch

- Returned pitch of allocation in bytes

WidthInBytes

- Requested allocation width in bytes

Height

- Requested allocation height in rows

ElementSizeBytes

- Size of largest reads/writes for range

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_OUT_OF_MEMORY](#)

Description

Allocates at least `WidthInBytes * Height` bytes of linear memory on the device and returns in `*dptr` a pointer to the allocated memory. The function may pad the allocation to ensure that corresponding pointers in any given row will continue to meet the alignment requirements for coalescing as the address is updated from row to row. `ElementSizeBytes`

specifies the size of the largest reads and writes that will be performed on the memory range. `ElementSizeBytes` may be 4, 8 or 16 (since coalesced memory transactions are not possible on other data sizes). If `ElementSizeBytes` is smaller than the actual read/write size of a kernel, the kernel will run correctly, but possibly at reduced speed. The pitch returned in `*pPitch` by [cuMemAllocPitch\(\)](#) is the width in bytes of the allocation. The intended usage of pitch is as a separate parameter of the allocation, used to compute addresses within the 2D array. Given the row and column of an array element of type `T`, the address is computed as:

```
↑ T* pElement = (T*)((char*)BaseAddress + Row * Pitch) + Column;
```

The pitch returned by [cuMemAllocPitch\(\)](#) is guaranteed to work with [cuMemcpy2D\(\)](#) under all circumstances. For allocations of 2D arrays, it is recommended that programmers consider performing pitch allocations using [cuMemAllocPitch\(\)](#). Due to alignment restrictions in the hardware, this is especially true if the application will be performing 2D memory copies between different regions of device memory (whether linear memory or CUDA arrays).

The byte alignment of the pitch returned by [cuMemAllocPitch\(\)](#) is guaranteed to match or exceed the alignment requirement for texture binding with [cuTexRefSetAddress2D\(\)](#).



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#), [cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemcpy2D](#), [cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#), [cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#), [cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#), [cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#), [cuMemFreeHost](#), [cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#), [cuMemsetD2D8](#), [cuMemsetD2D16](#), [cuMemsetD2D32](#), [cuMemsetD8](#), [cuMemsetD16](#), [cuMemsetD32](#), [cudaMallocPitch](#)

CUresult cuMemcpy (CUdeviceptr dst, CUdeviceptr src, size_t ByteCount)

Copies memory.

Parameters

dst

- Destination unified virtual address space pointer

src

- Source unified virtual address space pointer

ByteCount

- Size of memory copy in bytes

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Copies data between two pointers. `dst` and `src` are base pointers of the destination and source, respectively. `ByteCount` specifies the number of bytes to copy. Note that this function infers the type of the transfer (host to host, host to device, device to device, or device to host) from the pointer values. This function is only allowed in contexts which support unified addressing.

**Note:**

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ This function exhibits [synchronous](#) behavior for most use cases.
- ▶ Memory regions requested must be either entirely registered with CUDA, or in the case of host pageable transfers, not registered at all. Memory regions spanning over allocations that are both registered and not registered with CUDA are not supported and will return `CUDA_ERROR_INVALID_VALUE`.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#),
[cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#),
[cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#),
[cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#),
[cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#), [cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#),
[cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#), [cuMemFreeHost](#),
[cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#),
[cuMemsetD2D8](#), [cuMemsetD2D16](#), [cuMemsetD2D32](#), [cuMemsetD8](#), [cuMemsetD16](#),
[cuMemsetD32](#), [cudaMemcpy](#), [cudaMemcpyToSymbol](#), [cudaMemcpyFromSymbol](#)

CUresult cuMemcpy2D (const CUDA_MEMCPY2D *pCopy)

Copies memory for 2D arrays.

Parameters

pCopy

- Parameters for the memory copy

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Perform a 2D memory copy according to the parameters specified in pCopy. The CUDA_MEMCPY2D structure is defined as:

```
↑ typedef struct CUDA_MEMCPY2D_st {
    unsigned int srcXInBytes, srcY;
    CUmemorytype srcMemoryType;
    const void *srcHost;
    CUdeviceptr srcDevice;
    CUarray srcArray;
    unsigned int srcPitch;

    unsigned int dstXInBytes, dstY;
    CUmemorytype dstMemoryType;
    void *dstHost;
    CUdeviceptr dstDevice;
    CUarray dstArray;
    unsigned int dstPitch;

    unsigned int WidthInBytes;
    unsigned int Height;
} CUDA\_MEMCPY2D;
```

where:

- ▶ srcMemoryType and dstMemoryType specify the type of memory of the source and destination, respectively; CUmemorytype_enum is defined as:

```
↑ typedef enum CUmemorytype_enum {
    CU\_MEMORYTYPE\_HOST = 0x01,
    CU\_MEMORYTYPE\_DEVICE = 0x02,
    CU\_MEMORYTYPE\_ARRAY = 0x03,
    CU\_MEMORYTYPE\_UNIFIED = 0x04
} CUmemorytype;
```

If srcMemoryType is [CU_MEMORYTYPE_UNIFIED](#), srcDevice and srcPitch specify the (unified virtual address space) base address of the source data and the bytes per row to apply. srcArray is ignored. This value may be used only if unified addressing is supported in the calling context.

If `srcMemoryType` is `CU_MEMORYTYPE_HOST`, `srcHost` and `srcPitch` specify the (host) base address of the source data and the bytes per row to apply. `srcArray` is ignored.

If `srcMemoryType` is `CU_MEMORYTYPE_DEVICE`, `srcDevice` and `srcPitch` specify the (device) base address of the source data and the bytes per row to apply. `srcArray` is ignored.

If `srcMemoryType` is `CU_MEMORYTYPE_ARRAY`, `srcArray` specifies the handle of the source data. `srcHost`, `srcDevice` and `srcPitch` are ignored.

If `dstMemoryType` is `CU_MEMORYTYPE_HOST`, `dstHost` and `dstPitch` specify the (host) base address of the destination data and the bytes per row to apply. `dstArray` is ignored.

If `dstMemoryType` is `CU_MEMORYTYPE_UNIFIED`, `dstDevice` and `dstPitch` specify the (unified virtual address space) base address of the source data and the bytes per row to apply. `dstArray` is ignored. This value may be used only if unified addressing is supported in the calling context.

If `dstMemoryType` is `CU_MEMORYTYPE_DEVICE`, `dstDevice` and `dstPitch` specify the (device) base address of the destination data and the bytes per row to apply. `dstArray` is ignored.

If `dstMemoryType` is `CU_MEMORYTYPE_ARRAY`, `dstArray` specifies the handle of the destination data. `dstHost`, `dstDevice` and `dstPitch` are ignored.

- ▶ `srcXInBytes` and `srcY` specify the base address of the source data for the copy.

For host pointers, the starting address is

```
↑ void* Start = (void*)((char*)srcHost+srcY*srcPitch + srcXInBytes);
```

For device pointers, the starting address is

```
↑ CUdeviceptr Start = srcDevice+srcY*srcPitch+srcXInBytes;
```

For CUDA arrays, `srcXInBytes` must be evenly divisible by the array element size.

- ▶ `dstXInBytes` and `dstY` specify the base address of the destination data for the copy.

For host pointers, the base address is

```
↑ void* dstStart = (void*)((char*)dstHost+dstY*dstPitch + dstXInBytes);
```

For device pointers, the starting address is

```
↑ CUdeviceptr dstStart = dstDevice+dstY*dstPitch+dstXInBytes;
```

For CUDA arrays, `dstXInBytes` must be evenly divisible by the array element size.

- ▶ `WidthInBytes` and `Height` specify the width (in bytes) and height of the 2D copy being performed.
- ▶ If specified, `srcPitch` must be greater than or equal to `WidthInBytes + srcXInBytes`, and `dstPitch` must be greater than or equal to `WidthInBytes + dstXInBytes`.

[cuMemcpy2D\(\)](#) returns an error if any pitch is greater than the maximum allowed ([CU_DEVICE_ATTRIBUTE_MAX_PITCH](#)). [cuMemAllocPitch\(\)](#) passes back pitches that always work with [cuMemcpy2D\(\)](#). On intra-device memory copies (device to device, CUDA array to device, CUDA array to CUDA array), [cuMemcpy2D\(\)](#) may fail for pitches not computed by [cuMemAllocPitch\(\)](#). [cuMemcpy2DUnaligned\(\)](#) does not have this restriction, but may run significantly slower in the cases where [cuMemcpy2D\(\)](#) would have returned an error code.

**Note:**

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ This function exhibits [synchronous](#) behavior for most use cases.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#),
[cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2DAsync](#),
[cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#), [cuMemcpyAtoA](#),
[cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#), [cuMemcpyDtoD](#),
[cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#), [cuMemcpyHtoA](#),
[cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#), [cuMemFreeHost](#),
[cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#),
[cuMemsetD2D8](#), [cuMemsetD2D16](#), [cuMemsetD2D32](#), [cuMemsetD8](#), [cuMemsetD16](#),
[cuMemsetD32](#), [cudaMemcpy2D](#), [cudaMemcpy2DToArray](#), [cudaMemcpy2DFromArray](#)

CUresult cuMemcpy2DAsync (const CUDA_MEMCPY2D *pCopy, CUstream hStream)

Copies memory for 2D arrays.

Parameters

pCopy

- Parameters for the memory copy

hStream

- Stream identifier

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_INVALID_HANDLE](#)

Description

Perform a 2D memory copy according to the parameters specified in `pCopy`. The `CUDA_MEMCPY2D` structure is defined as:

```
↑ typedef struct CUDA_MEMCPY2D_st {
    unsigned int srcXInBytes, srcY;
    CUmemorytype srcMemoryType;
    const void *srcHost;
    CUdeviceptr srcDevice;
    CUarray srcArray;
    unsigned int srcPitch;
    unsigned int dstXInBytes, dstY;
    CUmemorytype dstMemoryType;
    void *dstHost;
    CUdeviceptr dstDevice;
    CUarray dstArray;
    unsigned int dstPitch;
    unsigned int WidthInBytes;
    unsigned int Height;
} CUDA_MEMCPY2D;
```

where:

- ▶ `srcMemoryType` and `dstMemoryType` specify the type of memory of the source and destination, respectively; `CUmemorytype_enum` is defined as:

```
↑ typedef enum CUmemorytype_enum {
    CU_MEMORYTYPE_HOST = 0x01,
    CU_MEMORYTYPE_DEVICE = 0x02,
    CU_MEMORYTYPE_ARRAY = 0x03,
    CU_MEMORYTYPE_UNIFIED = 0x04
} CUmemorytype;
```

If `srcMemoryType` is `CU_MEMORYTYPE_HOST`, `srcHost` and `srcPitch` specify the (host) base address of the source data and the bytes per row to apply. `srcArray` is ignored.

If `srcMemoryType` is `CU_MEMORYTYPE_UNIFIED`, `srcDevice` and `srcPitch` specify the (unified virtual address space) base address of the source data and the bytes per row to apply. `srcArray` is ignored. This value may be used only if unified addressing is supported in the calling context.

If `srcMemoryType` is `CU_MEMORYTYPE_DEVICE`, `srcDevice` and `srcPitch` specify the (device) base address of the source data and the bytes per row to apply. `srcArray` is ignored.

If `srcMemoryType` is `CU_MEMORYTYPE_ARRAY`, `srcArray` specifies the handle of the source data. `srcHost`, `srcDevice` and `srcPitch` are ignored.

If `dstMemoryType` is `CU_MEMORYTYPE_UNIFIED`, `dstDevice` and `dstPitch` specify the (unified virtual address space) base address of the source data and the bytes per row to apply. `dstArray` is ignored. This value may be used only if unified addressing is supported in the calling context.

If `dstMemoryType` is `CU_MEMORYTYPE_HOST`, `dstHost` and `dstPitch` specify the (host) base address of the destination data and the bytes per row to apply. `dstArray` is ignored.

If `dstMemoryType` is [CU_MEMORYTYPE_DEVICE](#), `dstDevice` and `dstPitch` specify the (device) base address of the destination data and the bytes per row to apply. `dstArray` is ignored.

If `dstMemoryType` is [CU_MEMORYTYPE_ARRAY](#), `dstArray` specifies the handle of the destination data. `dstHost`, `dstDevice` and `dstPitch` are ignored.

- ▶ `srcXInBytes` and `srcY` specify the base address of the source data for the copy.

For host pointers, the starting address is

```
↑ void* Start = (void*)((char*)srcHost+srcY*srcPitch + srcXInBytes);
```

For device pointers, the starting address is

```
↑ CUdeviceptr Start = srcDevice+srcY*srcPitch+srcXInBytes;
```

For CUDA arrays, `srcXInBytes` must be evenly divisible by the array element size.

- ▶ `dstXInBytes` and `dstY` specify the base address of the destination data for the copy.

For host pointers, the base address is

```
↑ void* dstStart = (void*)((char*)dstHost+dstY*dstPitch + dstXInBytes);
```

For device pointers, the starting address is

```
↑ CUdeviceptr dstStart = dstDevice+dstY*dstPitch+dstXInBytes;
```

For CUDA arrays, `dstXInBytes` must be evenly divisible by the array element size.

- ▶ `WidthInBytes` and `Height` specify the width (in bytes) and height of the 2D copy being performed.
- ▶ If specified, `srcPitch` must be greater than or equal to `WidthInBytes + srcXInBytes`, and `dstPitch` must be greater than or equal to `WidthInBytes + dstXInBytes`.
- ▶ If specified, `srcPitch` must be greater than or equal to `WidthInBytes + srcXInBytes`, and `dstPitch` must be greater than or equal to `WidthInBytes + dstXInBytes`.
- ▶ If specified, `srcHeight` must be greater than or equal to `Height + srcY`, and `dstHeight` must be greater than or equal to `Height + dstY`.

[cuMemcpy2DAsync\(\)](#) returns an error if any pitch is greater than the maximum allowed ([CU_DEVICE_ATTRIBUTE_MAX_PITCH](#)). [cuMemAllocPitch\(\)](#) passes back pitches that always work with [cuMemcpy2D\(\)](#). On intra-device memory copies (device to device, CUDA array to device, CUDA array to CUDA array), [cuMemcpy2DAsync\(\)](#) may fail for pitches not computed by [cuMemAllocPitch\(\)](#).



Note:

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ This function exhibits [asynchronous](#) behavior for most use cases.
- ▶ This function uses standard [default stream](#) semantics.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#), [cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#), [cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#), [cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#), [cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#), [cuMemFreeHost](#), [cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#), [cuMemsetD2D8](#), [cuMemsetD2D8Async](#), [cuMemsetD2D16](#), [cuMemsetD2D16Async](#), [cuMemsetD2D32](#), [cuMemsetD2D32Async](#), [cuMemsetD8](#), [cuMemsetD8Async](#), [cuMemsetD16](#), [cuMemsetD16Async](#), [cuMemsetD32](#), [cuMemsetD32Async](#), [cudaMemcpy2DAsync](#), [cudaMemcpy2DToArrayAsync](#), [cudaMemcpy2DFromArrayAsync](#)

CUresult cuMemcpy2DUnaligned (const CUDA_MEMCPY2D *pCopy)

Copies memory for 2D arrays.

Parameters

pCopy

- Parameters for the memory copy

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Perform a 2D memory copy according to the parameters specified in pCopy. The CUDA_MEMCPY2D structure is defined as:

```
↑ typedef struct CUDA_MEMCPY2D_st {
    unsigned int srcXInBytes, srcY;
    CUmemorytype srcMemoryType;
    const void *srcHost;
    CUdeviceptr srcDevice;
    CUarray srcArray;
    unsigned int srcPitch;
    unsigned int dstXInBytes, dstY;
    CUmemorytype dstMemoryType;
    void *dstHost;
    CUdeviceptr dstDevice;
    CUarray dstArray;
    unsigned int dstPitch;
    unsigned int WidthInBytes;
    unsigned int Height;
} CUDA_MEMCPY2D;
```

where:

- `srcMemoryType` and `dstMemoryType` specify the type of memory of the source and destination, respectively; `CUmemorytype_enum` is defined as:

```
↑ typedef enum CUmemorytype_enum {
    CU_MEMORYTYPE_HOST = 0x01,
    CU_MEMORYTYPE_DEVICE = 0x02,
    CU_MEMORYTYPE_ARRAY = 0x03,
    CU_MEMORYTYPE_UNIFIED = 0x04
} CUmemorytype;
```

If `srcMemoryType` is `CU_MEMORYTYPE_UNIFIED`, `srcDevice` and `srcPitch` specify the (unified virtual address space) base address of the source data and the bytes per row to apply. `srcArray` is ignored. This value may be used only if unified addressing is supported in the calling context.

If `srcMemoryType` is `CU_MEMORYTYPE_HOST`, `srcHost` and `srcPitch` specify the (host) base address of the source data and the bytes per row to apply. `srcArray` is ignored.

If `srcMemoryType` is `CU_MEMORYTYPE_DEVICE`, `srcDevice` and `srcPitch` specify the (device) base address of the source data and the bytes per row to apply. `srcArray` is ignored.

If `srcMemoryType` is `CU_MEMORYTYPE_ARRAY`, `srcArray` specifies the handle of the source data. `srcHost`, `srcDevice` and `srcPitch` are ignored.

If `dstMemoryType` is `CU_MEMORYTYPE_UNIFIED`, `dstDevice` and `dstPitch` specify the (unified virtual address space) base address of the source data and the bytes per row to apply. `dstArray` is ignored. This value may be used only if unified addressing is supported in the calling context.

If `dstMemoryType` is `CU_MEMORYTYPE_HOST`, `dstHost` and `dstPitch` specify the (host) base address of the destination data and the bytes per row to apply. `dstArray` is ignored.

If `dstMemoryType` is `CU_MEMORYTYPE_DEVICE`, `dstDevice` and `dstPitch` specify the (device) base address of the destination data and the bytes per row to apply. `dstArray` is ignored.

If `dstMemoryType` is `CU_MEMORYTYPE_ARRAY`, `dstArray` specifies the handle of the destination data. `dstHost`, `dstDevice` and `dstPitch` are ignored.

- `srcXInBytes` and `srcY` specify the base address of the source data for the copy.

For host pointers, the starting address is

```
↑ void* Start = (void*)((char*)srcHost+srcY*srcPitch + srcXInBytes);
```

For device pointers, the starting address is

```
↑ CUdeviceptr Start = srcDevice+srcY*srcPitch+srcXInBytes;
```

For CUDA arrays, `srcXInBytes` must be evenly divisible by the array element size.

- `dstXInBytes` and `dstY` specify the base address of the destination data for the copy.

For host pointers, the base address is

```
↑ void* dstStart = (void*)((char*)dstHost+dstY*dstPitch + dstXInBytes);
```

For device pointers, the starting address is

```
↑ CUdeviceptr dstStart = dstDevice+dstY*dstPitch+dstXInBytes;
```

For CUDA arrays, `dstXInBytes` must be evenly divisible by the array element size.

- ▶ `WidthInBytes` and `Height` specify the width (in bytes) and height of the 2D copy being performed.
- ▶ If specified, `srcPitch` must be greater than or equal to `WidthInBytes + srcXInBytes`, and `dstPitch` must be greater than or equal to `WidthInBytes + dstXInBytes`.

[cuMemcpy2D\(\)](#) returns an error if any pitch is greater than the maximum allowed (`CU_DEVICE_ATTRIBUTE_MAX_PITCH`). [cuMemAllocPitch\(\)](#) passes back pitches that always work with [cuMemcpy2D\(\)](#). On intra-device memory copies (device to device, CUDA array to device, CUDA array to CUDA array), [cuMemcpy2D\(\)](#) may fail for pitches not computed by [cuMemAllocPitch\(\)](#). [cuMemcpy2DUnaligned\(\)](#) does not have this restriction, but may run significantly slower in the cases where [cuMemcpy2D\(\)](#) would have returned an error code.



Note:

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ This function exhibits [synchronous](#) behavior for most use cases.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#),
[cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#),
[cuMemcpy2D](#), [cuMemcpy2DAsync](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#), [cuMemcpyAtoA](#),
[cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#), [cuMemcpyDtoD](#),
[cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#), [cuMemcpyHtoA](#),
[cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#), [cuMemFreeHost](#),
[cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#),
[cuMemsetD2D8](#), [cuMemsetD2D16](#), [cuMemsetD2D32](#), [cuMemsetD8](#), [cuMemsetD16](#),
[cuMemsetD32](#), [cudaMemcpy2D](#), [cudaMemcpy2DToArray](#), [cudaMemcpy2DFromArray](#)

CUresult cuMemcpy3D (const CUDA_MEMCPY3D *pCopy)

Copies memory for 3D arrays.

Parameters

pCopy

- Parameters for the memory copy

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Perform a 3D memory copy according to the parameters specified in pCopy. The CUDA_MEMCPY3D structure is defined as:

```
↑ typedef struct CUDA_MEMCPY3D_st {
    unsigned int srcXInBytes, srcY, srcZ;
    unsigned int srcLOD;
    CUmemorytype srcMemoryType;
    const void *srcHost;
    CUdeviceptr srcDevice;
    CUarray srcArray;
    unsigned int srcPitch; // ignored when src is array
    unsigned int srcHeight; // ignored when src is array; may be 0
if Depth==1

    unsigned int dstXInBytes, dstY, dstZ;
    unsigned int dstLOD;
    CUmemorytype dstMemoryType;
    void *dstHost;
    CUdeviceptr dstDevice;
    CUarray dstArray;
    unsigned int dstPitch; // ignored when dst is array
    unsigned int dstHeight; // ignored when dst is array; may be 0
if Depth==1

    unsigned int WidthInBytes;
    unsigned int Height;
    unsigned int Depth;
} CUDA_MEMCPY3D;
```

where:

- ▶ srcMemoryType and dstMemoryType specify the type of memory of the source and destination, respectively; CUmemorytype_enum is defined as:

```
↑ typedef enum CUmemorytype_enum {
    CU_MEMORYTYPE_HOST = 0x01,
    CU_MEMORYTYPE_DEVICE = 0x02,
    CU_MEMORYTYPE_ARRAY = 0x03,
    CU_MEMORYTYPE_UNIFIED = 0x04
} CUmemorytype;
```

If `srcMemoryType` is `CU_MEMORYTYPE_UNIFIED`, `srcDevice` and `srcPitch` specify the (unified virtual address space) base address of the source data and the bytes per row to apply. `srcArray` is ignored. This value may be used only if unified addressing is supported in the calling context.

If `srcMemoryType` is `CU_MEMORYTYPE_HOST`, `srcHost`, `srcPitch` and `srcHeight` specify the (host) base address of the source data, the bytes per row, and the height of each 2D slice of the 3D array. `srcArray` is ignored.

If `srcMemoryType` is `CU_MEMORYTYPE_DEVICE`, `srcDevice`, `srcPitch` and `srcHeight` specify the (device) base address of the source data, the bytes per row, and the height of each 2D slice of the 3D array. `srcArray` is ignored.

If `srcMemoryType` is `CU_MEMORYTYPE_ARRAY`, `srcArray` specifies the handle of the source data. `srcHost`, `srcDevice`, `srcPitch` and `srcHeight` are ignored.

If `dstMemoryType` is `CU_MEMORYTYPE_UNIFIED`, `dstDevice` and `dstPitch` specify the (unified virtual address space) base address of the source data and the bytes per row to apply. `dstArray` is ignored. This value may be used only if unified addressing is supported in the calling context.

If `dstMemoryType` is `CU_MEMORYTYPE_HOST`, `dstHost` and `dstPitch` specify the (host) base address of the destination data, the bytes per row, and the height of each 2D slice of the 3D array. `dstArray` is ignored.

If `dstMemoryType` is `CU_MEMORYTYPE_DEVICE`, `dstDevice` and `dstPitch` specify the (device) base address of the destination data, the bytes per row, and the height of each 2D slice of the 3D array. `dstArray` is ignored.

If `dstMemoryType` is `CU_MEMORYTYPE_ARRAY`, `dstArray` specifies the handle of the destination data. `dstHost`, `dstDevice`, `dstPitch` and `dstHeight` are ignored.

- `srcXInBytes`, `srcY` and `srcZ` specify the base address of the source data for the copy.

For host pointers, the starting address is

```
↑ void* Start = (void*)((char*)srcHost+(srcZ*srcHeight+srcY)*srcPitch +
srcXInBytes);
```

For device pointers, the starting address is

```
↑ CUdeviceptr Start = srcDevice+(srcZ*srcHeight+srcY)*srcPitch+srcXInBytes;
```

For CUDA arrays, `srcXInBytes` must be evenly divisible by the array element size.

- `dstXInBytes`, `dstY` and `dstZ` specify the base address of the destination data for the copy.

For host pointers, the base address is

```
↑ void* dstStart = (void*)((char*)dstHost+(dstZ*dstHeight+dstY)*dstPitch +
dstXInBytes);
```

For device pointers, the starting address is


```
↑ CUdeviceptr dstStart = dstDevice+(dstZ*dstHeight+dstY)*dstPitch+dstXInBytes;
```

For CUDA arrays, `dstXInBytes` must be evenly divisible by the array element size.

- ▶ `WidthInBytes`, `Height` and `Depth` specify the width (in bytes), height and depth of the 3D copy being performed.
- ▶ If specified, `srcPitch` must be greater than or equal to `WidthInBytes + srcXInBytes`, and `dstPitch` must be greater than or equal to `WidthInBytes + dstXInBytes`.
- ▶ If specified, `srcHeight` must be greater than or equal to `Height + srcY`, and `dstHeight` must be greater than or equal to `Height + dstY`.

`cuMemcpy3D()` returns an error if any pitch is greater than the maximum allowed (`CU_DEVICE_ATTRIBUTE_MAX_PITCH`).

The `srcLOD` and `dstLOD` members of the `CUDA_MEMCPY3D` structure must be set to 0.

 **Note:**

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ This function exhibits [synchronous](#) behavior for most use cases.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#), [cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#), [cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3DAsync](#), [cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#), [cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#), [cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#), [cuMemFreeHost](#), [cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#), [cuMemsetD2D8](#), [cuMemsetD2D16](#), [cuMemsetD2D32](#), [cuMemsetD8](#), [cuMemsetD16](#), [cuMemsetD32](#), [cudaMemcpy3D](#)

CUresult cuMemcpy3DAsync (const CUDA_MEMCPY3D *pCopy, CUstream hStream)

Copies memory for 3D arrays.

Parameters

pCopy

- Parameters for the memory copy

hStream

- Stream identifier

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_INVALID_HANDLE](#)

Description

Perform a 3D memory copy according to the parameters specified in `pCopy`. The `CUDA_MEMCPY3D` structure is defined as:

```
↑ typedef struct CUDA_MEMCPY3D_st {
    unsigned int srcXInBytes, srcY, srcZ;
    unsigned int srcLOD;
    CUmemorytype srcMemoryType;
    const void *srcHost;
    CUdeviceptr srcDevice;
    CUarray srcArray;
    unsigned int srcPitch; // ignored when src is array
    unsigned int srcHeight; // ignored when src is array; may be 0
if Depth==1

    unsigned int dstXInBytes, dstY, dstZ;
    unsigned int dstLOD;
    CUmemorytype dstMemoryType;
    void *dstHost;
    CUdeviceptr dstDevice;
    CUarray dstArray;
    unsigned int dstPitch; // ignored when dst is array
    unsigned int dstHeight; // ignored when dst is array; may be 0
if Depth==1

    unsigned int WidthInBytes;
    unsigned int Height;
    unsigned int Depth;
} CUDA_MEMCPY3D;
```

where:

- `srcMemoryType` and `dstMemoryType` specify the type of memory of the source and destination, respectively; `CUmemorytype_enum` is defined as:

```
↑ typedef enum CUmemorytype_enum {
    CU_MEMORYTYPE_HOST = 0x01,
    CU_MEMORYTYPE_DEVICE = 0x02,
    CU_MEMORYTYPE_ARRAY = 0x03,
    CU_MEMORYTYPE_UNIFIED = 0x04
} CUmemorytype;
```

If `srcMemoryType` is `CU_MEMORYTYPE_UNIFIED`, `srcDevice` and `srcPitch` specify the (unified virtual address space) base address of the source data and the bytes per row to apply. `srcArray` is ignored. This value may be used only if unified addressing is supported in the calling context.

If `srcMemoryType` is `CU_MEMORYTYPE_HOST`, `srcHost`, `srcPitch` and `srcHeight` specify the (host) base address of the source data, the bytes per row, and the height of each 2D slice of the 3D array. `srcArray` is ignored.

If `srcMemoryType` is `CU_MEMORYTYPE_DEVICE`, `srcDevice`, `srcPitch` and `srcHeight` specify the (device) base address of the source data, the bytes per row, and the height of each 2D slice of the 3D array. `srcArray` is ignored.

If `srcMemoryType` is `CU_MEMORYTYPE_ARRAY`, `srcArray` specifies the handle of the source data. `srcHost`, `srcDevice`, `srcPitch` and `srcHeight` are ignored.

If `dstMemoryType` is `CU_MEMORYTYPE_UNIFIED`, `dstDevice` and `dstPitch` specify the (unified virtual address space) base address of the source data and the bytes per row to apply. `dstArray` is ignored. This value may be used only if unified addressing is supported in the calling context.

If `dstMemoryType` is `CU_MEMORYTYPE_HOST`, `dstHost` and `dstPitch` specify the (host) base address of the destination data, the bytes per row, and the height of each 2D slice of the 3D array. `dstArray` is ignored.

If `dstMemoryType` is `CU_MEMORYTYPE_DEVICE`, `dstDevice` and `dstPitch` specify the (device) base address of the destination data, the bytes per row, and the height of each 2D slice of the 3D array. `dstArray` is ignored.

If `dstMemoryType` is `CU_MEMORYTYPE_ARRAY`, `dstArray` specifies the handle of the destination data. `dstHost`, `dstDevice`, `dstPitch` and `dstHeight` are ignored.

- ▶ `srcXInBytes`, `srcY` and `srcZ` specify the base address of the source data for the copy.

For host pointers, the starting address is

```
↑ void* Start = (void*)((char*)srcHost+(srcZ*srcHeight+srcY)*srcPitch +
srcXInBytes);
```

For device pointers, the starting address is

```
↑ CUdeviceptr Start = srcDevice+(srcZ*srcHeight+srcY)*srcPitch+srcXInBytes;
```

For CUDA arrays, `srcXInBytes` must be evenly divisible by the array element size.

- ▶ `dstXInBytes`, `dstY` and `dstZ` specify the base address of the destination data for the copy.

For host pointers, the base address is

```
↑ void* dstStart = (void*)((char*)dstHost+(dstZ*dstHeight+dstY)*dstPitch +
dstXInBytes);
```

For device pointers, the starting address is

```
↑ CUdeviceptr dstStart = dstDevice+(dstZ*dstHeight+dstY)*dstPitch+dstXInBytes;
```


For CUDA arrays, `dstXInBytes` must be evenly divisible by the array element size.

- ▶ `WidthInBytes`, `Height` and `Depth` specify the width (in bytes), height and depth of the 3D copy being performed.
- ▶ If specified, `srcPitch` must be greater than or equal to `WidthInBytes + srcXInBytes`, and `dstPitch` must be greater than or equal to `WidthInBytes + dstXInBytes`.

- ▶ If specified, srcHeight must be greater than or equal to Height + srcY, and dstHeight must be greater than or equal to Height + dstY.

[cuMemcpy3DAsync\(\)](#) returns an error if any pitch is greater than the maximum allowed (CU_DEVICE_ATTRIBUTE_MAX_PITCH).

The srcLOD and dstLOD members of the CUDA_MEMCPY3D structure must be set to 0.



Note:

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ This function exhibits [asynchronous](#) behavior for most use cases.
- ▶ This function uses standard [default stream](#) semantics.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#), [cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#), [cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#), [cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#), [cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#), [cuMemFreeHost](#), [cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#), [cuMemsetD2D8](#), [cuMemsetD2D8Async](#), [cuMemsetD2D16](#), [cuMemsetD2D16Async](#), [cuMemsetD2D32](#), [cuMemsetD2D32Async](#), [cuMemsetD8](#), [cuMemsetD8Async](#), [cuMemsetD16](#), [cuMemsetD16Async](#), [cuMemsetD32](#), [cuMemsetD32Async](#), [cudaMemcpy3DAsync](#)

CUresult cuMemcpy3DPeer (const CUDA_MEMCPY3D_PEER *pCopy)

Copies memory between contexts.

Parameters

pCopy

- Parameters for the memory copy

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Perform a 3D memory copy according to the parameters specified in pCopy. See the definition of the CUDA_MEMCPY3D_PEER structure for documentation of its parameters.

**Note:**

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ This function exhibits [synchronous](#) behavior for most use cases.

See also:

[cuMemcpyDtoD](#), [cuMemcpyPeer](#), [cuMemcpyDtoDAsync](#), [cuMemcpyPeerAsync](#),
[cuMemcpy3DPeerAsync](#), [cudaMemcpy3DPeer](#)

CUresult cuMemcpy3DPeerAsync (const CUDA_MEMCPY3D_PEER *pCopy, CUstream hStream)

Copies memory between contexts asynchronously.

Parameters

pCopy

- Parameters for the memory copy

hStream

- Stream identifier

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Perform a 3D memory copy according to the parameters specified in `pCopy`. See the definition of the `CUDA_MEMCPY3D_PEER` structure for documentation of its parameters.

**Note:**

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ This function exhibits [asynchronous](#) behavior for most use cases.
- ▶ This function uses standard [default stream](#) semantics.

See also:

[cuMemcpyDtoD](#), [cuMemcpyPeer](#), [cuMemcpyDtoDAsync](#), [cuMemcpyPeerAsync](#),
[cuMemcpy3DPeerAsync](#), [cudaMemcpy3DPeerAsync](#)

CUresult cuMemcpyAsync (CUdeviceptr dst, CUdeviceptr src, size_t ByteCount, CUstream hStream)

Copies memory asynchronously.

Parameters

dst

- Destination unified virtual address space pointer

src

- Source unified virtual address space pointer

ByteCount

- Size of memory copy in bytes

hStream

- Stream identifier

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_HANDLE](#)

Description

Copies data between two pointers. `dst` and `src` are base pointers of the destination and source, respectively. `ByteCount` specifies the number of bytes to copy. Note that this function infers the type of the transfer (host to host, host to device, device to device, or device to host) from the pointer values. This function is only allowed in contexts which support unified addressing.

**Note:**

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ This function exhibits [asynchronous](#) behavior for most use cases.
- ▶ This function uses standard [default stream](#) semantics.
- ▶ Memory regions requested must be either entirely registered with CUDA, or in the case of host pageable transfers, not registered at all. Memory regions spanning over allocations that are both registered and not registered with CUDA are not supported and will return `CUDA_ERROR_INVALID_VALUE`.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#),
[cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#),
[cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#),
[cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#),
[cuMemcpyDtoD](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#), [cuMemcpyHtoA](#),
[cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#), [cuMemFreeHost](#),
[cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#),
[cuMemsetD2D8](#), [cuMemsetD2D8Async](#), [cuMemsetD2D16](#), [cuMemsetD2D16Async](#),
[cuMemsetD2D32](#), [cuMemsetD2D32Async](#), [cuMemsetD8](#), [cuMemsetD8Async](#), [cuMemsetD16](#),
[cuMemsetD16Async](#), [cuMemsetD32](#), [cuMemsetD32Async](#), [cudaMemcpyAsync](#),
[cudaMemcpyToSymbolAsync](#), [cudaMemcpyFromSymbolAsync](#)

CUresult cuMemcpyAtoA (CUarray dstArray, size_t dstOffset, CUarray srcArray, size_t srcOffset, size_t ByteCount)

Copies memory from Array to Array.

Parameters

dstArray

- Destination array

dstOffset

- Offset in bytes of destination array

srcArray

- Source array

srcOffset

- Offset in bytes of source array

ByteCount

- Size of memory copy in bytes

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Copies from one 1D CUDA array to another. `dstArray` and `srcArray` specify the handles of the destination and source CUDA arrays for the copy, respectively. `dstOffset` and `srcOffset` specify the destination and source offsets in bytes into the CUDA arrays. `ByteCount` is the number of bytes to be copied. The size of the elements in the CUDA arrays need not be the same format, but the elements must be the same size; and count must be evenly divisible by that size.

**Note:**

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ This function exhibits [synchronous](#) behavior for most use cases.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#),
[cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#),
[cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#),
[cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#), [cuMemcpyDtoD](#),
[cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#), [cuMemcpyHtoA](#),
[cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#), [cuMemFreeHost](#),
[cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#),
[cuMemsetD2D8](#), [cuMemsetD2D16](#), [cuMemsetD2D32](#), [cuMemsetD8](#), [cuMemsetD16](#),
[cuMemsetD32](#), [cudaMemcpyArrayToArray](#)

CUresult cuMemcpyAtoD (CUdeviceptr dstDevice, CUarray srcArray, size_t srcOffset, size_t ByteCount)

Copies memory from Array to Device.

Parameters

dstDevice

- Destination device pointer

srcArray

- Source array

srcOffset

- Offset in bytes of source array

ByteCount

- Size of memory copy in bytes

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Copies from one 1D CUDA array to device memory. `dstDevice` specifies the base pointer of the destination and must be naturally aligned with the CUDA array elements. `srcArray` and `srcOffset` specify the CUDA array handle and the offset in bytes into the array where the copy is to begin. `ByteCount` specifies the number of bytes to copy and must be evenly divisible by the array element size.

**Note:**

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ This function exhibits [synchronous](#) behavior for most use cases.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#), [cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#), [cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#), [cuMemcpyAtoA](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#), [cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#), [cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#), [cuMemFreeHost](#), [cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#), [cuMemsetD2D8](#), [cuMemsetD2D16](#), [cuMemsetD2D32](#), [cuMemsetD8](#), [cuMemsetD16](#), [cuMemsetD32](#), [cudaMemcpyFromArray](#)

CUresult cuMemcpyAtoH (void *dstHost, CUarray srcArray, size_t srcOffset, size_t ByteCount)

Copies memory from Array to Host.

Parameters

dstHost

- Destination device pointer

srcArray

- Source array

srcOffset

- Offset in bytes of source array

ByteCount

- Size of memory copy in bytes

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Copies from one 1D CUDA array to host memory. `dstHost` specifies the base pointer of the destination. `srcArray` and `srcOffset` specify the CUDA array handle and starting offset in bytes of the source data. `ByteCount` specifies the number of bytes to copy.

**Note:**

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ This function exhibits [synchronous](#) behavior for most use cases.
- ▶ Memory regions requested must be either entirely registered with CUDA, or in the case of host pageable transfers, not registered at all. Memory regions spanning over allocations that are both registered and not registered with CUDA are not supported and will return `CUDA_ERROR_INVALID_VALUE`.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#), [cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#), [cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#), [cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#), [cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#), [cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#), [cuMemFreeHost](#), [cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#), [cuMemsetD2D8](#), [cuMemsetD2D16](#), [cuMemsetD2D32](#), [cuMemsetD8](#), [cuMemsetD16](#), [cuMemsetD32](#), [cudaMemcpyFromArray](#)

**CUresult cuMemcpyAtoHAsync (void *dstHost,
CUarray srcArray, size_t srcOffset, size_t ByteCount,
CUstream hStream)**

Copies memory from Array to Host.

Parameters**dstHost**

- Destination pointer

srcArray

- Source array

srcOffset

- Offset in bytes of source array

ByteCount

- Size of memory copy in bytes

hStream

- Stream identifier

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_INVALID_HANDLE](#)

Description

Copies from one 1D CUDA array to host memory. `dstHost` specifies the base pointer of the destination. `srcArray` and `srcOffset` specify the CUDA array handle and starting offset in bytes of the source data. `ByteCount` specifies the number of bytes to copy.



Note:

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ This function exhibits [asynchronous](#) behavior for most use cases.
- ▶ This function uses standard [default stream](#) semantics.
- ▶ Memory regions requested must be either entirely registered with CUDA, or in the case of host pageable transfers, not registered at all. Memory regions spanning over allocations that are both registered and not registered with CUDA are not supported and will return `CUDA_ERROR_INVALID_VALUE`.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#),
[cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#),
[cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#),
[cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyDtoA](#), [cuMemcpyDtoD](#),
[cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#), [cuMemcpyHtoA](#),
[cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#), [cuMemFreeHost](#),
[cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#),
[cuMemsetD2D8](#), [cuMemsetD2D8Async](#), [cuMemsetD2D16](#), [cuMemsetD2D16Async](#),
[cuMemsetD2D32](#), [cuMemsetD2D32Async](#), [cuMemsetD8](#), [cuMemsetD8Async](#), [cuMemsetD16](#),
[cuMemsetD16Async](#), [cuMemsetD32](#), [cuMemsetD32Async](#), [cudaMemcpyFromArrayAsync](#)

CUresult cuMemcpyDtoA (CUarray dstArray, size_t dstOffset, CUdeviceptr srcDevice, size_t ByteCount)

Copies memory from Device to Array.

Parameters

dstArray

- Destination array

dstOffset

- Offset in bytes of destination array

srcDevice

- Source device pointer

ByteCount

- Size of memory copy in bytes

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Copies from device memory to a 1D CUDA array. `dstArray` and `dstOffset` specify the CUDA array handle and starting index of the destination data. `srcDevice` specifies the base pointer of the source. `ByteCount` specifies the number of bytes to copy.

**Note:**

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ This function exhibits [synchronous](#) behavior for most use cases.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#),
[cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#),
[cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#),
[cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoD](#),
[cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#), [cuMemcpyHtoA](#),
[cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#), [cuMemFreeHost](#),
[cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#),
[cuMemsetD2D8](#), [cuMemsetD2D16](#), [cuMemsetD2D32](#), [cuMemsetD8](#), [cuMemsetD16](#),
[cuMemsetD32](#), [cudaMemcpyToArray](#)

CUresult cuMemcpyDtoD (CUdeviceptr dstDevice, CUdeviceptr srcDevice, size_t ByteCount)

Copies memory from Device to Device.

Parameters**dstDevice**

- Destination device pointer

srcDevice

- Source device pointer

ByteCount

- Size of memory copy in bytes

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Copies from device memory to device memory. `dstDevice` and `srcDevice` are the base pointers of the destination and source, respectively. `ByteCount` specifies the number of bytes to copy.

**Note:**

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ This function exhibits [synchronous](#) behavior for most use cases.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#),
[cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#),
[cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#),
[cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#),
[cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#), [cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#),
[cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#), [cuMemFreeHost](#),
[cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#),
[cuMemsetD2D8](#), [cuMemsetD2D16](#), [cuMemsetD2D32](#), [cuMemsetD8](#), [cuMemsetD16](#),
[cuMemsetD32](#), [cudaMemcpy](#), [cudaMemcpyToSymbol](#), [cudaMemcpyFromSymbol](#)

CUresult cuMemcpyDtoDAsync (CUdeviceptr dstDevice, CUdeviceptr srcDevice, size_t ByteCount, CUstream hStream)

Copies memory from Device to Device.

Parameters**dstDevice**

- Destination device pointer

srcDevice

- Source device pointer

ByteCount

- Size of memory copy in bytes

hStream

- Stream identifier

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_INVALID_HANDLE](#)

Description

Copies from device memory to device memory. `dstDevice` and `srcDevice` are the base pointers of the destination and source, respectively. `ByteCount` specifies the number of bytes to copy.

**Note:**

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ This function exhibits [asynchronous](#) behavior for most use cases.
- ▶ This function uses standard [default stream](#) semantics.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#),
[cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#),
[cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#),
[cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#),
[cuMemcpyDtoD](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#), [cuMemcpyHtoA](#),
[cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#), [cuMemFreeHost](#),
[cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#),
[cuMemsetD2D8](#), [cuMemsetD2D8Async](#), [cuMemsetD2D16](#), [cuMemsetD2D16Async](#),
[cuMemsetD2D32](#), [cuMemsetD2D32Async](#), [cuMemsetD8](#), [cuMemsetD8Async](#), [cuMemsetD16](#),
[cuMemsetD16Async](#), [cuMemsetD32](#), [cuMemsetD32Async](#), [cudaMemcpyAsync](#),
[cudaMemcpyToSymbolAsync](#), [cudaMemcpyFromSymbolAsync](#)

CUresult cuMemcpyDtoH (void *dstHost, CUdeviceptr srcDevice, size_t ByteCount)

Copies memory from Device to Host.

Parameters

dstHost

- Destination host pointer

srcDevice

- Source device pointer

ByteCount


- Size of memory copy in bytes

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Copies from device to host memory. `dstHost` and `srcDevice` specify the base pointers of the destination and source, respectively. `ByteCount` specifies the number of bytes to copy.



Note:

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ This function exhibits [synchronous](#) behavior for most use cases.
- ▶ Memory regions requested must be either entirely registered with CUDA, or in the case of host pageable transfers, not registered at all. Memory regions spanning over allocations that are both registered and not registered with CUDA are not supported and will return `CUDA_ERROR_INVALID_VALUE`.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#), [cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#), [cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#), [cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#), [cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoHAsync](#), [cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#), [cuMemFreeHost](#), [cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#), [cuMemsetD2D8](#), [cuMemsetD2D16](#), [cuMemsetD2D32](#), [cuMemsetD8](#), [cuMemsetD16](#), [cuMemsetD32](#), [cudaMemcpy](#), [cudaMemcpyFromSymbol](#)

CUresult cuMemcpyDtoHAsync (void *dstHost, CUdeviceptr srcDevice, size_t ByteCount, CUstream hStream)

Copies memory from Device to Host.

Parameters

dstHost

- Destination host pointer

srcDevice

- Source device pointer

ByteCount

- Size of memory copy in bytes

hStream

- Stream identifier

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_HANDLE](#)

Description

Copies from device to host memory. `dstHost` and `srcDevice` specify the base pointers of the destination and source, respectively. `ByteCount` specifies the number of bytes to copy.



Note:

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ This function exhibits [asynchronous](#) behavior for most use cases.
- ▶ This function uses standard [default stream](#) semantics.
- ▶ Memory regions requested must be either entirely registered with CUDA, or in the case of host pageable transfers, not registered at all. Memory regions spanning over allocations that are both registered and not registered with CUDA are not supported and will return `CUDA_ERROR_INVALID_VALUE`.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#), [cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#), [cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#),

[cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#), [cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#), [cuMemFreeHost](#), [cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#), [cuMemsetD2D8](#), [cuMemsetD2D8Async](#), [cuMemsetD2D16](#), [cuMemsetD2D16Async](#), [cuMemsetD2D32](#), [cuMemsetD2D32Async](#), [cuMemsetD8](#), [cuMemsetD8Async](#), [cuMemsetD16](#), [cuMemsetD16Async](#), [cuMemsetD32](#), [cuMemsetD32Async](#), [cudaMemcpyAsync](#), [cudaMemcpyFromSymbolAsync](#)

CUresult cuMemcpyHtoA (CUarray dstArray, size_t dstOffset, const void *srcHost, size_t ByteCount)

Copies memory from Host to Array.

Parameters

dstArray

- Destination array

dstOffset

- Offset in bytes of destination array

srcHost

- Source host pointer

ByteCount

- Size of memory copy in bytes

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Copies from host memory to a 1D CUDA array. `dstArray` and `dstOffset` specify the CUDA array handle and starting offset in bytes of the destination data. `pSrc` specifies the base address of the source. `ByteCount` specifies the number of bytes to copy.



Note:

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ This function exhibits [synchronous](#) behavior for most use cases.
- ▶ Memory regions requested must be either entirely registered with CUDA, or in the case of host pageable transfers, not registered at all. Memory regions spanning over allocations that are both registered and not registered with CUDA are not supported and will return `CUDA_ERROR_INVALID_VALUE`.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#), [cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#), [cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#), [cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#), [cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#), [cuMemFreeHost](#), [cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#), [cuMemsetD2D8](#), [cuMemsetD2D16](#), [cuMemsetD2D32](#), [cuMemsetD8](#), [cuMemsetD16](#), [cuMemsetD32](#), [cudaMemcpyToArray](#)

CUresult cuMemcpyHtoAAsync (CUarray dstArray, size_t dstOffset, const void *srcHost, size_t ByteCount, CUstream hStream)

Copies memory from Host to Array.

Parameters

dstArray

- Destination array

dstOffset

- Offset in bytes of destination array

srcHost

- Source host pointer

ByteCount

- Size of memory copy in bytes

hStream

- Stream identifier

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_HANDLE](#)

Description

Copies from host memory to a 1D CUDA array. `dstArray` and `dstOffset` specify the CUDA array handle and starting offset in bytes of the destination data. `srcHost` specifies the base address of the source. `ByteCount` specifies the number of bytes to copy.

**Note:**

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ This function exhibits [asynchronous](#) behavior for most use cases.
- ▶ This function uses standard [default stream](#) semantics.
- ▶ Memory regions requested must be either entirely registered with CUDA, or in the case of host pageable transfers, not registered at all. Memory regions spanning over allocations that are both registered and not registered with CUDA are not supported and will return `CUDA_ERROR_INVALID_VALUE`.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#), [cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#), [cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#), [cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#), [cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#), [cuMemcpyHtoA](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#), [cuMemFreeHost](#), [cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#), [cuMemsetD2D8](#), [cuMemsetD2D8Async](#), [cuMemsetD2D16](#), [cuMemsetD2D16Async](#), [cuMemsetD2D32](#), [cuMemsetD2D32Async](#), [cuMemsetD8](#), [cuMemsetD8Async](#), [cuMemsetD16](#), [cuMemsetD16Async](#), [cuMemsetD32](#), [cuMemsetD32Async](#), [cudaMemcpyToArrayAsync](#)

CUresult cuMemcpyHtoD (CUdeviceptr dstDevice, const void *srcHost, size_t ByteCount)

Copies memory from Host to Device.

Parameters

dstDevice

- Destination device pointer

srcHost

- Source host pointer

ByteCount

- Size of memory copy in bytes

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Copies from host memory to device memory. `dstDevice` and `srcHost` are the base addresses of the destination and source, respectively. `ByteCount` specifies the number of bytes to copy.



Note:

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ This function exhibits [synchronous](#) behavior for most use cases.
- ▶ Memory regions requested must be either entirely registered with CUDA, or in the case of host pageable transfers, not registered at all. Memory regions spanning over allocations that are both registered and not registered with CUDA are not supported and will return `CUDA_ERROR_INVALID_VALUE`.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#),
[cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#),
[cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#),
[cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#),
[cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#),
[cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#), [cuMemFreeHost](#),
[cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#),
[cuMemsetD2D8](#), [cuMemsetD2D16](#), [cuMemsetD2D32](#), [cuMemsetD8](#), [cuMemsetD16](#),
[cuMemsetD32](#), [cudaMemcpy](#), [cudaMemcpyToSymbol](#)

CUresult cuMemcpyHtoDAsync (CUdeviceptr dstDevice, const void *srcHost, size_t ByteCount, CUstream hStream)

Copies memory from Host to Device.

Parameters

dstDevice

- Destination device pointer

srcHost

- Source host pointer

ByteCount

- Size of memory copy in bytes

hStream

- Stream identifier

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_INVALID_HANDLE](#)

Description

Copies from host memory to device memory. `dstDevice` and `srcHost` are the base addresses of the destination and source, respectively. `ByteCount` specifies the number of bytes to copy.

**Note:**

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ This function exhibits [asynchronous](#) behavior for most use cases.
- ▶ This function uses standard [default stream](#) semantics.
- ▶ Memory regions requested must be either entirely registered with CUDA, or in the case of host pageable transfers, not registered at all. Memory regions spanning over allocations that are both registered and not registered with CUDA are not supported and will return `CUDA_ERROR_INVALID_VALUE`.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#),
[cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#),
[cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#),
[cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#),
[cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#),
[cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemFree](#), [cuMemFreeHost](#),
[cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#),
[cuMemsetD2D8](#), [cuMemsetD2D8Async](#), [cuMemsetD2D16](#), [cuMemsetD2D16Async](#),
[cuMemsetD2D32](#), [cuMemsetD2D32Async](#), [cuMemsetD8](#), [cuMemsetD8Async](#), [cuMemsetD16](#),
[cuMemsetD16Async](#), [cuMemsetD32](#), [cuMemsetD32Async](#), [cudaMemcpyAsync](#),
[cudaMemcpyToSymbolAsync](#)

CUresult cuMemcpyPeer (CUdeviceptr dstDevice, CUcontext dstContext, CUdeviceptr srcDevice, CUcontext srcContext, size_t ByteCount)

Copies device memory between two contexts.

Parameters

dstDevice

- Destination device pointer

dstContext

- Destination context

srcDevice

- Source device pointer

srcContext

- Source context

ByteCount

- Size of memory copy in bytes

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Copies from device memory in one context to device memory in another context. `dstDevice` is the base device pointer of the destination memory and `dstContext` is the destination context. `srcDevice` is the base device pointer of the source memory and `srcContext` is the source pointer. `ByteCount` specifies the number of bytes to copy.



Note:

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ This function exhibits [synchronous](#) behavior for most use cases.

See also:

[cuMemcpyDtoD](#), [cuMemcpy3DPeer](#), [cuMemcpyDtoDAsync](#), [cuMemcpyPeerAsync](#), [cuMemcpy3DPeerAsync](#), [cudaMemcpyPeer](#)

CUresult cuMemcpyPeerAsync (CUdeviceptr dstDevice, CUcontext dstContext, CUdeviceptr srcDevice, CUcontext srcContext, size_t ByteCount, CUstream hStream)

Copies device memory between two contexts asynchronously.

Parameters

dstDevice

- Destination device pointer

dstContext

- Destination context

srcDevice

- Source device pointer

srcContext

- Source context

ByteCount

- Size of memory copy in bytes

hStream

- Stream identifier

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_HANDLE](#)

Description

Copies from device memory in one context to device memory in another context. `dstDevice` is the base device pointer of the destination memory and `dstContext` is the destination context. `srcDevice` is the base device pointer of the source memory and `srcContext` is the source pointer. `ByteCount` specifies the number of bytes to copy.



Note:

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ This function exhibits [asynchronous](#) behavior for most use cases.
- ▶ This function uses standard [default stream](#) semantics.

See also:

[cuMemcpyDtoD](#), [cuMemcpyPeer](#), [cuMemcpy3DPeer](#), [cuMemcpyDtoDAsync](#),
[cuMemcpy3DPeerAsync](#), [cudaMemcpyPeerAsync](#)

CUresult cuMemFree (CUdeviceptr dptr)

Frees device memory.

Parameters

dptr

- Pointer to memory to free

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Frees the memory space pointed to by `dptr`, which must have been returned by a previous call to [cuMemAlloc\(\)](#) or [cuMemAllocPitch\(\)](#).



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#),
[cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#),
[cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#),
[cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#),
[cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#),
[cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#),
[cuMemFreeHost](#), [cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#),
[cuMemHostGetDevicePointer](#), [cuMemsetD2D8](#), [cuMemsetD2D16](#), [cuMemsetD2D32](#),
[cuMemsetD8](#), [cuMemsetD16](#), [cuMemsetD32](#), [cudaFree](#)

CUresult cuMemFreeHost (void *p)

Frees page-locked host memory.

Parameters

p

- Pointer to memory to free

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Frees the memory space pointed to by `p`, which must have been returned by a previous call to [cuMemAllocHost\(\)](#).



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#),
[cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#),
[cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#),
[cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#),
[cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#),
[cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#),
[cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#),
[cuMemsetD2D8](#), [cuMemsetD2D16](#), [cuMemsetD2D32](#), [cuMemsetD8](#), [cuMemsetD16](#),
[cuMemsetD32](#), [cudaFreeHost](#)

CUresult cuMemGetAddressRange (CUdeviceptr *pbase, size_t *psize, CUdeviceptr dptr)

Get information on memory allocations.

Parameters

pbase

- Returned base address

psize

- Returned size of device memory allocation

dptr

- Device pointer to query

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_NOT_FOUND](#),
[CUDA_ERROR_INVALID_VALUE](#)

Description

Returns the base address in `*pbase` and size in `*psize` of the allocation by [cuMemAlloc\(\)](#) or [cuMemAllocPitch\(\)](#) that contains the input pointer `dptr`. Both parameters `pbase` and `psize` are optional. If one of them is NULL, it is ignored.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#), [cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#), [cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#), [cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#), [cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#), [cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#), [cuMemFreeHost](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#), [cuMemsetD2D8](#), [cuMemsetD2D16](#), [cuMemsetD2D32](#), [cuMemsetD8](#), [cuMemsetD16](#), [cuMemsetD32](#)

CUresult cuMemGetInfo (size_t *free, size_t *total)

Gets free and total memory.

Parameters

free

- Returned free memory in bytes

total

- Returned total memory in bytes

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Returns in `*free` and `*total` respectively, the free and total amount of memory available for allocation by the CUDA context, in bytes.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#), [cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#), [cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#), [cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#), [cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#), [cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#), [cuMemFreeHost](#), [cuMemGetAddressRange](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#), [cuMemsetD2D8](#), [cuMemsetD2D16](#), [cuMemsetD2D32](#), [cuMemsetD8](#), [cuMemsetD16](#), [cuMemsetD32](#), [cudaMemGetInfo](#)

CUresult cuMemHostAlloc (void **pp, size_t bytesize, unsigned int Flags)

Allocates page-locked host memory.

Parameters

pp

- Returned host pointer to page-locked memory

bytesize

- Requested allocation size in bytes

Flags

- Flags for allocation request

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_OUT_OF_MEMORY](#)

Description

Allocates `bytesize` bytes of host memory that is page-locked and accessible to the device. The driver tracks the virtual memory ranges allocated with this function and automatically accelerates calls to functions such as [cuMemcpyHtoD\(\)](#). Since the memory can be accessed directly by the device, it can be read or written with much higher bandwidth than pageable memory obtained with functions such as `malloc()`. Allocating excessive amounts of pinned memory may degrade system performance, since it reduces the amount of memory available to the system for paging. As a result, this function is best used sparingly to allocate staging areas for data exchange between host and device.

The `Flags` parameter enables different options to be specified that affect the allocation, as follows.

- ▶ [CU_MEMHOSTALLOC_PORTABLE](#): The memory returned by this call will be considered as pinned memory by all CUDA contexts, not just the one that performed the allocation.
- ▶ [CU_MEMHOSTALLOC_DEVICEMAP](#): Maps the allocation into the CUDA address space. The device pointer to the memory may be obtained by calling [cuMemHostGetDevicePointer\(\)](#).
- ▶ [CU_MEMHOSTALLOC_WRITECOMBINED](#): Allocates the memory as write-combined (WC). WC memory can be transferred across the PCI Express bus more quickly on some system configurations, but cannot be read efficiently by most CPUs. WC memory is a good option for buffers that will be written by the CPU and read by the GPU via mapped pinned memory or host->device transfers.

All of these flags are orthogonal to one another: a developer may allocate memory that is portable, mapped and/or write-combined with no restrictions.

The [CU_MEMHOSTALLOC_DEVICEMAP](#) flag may be specified on CUDA contexts for devices that do not support mapped pinned memory. The failure is deferred to [cuMemHostGetDevicePointer\(\)](#) because the memory may be mapped into other CUDA contexts via the [CU_MEMHOSTALLOC_PORTABLE](#) flag.

The memory allocated by this function must be freed with [cuMemFreeHost\(\)](#).

Note all host memory allocated using [cuMemHostAlloc\(\)](#) will automatically be immediately accessible to all contexts on all devices which support unified addressing (as may be queried using [CU_DEVICE_ATTRIBUTE_UNIFIED_ADDRESSING](#)). Unless the flag [CU_MEMHOSTALLOC_WRITECOMBINED](#) is specified, the device pointer that may be used to access this host memory from those contexts is always equal to the returned host pointer `*pp`. If the flag [CU_MEMHOSTALLOC_WRITECOMBINED](#) is specified, then the function [cuMemHostGetDevicePointer\(\)](#) must be used to query the device pointer, even if the context supports unified addressing. See [Unified Addressing](#) for additional details.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#),
[cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#),
[cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#),
[cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#),
[cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#),
[cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#),
[cuMemFreeHost](#), [cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostGetDevicePointer](#),

[cuMemsetD2D8](#), [cuMemsetD2D16](#), [cuMemsetD2D32](#), [cuMemsetD8](#), [cuMemsetD16](#),
[cuMemsetD32](#), [cudaHostAlloc](#)

CUresult cuMemHostGetDevicePointer (CUdeviceptr *pdptr, void *p, unsigned int Flags)

Passes back device pointer of mapped pinned memory.

Parameters

pdptr

- Returned device pointer

p

- Host pointer

Flags

- Options (must be 0)

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Passes back the device pointer `pdptr` corresponding to the mapped, pinned host buffer `p` allocated by [cuMemHostAlloc](#).

[cuMemHostGetDevicePointer\(\)](#) will fail if the [CU_MEMHOSTALLOC_DEVICEMAP](#) flag was not specified at the time the memory was allocated, or if the function is called on a GPU that does not support mapped pinned memory.

For devices that have a non-zero value for the device attribute [CU_DEVICE_ATTRIBUTE_CAN_USE_HOST_POINTER_FOR_REGISTERED_MEM](#), the memory can also be accessed from the device using the host pointer `p`. The device pointer returned by [cuMemHostGetDevicePointer\(\)](#) may or may not match the original host pointer `p` and depends on the devices visible to the application. If all devices visible to the application have a non-zero value for the device attribute, the device pointer returned by [cuMemHostGetDevicePointer\(\)](#) will match the original pointer `p`. If any device visible to the application has a zero value for the device attribute, the device pointer returned by [cuMemHostGetDevicePointer\(\)](#) will not match the original host pointer `p`, but it will be suitable for use on all devices provided Unified Virtual Addressing is enabled. In such systems, it is valid to access the memory using either pointer on devices that have a non-zero value for the device attribute. Note however that such devices should access the memory using only of the two pointers and not both.

`Flags` provides for future releases. For now, it must be set to 0.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#),
[cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#),
[cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#),
[cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#),
[cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#),
[cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#),
[cuMemFree](#), [cuMemFreeHost](#), [cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#),
[cuMemsetD2D8](#), [cuMemsetD2D16](#), [cuMemsetD2D32](#), [cuMemsetD8](#), [cuMemsetD16](#),
[cuMemsetD32](#), [cudaHostGetDevicePointer](#)

CUresult cuMemHostGetFlags (unsigned int *pFlags, void *p)

Passes back flags that were used for a pinned allocation.

Parameters

pFlags

- Returned flags word

p

- Host pointer

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Passes back the flags `pFlags` that were specified when allocating the pinned host buffer `p` allocated by [cuMemHostAlloc](#).

[cuMemHostGetFlags\(\)](#) will fail if the pointer does not reside in an allocation performed by [cuMemAllocHost\(\)](#) or [cuMemHostAlloc\(\)](#).

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuMemAllocHost](#), [cuMemHostAlloc](#), [cudaHostGetFlags](#)

CUresult cuMemHostRegister (void *p, size_t bytesize, unsigned int Flags)

Registers an existing host memory range for use by CUDA.

Parameters

p

- Host pointer to memory to page-lock

bytesize

- Size in bytes of the address range to page-lock

Flags

- Flags for allocation request

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_OUT_OF_MEMORY](#), [CUDA_ERROR_HOST_MEMORY_ALREADY_REGISTERED](#), [CUDA_ERROR_NOT_PERMITTED](#), [CUDA_ERROR_NOT_SUPPORTED](#)

Description

Page-locks the memory range specified by `p` and `bytesize` and maps it for the device(s) as specified by `Flags`. This memory range also is added to the same tracking mechanism as [cuMemHostAlloc](#) to automatically accelerate calls to functions such as [cuMemcpyHtoD\(\)](#). Since the memory can be accessed directly by the device, it can be read or written with much higher bandwidth than pageable memory that has not been registered. Page-locking excessive amounts of memory may degrade system performance, since it reduces the amount of memory available to the system for paging. As a result, this function is best used sparingly to register staging areas for data exchange between host and device.

This function has limited support on Mac OS X. OS 10.7 or higher is required.

The `Flags` parameter enables different options to be specified that affect the allocation, as follows.

- ▶ [CU_MEMHOSTREGISTER_PORTABLE](#): The memory returned by this call will be considered as pinned memory by all CUDA contexts, not just the one that performed the allocation.
- ▶ [CU_MEMHOSTREGISTER_DEVICEMAP](#): Maps the allocation into the CUDA address space. The device pointer to the memory may be obtained by calling [cuMemHostGetDevicePointer\(\)](#).

- ▶ [CU_MEMHOSTREGISTER_IOMEMORY](#): The pointer is treated as pointing to some I/O memory space, e.g. the PCI Express resource of a 3rd party device.
- ▶ [CU_MEMHOSTREGISTER_READ_ONLY](#): The pointer is treated as pointing to memory that is considered read-only by the device. On platforms without `CU_DEVICE_ATTRIBUTE_PAGEABLE_MEMORY_ACCESS_USES_HOST_PAGE_TABLES`, this flag is required in order to register memory mapped to the CPU as read-only. Support for the use of this flag can be queried from the device attribute `CU_DEVICE_ATTRIBUTE_READ_ONLY_HOST_REGISTER_SUPPORTED`. Using this flag with a current context associated with a device that does not have this attribute set will cause `cuMemHostRegister` to error with `CUDA_ERROR_NOT_SUPPORTED`.

All of these flags are orthogonal to one another: a developer may page-lock memory that is portable or mapped with no restrictions.

The [CU_MEMHOSTREGISTER_DEVICEMAP](#) flag may be specified on CUDA contexts for devices that do not support mapped pinned memory. The failure is deferred to `cuMemHostGetDevicePointer()` because the memory may be mapped into other CUDA contexts via the [CU_MEMHOSTREGISTER_PORTABLE](#) flag.

For devices that have a non-zero value for the device attribute [CU_DEVICE_ATTRIBUTE_CAN_USE_HOST_POINTER_FOR_REGISTERED_MEM](#), the memory can also be accessed from the device using the host pointer `p`. The device pointer returned by `cuMemHostGetDevicePointer()` may or may not match the original host pointer `ptr` and depends on the devices visible to the application. If all devices visible to the application have a non-zero value for the device attribute, the device pointer returned by `cuMemHostGetDevicePointer()` will match the original pointer `ptr`. If any device visible to the application has a zero value for the device attribute, the device pointer returned by `cuMemHostGetDevicePointer()` will not match the original host pointer `ptr`, but it will be suitable for use on all devices provided Unified Virtual Addressing is enabled. In such systems, it is valid to access the memory using either pointer on devices that have a non-zero value for the device attribute. Note however that such devices should access the memory using only of the two pointers and not both.

The memory page-locked by this function must be unregistered with `cuMemHostUnregister()`.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuMemHostUnregister](#), [cuMemHostGetFlags](#), [cuMemHostGetDevicePointer](#), [cudaHostRegister](#)

CUresult cuMemHostUnregister (void *p)

Unregisters a memory range that was registered with cuMemHostRegister.

Parameters

p

- Host pointer to memory to unregister

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_OUT_OF_MEMORY](#), [CUDA_ERROR_HOST_MEMORY_NOT_REGISTERED](#),

Description

Unmaps the memory range whose base address is specified by p, and makes it pageable again.

The base address must be the same one specified to [cuMemHostRegister\(\)](#).



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuMemHostRegister](#), [cudaHostUnregister](#)

CUresult cuMemsetD16 (CUdeviceptr dstDevice, unsigned short us, size_t N)

Initializes device memory.

Parameters

dstDevice

- Destination device pointer

us

- Value to set

N

- Number of elements

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Sets the memory range of N 16-bit values to the specified value `us`. The `dstDevice` pointer must be two byte aligned.



Note:

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ See also [memset synchronization details](#).

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#),
[cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#),
[cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#),
[cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#),
[cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#),
[cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#),
[cuMemFree](#), [cuMemFreeHost](#), [cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#),
[cuMemHostGetDevicePointer](#), [cuMemsetD2D8](#), [cuMemsetD2D8Async](#), [cuMemsetD2D16](#),
[cuMemsetD2D16Async](#), [cuMemsetD2D32](#), [cuMemsetD2D32Async](#), [cuMemsetD8](#),
[cuMemsetD8Async](#), [cuMemsetD16Async](#), [cuMemsetD32](#), [cuMemsetD32Async](#), [cudaMemset](#)

CUresult cuMemsetD16Async (CUdeviceptr dstDevice, unsigned short us, size_t N, CUstream hStream)

Sets device memory.

Parameters

dstDevice

- Destination device pointer

us

- Value to set

N

- Number of elements

hStream

- Stream identifier

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Sets the memory range of N 16-bit values to the specified value `us`. The `dstDevice` pointer must be two byte aligned.



Note:

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ See also [memset synchronization details](#).
- ▶ This function uses standard [default stream](#) semantics.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#),
[cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#),
[cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#),
[cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#),
[cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#),
[cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#),
[cuMemFree](#), [cuMemFreeHost](#), [cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#),
[cuMemHostGetDevicePointer](#), [cuMemsetD2D8](#), [cuMemsetD2D8Async](#), [cuMemsetD2D16](#),
[cuMemsetD2D16Async](#), [cuMemsetD2D32](#), [cuMemsetD2D32Async](#), [cuMemsetD8](#),
[cuMemsetD8Async](#), [cuMemsetD16](#), [cuMemsetD32](#), [cuMemsetD32Async](#), [cudaMemsetAsync](#)

CUresult cuMemsetD2D16 (CUdeviceptr dstDevice, size_t dstPitch, unsigned short us, size_t Width, size_t Height)

Initializes device memory.

Parameters

dstDevice

- Destination device pointer

dstPitch

- Pitch of destination device pointer(Unused if `Height` is 1)

us

- Value to set

Width

- Width of row

Height

- Number of rows

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Sets the 2D memory range of `width` 16-bit values to the specified value `us`. `Height` specifies the number of rows to set, and `dstPitch` specifies the number of bytes between each row. The `dstDevice` pointer and `dstPitch` offset must be two byte aligned. This function performs fastest when the pitch is one that has been passed back by [cuMemAllocPitch\(\)](#).

**Note:**

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ See also [memset synchronization details](#).

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#),
[cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#),
[cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#),
[cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#),
[cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#),
[cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#),
[cuMemFree](#), [cuMemFreeHost](#), [cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#),
[cuMemHostGetDevicePointer](#), [cuMemsetD2D8](#), [cuMemsetD2D8Async](#), [cuMemsetD2D16Async](#),
[cuMemsetD2D32](#), [cuMemsetD2D32Async](#), [cuMemsetD8](#), [cuMemsetD8Async](#), [cuMemsetD16](#),
[cuMemsetD16Async](#), [cuMemsetD32](#), [cuMemsetD32Async](#), [cudaMemset2D](#)

CUresult cuMemsetD2D16Async (CUdeviceptr dstDevice, size_t dstPitch, unsigned short us, size_t Width, size_t Height, CUstream hStream)

Sets device memory.

Parameters

dstDevice

- Destination device pointer

dstPitch

- Pitch of destination device pointer(Unused if Height is 1)

us

- Value to set

Width

- Width of row

Height

- Number of rows

hStream

- Stream identifier

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Sets the 2D memory range of width 16-bit values to the specified value `us`. `Height` specifies the number of rows to set, and `dstPitch` specifies the number of bytes between each row. The `dstDevice` pointer and `dstPitch` offset must be two byte aligned. This function performs fastest when the pitch is one that has been passed back by [cuMemAllocPitch\(\)](#).



Note:

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ See also [memset synchronization details](#).
- ▶ This function uses standard [default stream](#) semantics.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#), [cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#), [cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#),

[cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#), [cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#), [cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#), [cuMemFreeHost](#), [cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#), [cuMemsetD2D8](#), [cuMemsetD2D8Async](#), [cuMemsetD2D16](#), [cuMemsetD2D32](#), [cuMemsetD2D32Async](#), [cuMemsetD8](#), [cuMemsetD8Async](#), [cuMemsetD16](#), [cuMemsetD16Async](#), [cuMemsetD32](#), [cuMemsetD32Async](#), [cudaMemset2DAsync](#)

CUresult cuMemsetD2D32 (CUdeviceptr dstDevice, size_t dstPitch, unsigned int ui, size_t Width, size_t Height)

Initializes device memory.

Parameters

dstDevice

- Destination device pointer

dstPitch

- Pitch of destination device pointer(Unused if Height is 1)

ui

- Value to set

Width

- Width of row

Height

- Number of rows

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Sets the 2D memory range of width 32-bit values to the specified value `ui`. `Height` specifies the number of rows to set, and `dstPitch` specifies the number of bytes between each row. The `dstDevice` pointer and `dstPitch` offset must be four byte aligned. This function performs fastest when the pitch is one that has been passed back by [cuMemAllocPitch\(\)](#).



Note:

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ See also [memset synchronization details](#).

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#),
[cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#),
[cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#),
[cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#),
[cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#),
[cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#),
[cuMemFree](#), [cuMemFreeHost](#), [cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#),
[cuMemHostGetDevicePointer](#), [cuMemsetD2D8](#), [cuMemsetD2D8Async](#), [cuMemsetD2D16](#),
[cuMemsetD2D16Async](#), [cuMemsetD2D32Async](#), [cuMemsetD8](#), [cuMemsetD8Async](#),
[cuMemsetD16](#), [cuMemsetD16Async](#), [cuMemsetD32](#), [cuMemsetD32Async](#), [cudaMemset2D](#)

CUresult cuMemsetD2D32Async (CUdeviceptr dstDevice, size_t dstPitch, unsigned int ui, size_t Width, size_t Height, CUstream hStream)

Sets device memory.

Parameters

dstDevice

- Destination device pointer

dstPitch

- Pitch of destination device pointer(Unused if Height is 1)

ui

- Value to set

Width

- Width of row

Height

- Number of rows

hStream

- Stream identifier

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Sets the 2D memory range of width 32-bit values to the specified value `ui`. `Height` specifies the number of rows to set, and `dstPitch` specifies the number of bytes between each row. The `dstDevice` pointer and `dstPitch` offset must be four byte aligned. This function performs fastest when the pitch is one that has been passed back by [cuMemAllocPitch\(\)](#).

**Note:**

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ See also [memset synchronization details](#).
- ▶ This function uses standard [default stream](#) semantics.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#),
[cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#),
[cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#),
[cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#),
[cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#),
[cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#),
[cuMemFree](#), [cuMemFreeHost](#), [cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#),
[cuMemHostGetDevicePointer](#), [cuMemsetD2D8](#), [cuMemsetD2D8Async](#), [cuMemsetD2D16](#),
[cuMemsetD2D16Async](#), [cuMemsetD2D32](#), [cuMemsetD8](#), [cuMemsetD8Async](#), [cuMemsetD16](#),
[cuMemsetD16Async](#), [cuMemsetD32](#), [cuMemsetD32Async](#), [cudaMemset2DAsync](#)

CUresult cuMemsetD2D8 (CUdeviceptr dstDevice, size_t dstPitch, unsigned char uc, size_t Width, size_t Height)

Initializes device memory.

Parameters

dstDevice

- Destination device pointer

dstPitch

- Pitch of destination device pointer (Unused if Height is 1)

uc

- Value to set

Width

- Width of row

Height

- Number of rows

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Sets the 2D memory range of `width` 8-bit values to the specified value `uc`. `Height` specifies the number of rows to set, and `dstPitch` specifies the number of bytes between each row. This function performs fastest when the pitch is one that has been passed back by [cuMemAllocPitch\(\)](#).



Note:

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ See also [memset synchronization details](#).

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#), [cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#), [cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#), [cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#), [cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#), [cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#), [cuMemFreeHost](#), [cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#), [cuMemsetD2D8Async](#), [cuMemsetD2D16](#), [cuMemsetD2D16Async](#), [cuMemsetD2D32](#), [cuMemsetD2D32Async](#), [cuMemsetD8](#), [cuMemsetD8Async](#), [cuMemsetD16](#), [cuMemsetD16Async](#), [cuMemsetD32](#), [cuMemsetD32Async](#), [cudaMemset2D](#)

CUresult cuMemsetD2D8Async (CUdeviceptr dstDevice, size_t dstPitch, unsigned char uc, size_t Width, size_t Height, CUstream hStream)

Sets device memory.

Parameters

dstDevice

- Destination device pointer

dstPitch

- Pitch of destination device pointer(Unused if `Height` is 1)

uc

- Value to set

Width

- Width of row

Height

- Number of rows

hStream

- Stream identifier

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Sets the 2D memory range of `width` 8-bit values to the specified value `uc`. `Height` specifies the number of rows to set, and `dstPitch` specifies the number of bytes between each row. This function performs fastest when the pitch is one that has been passed back by [cuMemAllocPitch\(\)](#).

**Note:**

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ See also [memset synchronization details](#).
- ▶ This function uses standard [default stream](#) semantics.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#),
[cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#),
[cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#),
[cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#),
[cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#),
[cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#),
[cuMemFree](#), [cuMemFreeHost](#), [cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#),
[cuMemHostGetDevicePointer](#), [cuMemsetD2D8](#), [cuMemsetD2D16](#), [cuMemsetD2D16Async](#),
[cuMemsetD2D32](#), [cuMemsetD2D32Async](#), [cuMemsetD8](#), [cuMemsetD8Async](#), [cuMemsetD16](#),
[cuMemsetD16Async](#), [cuMemsetD32](#), [cuMemsetD32Async](#), [cudaMemset2DAsync](#)

CUresult cuMemsetD32 (CUdeviceptr dstDevice, unsigned int ui, size_t N)

Initializes device memory.

Parameters**dstDevice**

- Destination device pointer

ui

- Value to set

N

- Number of elements

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Sets the memory range of N 32-bit values to the specified value ui . The `dstDevice` pointer must be four byte aligned.

**Note:**

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ See also [memset synchronization details](#).

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#),
[cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#),
[cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#),
[cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#),
[cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#),
[cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#),
[cuMemFree](#), [cuMemFreeHost](#), [cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#),
[cuMemHostGetDevicePointer](#), [cuMemsetD2D8](#), [cuMemsetD2D8Async](#), [cuMemsetD2D16](#),
[cuMemsetD2D16Async](#), [cuMemsetD2D32](#), [cuMemsetD2D32Async](#), [cuMemsetD8](#),
[cuMemsetD8Async](#), [cuMemsetD16](#), [cuMemsetD16Async](#), [cuMemsetD32Async](#), [cudaMemset](#)

CUresult cuMemsetD32Async (CUdeviceptr dstDevice, unsigned int ui, size_t N, CUstream hStream)

Sets device memory.

Parameters**dstDevice**

- Destination device pointer

ui

- Value to set

N

- Number of elements

hStream

- Stream identifier

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Sets the memory range of `N` 32-bit values to the specified value `ui`. The `dstDevice` pointer must be four byte aligned.

**Note:**

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ See also [memset synchronization details](#).
- ▶ This function uses standard [default stream](#) semantics.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#),
[cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#),
[cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#),
[cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#),
[cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#),
[cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#),
[cuMemFree](#), [cuMemFreeHost](#), [cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#),
[cuMemHostGetDevicePointer](#), [cuMemsetD2D8](#), [cuMemsetD2D8Async](#), [cuMemsetD2D16](#),
[cuMemsetD2D16Async](#), [cuMemsetD2D32](#), [cuMemsetD2D32Async](#), [cuMemsetD8](#),
[cuMemsetD8Async](#), [cuMemsetD16](#), [cuMemsetD16Async](#), [cuMemsetD32](#), [cudaMemsetAsync](#)

CUresult cuMemsetD8 (CUdeviceptr dstDevice, unsigned char uc, size_t N)

Initializes device memory.

Parameters**dstDevice**

- Destination device pointer

uc

- Value to set

N

- Number of elements

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Sets the memory range of N 8-bit values to the specified value uc.

**Note:**

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ See also [memset synchronization details](#).

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#),
[cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#),
[cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#),
[cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#),
[cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#),
[cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#),
[cuMemFree](#), [cuMemFreeHost](#), [cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#),
[cuMemHostGetDevicePointer](#), [cuMemsetD2D8](#), [cuMemsetD2D8Async](#), [cuMemsetD2D16](#),
[cuMemsetD2D16Async](#), [cuMemsetD2D32](#), [cuMemsetD2D32Async](#), [cuMemsetD8Async](#),
[cuMemsetD16](#), [cuMemsetD16Async](#), [cuMemsetD32](#), [cuMemsetD32Async](#), [cudaMemset](#)

CUresult cuMemsetD8Async (CUdeviceptr dstDevice, unsigned char uc, size_t N, CUstream hStream)

Sets device memory.

Parameters**dstDevice**

- Destination device pointer

uc

- Value to set

N

- Number of elements

hStream

- Stream identifier

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Sets the memory range of N 8-bit values to the specified value uc .



Note:

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ See also [memset synchronization details](#).
- ▶ This function uses standard [default stream](#) semantics.

See also:

[cuArray3DCreate](#), [cuArray3DGetDescriptor](#), [cuArrayCreate](#), [cuArrayDestroy](#), [cuArrayGetDescriptor](#), [cuMemAlloc](#), [cuMemAllocHost](#), [cuMemAllocPitch](#), [cuMemcpy2D](#), [cuMemcpy2DAsync](#), [cuMemcpy2DUnaligned](#), [cuMemcpy3D](#), [cuMemcpy3DAsync](#), [cuMemcpyAtoA](#), [cuMemcpyAtoD](#), [cuMemcpyAtoH](#), [cuMemcpyAtoHAsync](#), [cuMemcpyDtoA](#), [cuMemcpyDtoD](#), [cuMemcpyDtoDAsync](#), [cuMemcpyDtoH](#), [cuMemcpyDtoHAsync](#), [cuMemcpyHtoA](#), [cuMemcpyHtoAAsync](#), [cuMemcpyHtoD](#), [cuMemcpyHtoDAsync](#), [cuMemFree](#), [cuMemFreeHost](#), [cuMemGetAddressRange](#), [cuMemGetInfo](#), [cuMemHostAlloc](#), [cuMemHostGetDevicePointer](#), [cuMemsetD2D8](#), [cuMemsetD2D8Async](#), [cuMemsetD2D16](#), [cuMemsetD2D16Async](#), [cuMemsetD2D32](#), [cuMemsetD2D32Async](#), [cuMemsetD8](#), [cuMemsetD16](#), [cuMemsetD16Async](#), [cuMemsetD32](#), [cuMemsetD32Async](#), [cudaMemsetAsync](#)

CUresult cuMipmappedArrayCreate (CUmipmappedArray *pHandle, const CUDA_ARRAY3D_DESCRIPTOR *pMipmappedArrayDesc, unsigned int numMipmapLevels)

Creates a CUDA mipmapped array.

Parameters

pHandle

- Returned mipmapped array

pMipmappedArrayDesc

- mipmapped array descriptor

numMipmapLevels

- Number of mipmap levels

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_OUT_OF_MEMORY](#), [CUDA_ERROR_UNKNOWN](#)

Description

Creates a CUDA mipmapped array according to the `CUDA_ARRAY3D_DESCRIPTOR` structure `pMipmappedArrayDesc` and returns a handle to the new CUDA mipmapped array in `*pHandle`. `numMipmapLevels` specifies the number of mipmap levels to be allocated. This value is clamped to the range $[1, 1 + \text{floor}(\log_2(\max(\text{width}, \text{height}, \text{depth})))]$.

The `CUDA_ARRAY3D_DESCRIPTOR` is defined as:

```
↑ typedef struct {
    unsigned int Width;
    unsigned int Height;
    unsigned int Depth;
    CUarray_format Format;
    unsigned int NumChannels;
    unsigned int Flags;
} CUDA_ARRAY3D_DESCRIPTOR;
```

where:

- ▶ `Width`, `Height`, and `Depth` are the width, height, and depth of the CUDA array (in elements); the following types of CUDA arrays can be allocated:
 - ▶ A 1D mipmapped array is allocated if `Height` and `Depth` extents are both zero.
 - ▶ A 2D mipmapped array is allocated if only `Depth` extent is zero.
 - ▶ A 3D mipmapped array is allocated if all three extents are non-zero.
 - ▶ A 1D layered CUDA mipmapped array is allocated if only `Height` is zero and the [CUDA_ARRAY3D_LAYERED](#) flag is set. Each layer is a 1D array. The number of layers is determined by the depth extent.
 - ▶ A 2D layered CUDA mipmapped array is allocated if all three extents are non-zero and the [CUDA_ARRAY3D_LAYERED](#) flag is set. Each layer is a 2D array. The number of layers is determined by the depth extent.
 - ▶ A cubemap CUDA mipmapped array is allocated if all three extents are non-zero and the [CUDA_ARRAY3D_CUBEMAP](#) flag is set. `Width` must be equal to `Height`, and `Depth` must be six. A cubemap is a special type of 2D layered CUDA array, where the six layers represent the six faces of a cube. The order of the six layers in memory is the same as that listed in [CUarray_cubemap_face](#).
 - ▶ A cubemap layered CUDA mipmapped array is allocated if all three extents are non-zero, and both, [CUDA_ARRAY3D_CUBEMAP](#) and [CUDA_ARRAY3D_LAYERED](#) flags are set. `Width` must be equal to `Height`, and `Depth` must be a multiple of six. A cubemap layered CUDA array is a special type of 2D layered CUDA array that consists

of a collection of cubemaps. The first six layers represent the first cubemap, the next six layers form the second cubemap, and so on.

- ▶ Format specifies the format of the elements; `CUarray_format` is defined as:

```
↑
typedef enum CUarray_format_enum {
    CU_AD_FORMAT_UNSIGNED_INT8 = 0x01,
    CU_AD_FORMAT_UNSIGNED_INT16 = 0x02,
    CU_AD_FORMAT_UNSIGNED_INT32 = 0x03,
    CU_AD_FORMAT_SIGNED_INT8 = 0x08,
    CU_AD_FORMAT_SIGNED_INT16 = 0x09,
    CU_AD_FORMAT_SIGNED_INT32 = 0x0a,
    CU_AD_FORMAT_HALF = 0x10,
    CU_AD_FORMAT_FLOAT = 0x20
} CUarray_format;
```

- ▶ NumChannels specifies the number of packed components per CUDA array element; it may be 1, 2, or 4;
- ▶ Flags may be set to
 - ▶ `CUDA_ARRAY3D_LAYERED` to enable creation of layered CUDA mipmapped arrays. If this flag is set, `Depth` specifies the number of layers, not the depth of a 3D array.
 - ▶ `CUDA_ARRAY3D_SURFACE_LDST` to enable surface references to be bound to individual mipmap levels of the CUDA mipmapped array. If this flag is not set, `cuSurfRefSetArray` will fail when attempting to bind a mipmap level of the CUDA mipmapped array to a surface reference.
 - ▶ `CUDA_ARRAY3D_CUBEMAP` to enable creation of mipmapped cubemaps. If this flag is set, `Width` must be equal to `Height`, and `Depth` must be six. If the `CUDA_ARRAY3D_LAYERED` flag is also set, then `Depth` must be a multiple of six.
 - ▶ `CUDA_ARRAY3D_TEXTURE_GATHER` to indicate that the CUDA mipmapped array will be used for texture gather. Texture gather can only be performed on 2D CUDA mipmapped arrays.

`Width`, `Height` and `Depth` must meet certain size requirements as listed in the following table. All values are specified in elements. Note that for brevity's sake, the full name of the device attribute is not specified. For ex., `TEXTURE1D_MIPMAPPED_WIDTH` refers to the device attribute `CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE1D_MIPMAPPED_WIDTH`.

CUDA array type	Valid extents that must always be met {(width range in elements), (height range), (depth range)}	Valid extents with <code>CUDA_ARRAY3D_SURFACE_LDST</code> set {(width range in elements), (height range), (depth range)}
1D	{ (1, <code>TEXTURE1D_MIPMAPPED_WIDTH</code>), (1, <code>SURFACE1D_WIDTH</code>), 0, 0 }	{ (1, <code>TEXTURE1D_MIPMAPPED_WIDTH</code>), (1, <code>SURFACE1D_WIDTH</code>), 0, 0 }
2D	{ (1, <code>TEXTURE2D_MIPMAPPED_WIDTH</code>), (1, <code>TEXTURE2D_MIPMAPPED_HEIGHT</code>), 0 }	{ (1, <code>TEXTURE2D_MIPMAPPED_WIDTH</code>), (1, <code>TEXTURE2D_MIPMAPPED_HEIGHT</code>), 0 }

3D	{ (1,TEXTURE3D_WIDTH), (1,TEXTURE3D_HEIGHT), (1,TEXTURE3D_DEPTH) } OR { (1,SURFACE3D_WIDTH), (1,SURFACE3D_HEIGHT), (1,SURFACE3D_DEPTH) } { (1,TEXTURE3D_WIDTH_ALTERNATE), (1,TEXTURE3D_HEIGHT_ALTERNATE), (1,TEXTURE3D_DEPTH_ALTERNATE) }
1D Layered	{ (1,TEXTURE1D_LAYERED_WIDTH), 0, (1,TEXTURE1D_LAYERED_LAYERS) } OR { (1,SURFACE1D_LAYERED_WIDTH), 0, (1,SURFACE1D_LAYERED_LAYERS) }
2D Layered	{ (1,TEXTURE2D_LAYERED_WIDTH), (1,TEXTURE2D_LAYERED_HEIGHT), (1,TEXTURE2D_LAYERED_LAYERS) } OR { (1,SURFACE2D_LAYERED_WIDTH), (1,SURFACE2D_LAYERED_HEIGHT), (1,SURFACE2D_LAYERED_LAYERS) }
Cubemap	{ (1,TEXTURECUBEMAP_WIDTH), (1,TEXTURECUBEMAP_WIDTH), 6 } OR { (1,SURFACECUBEMAP_WIDTH), (1,SURFACECUBEMAP_WIDTH), 6 }
Cubemap Layered	{ (1,TEXTURECUBEMAP_LAYERED_WIDTH), (1,TEXTURECUBEMAP_LAYERED_WIDTH), (1,TEXTURECUBEMAP_LAYERED_LAYERS) } OR { (1,SURFACECUBEMAP_LAYERED_WIDTH), (1,SURFACECUBEMAP_LAYERED_WIDTH), (1,SURFACECUBEMAP_LAYERED_LAYERS) }

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuMipmappedArrayDestroy](#), [cuMipmappedArrayGetLevel](#), [cuArrayCreate](#),
[cudaMallocMipmappedArray](#)

CUresult cuMipmappedArrayDestroy (CUmipmappedArray hMipmappedArray)

Destroys a CUDA mipmapped array.

Parameters**hMipmappedArray**

- Mipmapped array to destroy

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_HANDLE](#),
[CUDA_ERROR_ARRAY_IS_MAPPED](#), [CUDA_ERROR_CONTEXT_IS_DESTROYED](#)

Description

Destroys the CUDA mipmapped array `hMipmappedArray`.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuMipmappedArrayCreate](#), [cuMipmappedArrayGetLevel](#), [cuArrayCreate](#),
[cudaFreeMipmappedArray](#)

CUresult cuMipmappedArrayGetLevel (CUarray *pLevelArray, CUmipmappedArray hMipmappedArray, unsigned int level)

Gets a mipmap level of a CUDA mipmapped array.

Parameters

pLevelArray

- Returned mipmap level CUDA array

hMipmappedArray

- CUDA mipmapped array

level

- Mipmap level

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_INVALID_HANDLE](#)

Description

Returns in `*pLevelArray` a CUDA array that represents a single mipmap level of the CUDA mipmapped array `hMipmappedArray`.

If `level` is greater than the maximum number of levels in this mipmapped array, [CUDA_ERROR_INVALID_VALUE](#) is returned.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuMipmappedArrayCreate](#), [cuMipmappedArrayDestroy](#), [cuArrayCreate](#),
[cudaGetMipmappedArrayLevel](#)

CUresult cuMipmappedArrayGetSparseProperties (CUDA_ARRAY_SPARSE_PROPERTIES *sparseProperties, CUmipmappedArray mipmap)

Returns the layout properties of a sparse CUDA mipmapped array.

Parameters

sparseProperties

- Pointer to `CUDA_ARRAY_SPARSE_PROPERTIES`

mipmap

- CUDA mipmapped array to get the sparse properties of

Returns

[CUDA_SUCCESS](#) [CUDA_ERROR_INVALID_VALUE](#)

Description

Returns the sparse array layout properties in `sparseProperties`. If the CUDA mipmapped array is not allocated with flag [CUDA_ARRAY3D_SPARSE](#) [CUDA_ERROR_INVALID_VALUE](#) will be returned.

For non-layered CUDA mipmapped arrays, [CUDA_ARRAY_SPARSE_PROPERTIES::mipTailSize](#) returns the size of the mip tail region. The mip tail region includes all mip levels whose width, height or depth is less than that of the tile. For layered CUDA mipmapped arrays, if [CUDA_ARRAY_SPARSE_PROPERTIES::flags](#) contains [CU_ARRAY_SPARSE_PROPERTIES_SINGLE_MIPTAIL](#), then [CUDA_ARRAY_SPARSE_PROPERTIES::mipTailSize](#) specifies the size of the mip tail of all layers combined. Otherwise, [CUDA_ARRAY_SPARSE_PROPERTIES::mipTailSize](#) specifies mip tail size per layer. The returned value of [CUDA_ARRAY_SPARSE_PROPERTIES::mipTailFirstLevel](#) is valid only if [CUDA_ARRAY_SPARSE_PROPERTIES::mipTailSize](#) is non-zero.

See also:

[cuArrayGetSparseProperties](#), [cuMemMapArrayAsync](#)

6.12. Virtual Memory Management

This section describes the virtual memory management functions of the low-level CUDA driver application programming interface.

CUresult cuMemAddressFree (CUdeviceptr ptr, size_t size)

Free an address range reservation.

Parameters

ptr

- Starting address of the virtual address range to free

size

- Size of the virtual address region to free

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_PERMITTED](#), [CUDA_ERROR_NOT_SUPPORTED](#)

Description

Frees a virtual address range reserved by [cuMemAddressReserve](#). The size must match what was given to [memAddressReserve](#) and the `ptr` given must match what was returned from [memAddressReserve](#).

See also:

[cuMemAddressReserve](#)

CUresult cuMemAddressReserve (CUdeviceptr *ptr, size_t size, size_t alignment, CUdeviceptr addr, unsigned long long flags)

Allocate an address range reservation.

Parameters

ptr

- Resulting pointer to start of virtual address range allocated

size

- Size of the reserved virtual address range requested

alignment

- Alignment of the reserved virtual address range requested

addr

- Fixed starting address range requested

flags

- Currently unused, must be zero

Returns

CUDA_SUCCESS, CUDA_ERROR_INVALID_VALUE, CUDA_ERROR_OUT_OF_MEMORY,
CUDA_ERROR_NOT_INITIALIZED, CUDA_ERROR_DEINITIALIZED,
CUDA_ERROR_NOT_PERMITTED, CUDA_ERROR_NOT_SUPPORTED

Description

Reserves a virtual address range based on the given parameters, giving the starting address of the range in `ptr`. This API requires a system that supports UVA. The size and address parameters must be a multiple of the host page size and the alignment must be a power of two or zero for default alignment.

See also:

[cuMemAddressFree](#)

CUresult cuMemCreate (CUmemGenericAllocationHandle *handle, size_t size, const CUmemAllocationProp *prop, unsigned long long flags)

Create a CUDA memory handle representing a memory allocation of a given size described by the given properties.

Parameters

handle

- Value of handle returned. All operations on this allocation are to be performed using this handle.

size

- Size of the allocation requested

prop

- Properties of the allocation to create.

flags

- flags for future use, must be zero now.

Returns

CUDA_SUCCESS, CUDA_ERROR_INVALID_VALUE, CUDA_ERROR_OUT_OF_MEMORY,
CUDA_ERROR_INVALID_DEVICE, CUDA_ERROR_NOT_INITIALIZED,
CUDA_ERROR_DEINITIALIZED, CUDA_ERROR_NOT_PERMITTED,
CUDA_ERROR_NOT_SUPPORTED

Description

This creates a memory allocation on the target device specified through the `prop` structure. The created allocation will not have any device or host mappings. The generic memory `handle` for the allocation can be mapped to the address space of calling process via [cuMemMap](#). This handle cannot be transmitted directly to other processes (see [cuMemExportToShareableHandle](#)). On Windows, the caller must also pass an `LPSECURITYATTRIBUTE` in `prop` to be associated with this handle which limits or allows access to this handle for a recipient process (see [CUmemAllocationProp::win32HandleMetaData](#) for more). The `size` of this allocation must be a multiple of the the value given via [cuMemGetAllocationGranularity](#) with the [CU_MEM_ALLOC_GRANULARITY_MINIMUM](#) flag. If `CUmemAllocationProp::allocFlags::usage` contains [CU_MEM_CREATE_USAGE_TILE_POOL](#) flag then the memory allocation is intended only to be used as backing tile pool for sparse CUDA arrays and sparse CUDA mipmapped arrays. (see [cuMemMapArrayAsync](#)).

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuMemRelease](#), [cuMemExportToShareableHandle](#), [cuMemImportFromShareableHandle](#)

CUresult cuMemExportToShareableHandle (void *shareableHandle, CUmemGenericAllocationHandle handle, CUmemAllocationHandleType handleType, unsigned long long flags)

Exports an allocation to a requested shareable handle type.

Parameters

shareableHandle

- Pointer to the location in which to store the requested handle type

handle

- CUDA handle for the memory allocation

handleType

- Type of shareable handle requested (defines type and size of the `shareableHandle` output parameter)

flags

- Reserved, must be zero

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_PERMITTED](#), [CUDA_ERROR_NOT_SUPPORTED](#)

Description

Given a CUDA memory handle, create a shareable memory allocation handle that can be used to share the memory with other processes. The recipient process can convert the shareable handle back into a CUDA memory handle using [cuMemImportFromShareableHandle](#) and map it with [cuMemMap](#). The implementation of what this handle is and how it can be transferred is defined by the requested handle type in `handleType`

Once all shareable handles are closed and the allocation is released, the allocated memory referenced will be released back to the OS and uses of the CUDA handle afterward will lead to undefined behavior.

This API can also be used in conjunction with other APIs (e.g. Vulkan, OpenGL) that support importing memory from the shareable type

See also:

[cuMemImportFromShareableHandle](#)

CUresult cuMemGetAccess (unsigned long long *flags, const CUmemLocation *location, CUdeviceptr ptr)

Get the access flags set for the given location and ptr.

Parameters

flags

- Flags set for this location

location

- Location in which to check the flags for

ptr

- Address in which to check the access flags for

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_DEVICE](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_PERMITTED](#), [CUDA_ERROR_NOT_SUPPORTED](#)

Description

See also:

[cuMemSetAccess](#)

CUresult cuMemGetAllocationGranularity (size_t *granularity, const CUmemAllocationProp *prop, CUmemAllocationGranularity_flags option)

Calculates either the minimal or recommended granularity.

Parameters

granularity

Returned granularity.

prop

Property for which to determine the granularity for

option

Determines which granularity to return

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_PERMITTED](#),
[CUDA_ERROR_NOT_SUPPORTED](#)

Description

Calculates either the minimal or recommended granularity for a given allocation specification and returns it in granularity. This granularity can be used as a multiple for alignment, size, or address mapping.

See also:

[cuMemCreate](#), [cuMemMap](#)

CUresult cuMemGetAllocationPropertiesFromHandle (CUmemAllocationProp *prop, CUmemGenericAllocationHandle handle)

Retrieve the contents of the property structure defining properties for this handle.

Parameters**prop**

- Pointer to a properties structure which will hold the information about this handle

handle

- Handle which to perform the query on

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_PERMITTED](#),
[CUDA_ERROR_NOT_SUPPORTED](#)

Description**See also:**

[cuMemCreate](#), [cuMemImportFromShareableHandle](#)

CUresult cuMemImportFromShareableHandle (CUmemGenericAllocationHandle *handle, void *osHandle, CUmemAllocationHandleType shHandleType)

Imports an allocation from a requested shareable handle type.

Parameters

handle

- CUDA Memory handle for the memory allocation.

osHandle

- Shareable Handle representing the memory allocation that is to be imported.

shHandleType

- handle type of the exported handle [CUmemAllocationHandleType](#).

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_PERMITTED](#),
[CUDA_ERROR_NOT_SUPPORTED](#)

Description

If the current process cannot support the memory described by this shareable handle, this API will error as [CUDA_ERROR_NOT_SUPPORTED](#).



Note:

Importing shareable handles exported from some graphics APIs (Vulkan, OpenGL, etc) created on devices under an SLI group may not be supported, and thus this API will return [CUDA_ERROR_NOT_SUPPORTED](#). There is no guarantee that the contents of `handle` will be the same CUDA memory handle for the same given OS shareable handle, or the same underlying allocation.

See also:

[cuMemExportToShareableHandle](#), [cuMemMap](#), [cuMemRelease](#)

CUresult cuMemMap (CUdeviceptr ptr, size_t size, size_t offset, CUmemGenericAllocationHandle handle, unsigned long long flags)

Maps an allocation handle to a reserved virtual address range.

Parameters

ptr

- Address where memory will be mapped.

size

- Size of the memory mapping.

offset

handle from which to start mapping Note: currently must be zero.

- Offset into the memory represented by

handle

- Handle to a shareable memory

flags

- flags for future use, must be zero now.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_DEVICE](#), [CUDA_ERROR_OUT_OF_MEMORY](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_PERMITTED](#), [CUDA_ERROR_NOT_SUPPORTED](#)

- ▶ handle from which to start mapping
- ▶ Note: currently must be zero.

Description

Maps bytes of memory represented by handle starting from byte offset to size to address range [addr, addr + size]. This range must be an address reservation previously reserved with [cuMemAddressReserve](#), and offset + size must be less than the size of the memory allocation. Both ptr, size, and offset must be a multiple of the value given via [cuMemGetAllocationGranularity](#) with the [CU_MEM_ALLOC_GRANULARITY_MINIMUM](#) flag.

Please note calling [cuMemMap](#) does not make the address accessible, the caller needs to update accessibility of a contiguous mapped VA range by calling [cuMemSetAccess](#).

Once a recipient process obtains a shareable memory handle from [cuMemImportFromShareableHandle](#), the process must use [cuMemMap](#) to map the memory into its address ranges before setting accessibility with [cuMemSetAccess](#).

[cuMemMap](#) can only create mappings on VA range reservations that are not currently mapped.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuMemUnmap](#), [cuMemSetAccess](#), [cuMemCreate](#), [cuMemAddressReserve](#),
[cuMemImportFromShareableHandle](#)

CUresult cuMemMapArrayAsync (CUarrayMapInfo *mapInfoList, unsigned int count, CUstream hStream)

Maps or unmaps subregions of sparse CUDA arrays and sparse CUDA mipmapped arrays.

Parameters

mapInfoList

- List of CUarrayMapInfo

count

- Count of CUarrayMapInfo in mapInfoList

hStream

- Stream identifier for the stream to use for map or unmap operations

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_HANDLE](#)

Description

Performs map or unmap operations on subregions of sparse CUDA arrays and sparse CUDA mipmapped arrays. Each operation is specified by a CUarrayMapInfo entry in the mapInfoList array of size count. The structure CUarrayMapInfo is defined as follow:

```
↑
typedef struct CUarrayMapInfo_st {
    CUresourcetype resourceType;
    union {
        CUmipmappedArray mipmap;
        CUarray array;
    } resource;

    CUarraySparseSubresourceType subresourceType;
    union {
        struct {
            unsigned int level;
            unsigned int layer;
            unsigned int offsetX;
            unsigned int offsetY;
            unsigned int offsetZ;
            unsigned int extentWidth;
        };
    };
};
```

```

        unsigned int extentHeight;
        unsigned int extentDepth;
    } sparseLevel;
    struct {
        unsigned int layer;
        unsigned long long offset;
        unsigned long long size;
    } mipTail;
} subresource;

CUmemOperationType memOperationType;

CUmemHandleType memHandleType;
union {
    CUmemGenericAllocationHandle memHandle;
} memHandle;

unsigned long long offset;
unsigned int deviceBitMask;
unsigned int flags;
unsigned int reserved[2];
} CUarrayMapInfo;

```

where [CUarrayMapInfo::resourceType](#) specifies the type of resource to be operated on. If [CUarrayMapInfo::resourceType](#) is set to [CUresourcetype::CU_RESOURCE_TYPE_ARRAY](#) then [CUarrayMapInfo::resource::array](#) must be set to a valid sparse CUDA array handle. The CUDA array must be either a 2D, 2D layered or 3D CUDA array and must have been allocated using [cuArrayCreate](#) or [cuArray3DCreate](#) with the flag [CUDA_ARRAY3D_SPARSE](#). For CUDA arrays obtained using [cuMipmappedArrayGetLevel](#), [CUDA_ERROR_INVALID_VALUE](#) will be returned. If [CUarrayMapInfo::resourceType](#) is set to [CUresourcetype::CU_RESOURCE_TYPE_MIPMAPPED_ARRAY](#) then [CUarrayMapInfo::resource::mipmapped](#) must be set to a valid sparse CUDA mipmapped array handle. The CUDA mipmapped array must be either a 2D, 2D layered or 3D CUDA mipmapped array and must have been allocated using [cuMipmappedArrayCreate](#) with the flag [CUDA_ARRAY3D_SPARSE](#).

[CUarrayMapInfo::subresourceType](#) specifies the type of subresource within the resource. [CUarraySparseSubresourceType_enum](#) is defined as:

```

↑ typedef enum CUarraySparseSubresourceType_enum {
    CU_ARRAY_SPARSE_SUBRESOURCE_TYPE_SPARSE_LEVEL = 0,
    CU_ARRAY_SPARSE_SUBRESOURCE_TYPE_MIPTAIL = 1
} CUarraySparseSubresourceType;

```

where

[CUarraySparseSubresourceType::CU_ARRAY_SPARSE_SUBRESOURCE_TYPE_SPARSE_LEVEL](#) indicates a sparse-miplevel which spans at least one tile in every dimension. The remaining miplevels which are too small to span at least one tile in any dimension constitute the mip tail region as indicated by [CUarraySparseSubresourceType::CU_ARRAY_SPARSE_SUBRESOURCE_TYPE_MIPTAIL](#) subresource type.

If [CUarrayMapInfo::subresourceType](#) is set to [CUarraySparseSubresourceType::CU_ARRAY_SPARSE_SUBRESOURCE_TYPE_SPARSE_LEVEL](#) then [CUarrayMapInfo::subresource::sparseLevel](#) struct must contain valid array subregion offsets and extents. The [CUarrayMapInfo::subresource::sparseLevel::offsetX](#),

`CUarrayMapInfo::subresource::sparseLevel::offsetY` and `CUarrayMapInfo::subresource::sparseLevel::offsetZ` must specify valid X, Y and Z offsets respectively. The `CUarrayMapInfo::subresource::sparseLevel::extentWidth`, `CUarrayMapInfo::subresource::sparseLevel::extentHeight` and `CUarrayMapInfo::subresource::sparseLevel::extentDepth` must specify valid width, height and depth extents respectively. These offsets and extents must be aligned to the corresponding tile dimension. For CUDA mipmapped arrays `CUarrayMapInfo::subresource::sparseLevel::level` must specify a valid mip level index. Otherwise, must be zero. For layered CUDA arrays and layered CUDA mipmapped arrays `CUarrayMapInfo::subresource::sparseLevel::layer` must specify a valid layer index. Otherwise, must be zero. `CUarrayMapInfo::subresource::sparseLevel::offsetZ` must be zero and `CUarrayMapInfo::subresource::sparseLevel::extentDepth` must be set to 1 for 2D and 2D layered CUDA arrays and CUDA mipmapped arrays. Tile extents can be obtained by calling [cuArrayGetSparseProperties](#) and [cuMipmappedArrayGetSparseProperties](#)

If [CUarrayMapInfo::subresourceType](#) is set to `CUarraySparseSubresourceType::CU_ARRAY_SPARSE_SUBRESOURCE_TYPE_MIPTAIL` then `CUarrayMapInfo::subresource::mipTail` struct must contain valid mip tail offset in `CUarrayMapInfo::subresource::mipTail::offset` and size in `CUarrayMapInfo::subresource::mipTail::size`. Both, mip tail offset and mip tail size must be aligned to the tile size. For layered CUDA mipmapped arrays which don't have the flag [CU_ARRAY_SPARSE_PROPERTIES_SINGLE_MIPTAIL](#) set in [CUDA_ARRAY_SPARSE_PROPERTIES::flags](#) as returned by [cuMipmappedArrayGetSparseProperties](#), `CUarrayMapInfo::subresource::mipTail::layer` must specify a valid layer index. Otherwise, must be zero.

[CUarrayMapInfo::memOperationType](#) specifies the type of operation. [CUmemOperationType](#) is defined as:

```
↑
typedef enum CUmemOperationType_enum {
    CU_MEM_OPERATION_TYPE_MAP = 1,
    CU_MEM_OPERATION_TYPE_UNMAP = 2
} CUmemOperationType;
```

If [CUarrayMapInfo::memOperationType](#) is set to `CUmemOperationType::CU_MEM_OPERATION_TYPE_MAP` then the subresource will be mapped onto the tile pool memory specified by `CUarrayMapInfo::memHandle` at offset [CUarrayMapInfo::offset](#). The tile pool allocation has to be created by specifying the [CU_MEM_CREATE_USAGE_TILE_POOL](#) flag when calling [cuMemCreate](#). Also, [CUarrayMapInfo::memHandleType](#) must be set to `CUmemHandleType::CU_MEM_HANDLE_TYPE_GENERIC`.

If [CUarrayMapInfo::memOperationType](#) is set to `CUmemOperationType::CU_MEM_OPERATION_TYPE_UNMAP` then an unmapping operation is performed. `CUarrayMapInfo::memHandle` must be NULL.

[CUarrayMapInfo::deviceBitMask](#) specifies the list of devices that must map or unmap physical memory. Currently, this mask must have exactly one bit set, and the corresponding device must match the device associated with the stream. If [CUarrayMapInfo::memOperationType](#)

is set to `CUmemOperationType::CU_MEM_OPERATION_TYPE_MAP`, the device must also match the device associated with the tile pool memory allocation as specified by `CUarrayMapInfo::memHandle`.

[CUarrayMapInfo::flags](#) and [CUarrayMapInfo::reserved\[\]](#) are unused and must be set to zero.

See also:

[cuMipmappedArrayCreate](#), [cuArrayCreate](#), [cuArray3DCreate](#), [cuMemCreate](#), [cuArrayGetSparseProperties](#), [cuMipmappedArrayGetSparseProperties](#)

CUresult cuMemRelease (CUmemGenericAllocationHandle handle)

Release a memory handle representing a memory allocation which was previously allocated through `cuMemCreate`.

Parameters

handle

Value of handle which was returned previously by `cuMemCreate`.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_PERMITTED](#), [CUDA_ERROR_NOT_SUPPORTED](#)

Description

Frees the memory that was allocated on a device through `cuMemCreate`.

The memory allocation will be freed when all outstanding mappings to the memory are unmapped and when all outstanding references to the handle (including its shareable counterparts) are also released. The generic memory handle can be freed when there are still outstanding mappings made with this handle. Each time a recipient process imports a shareable handle, it needs to pair it with [cuMemRelease](#) for the handle to be freed. If `handle` is not a valid handle the behavior is undefined.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuMemCreate](#)

CUresult cuMemRetainAllocationHandle (CUmemGenericAllocationHandle *handle, void *addr)

Given an address `addr`, returns the allocation handle of the backing memory allocation.

Parameters

handle

CUDA Memory handle for the backing memory allocation.

addr

Memory address to query, that has been mapped previously.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_PERMITTED](#),
[CUDA_ERROR_NOT_SUPPORTED](#)

Description

The handle is guaranteed to be the same handle value used to map the memory. If the address requested is not mapped, the function will fail. The returned handle must be released with corresponding number of calls to [cuMemRelease](#).



Note:

The address `addr`, can be any address in a range previously mapped by [cuMemMap](#), and not necessarily the start address.

See also:

[cuMemCreate](#), [cuMemRelease](#), [cuMemMap](#)

CUresult cuMemSetAccess (CUdeviceptr ptr, size_t size, const CUmemAccessDesc *desc, size_t count)

Set the access flags for each location specified in `desc` for the given virtual address range.

Parameters

ptr

- Starting address for the virtual address range

size

- Length of the virtual address range

desc

mapping for each location specified

- Array of `CUMemAccessDesc` that describe how to change the

count

- Number of `CUMemAccessDesc` in `desc`

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_DEVICE](#), [CUDA_ERROR_NOT_SUPPORTED](#)

- ▶ mapping for each location specified

Description

Given the virtual address range via `ptr` and `size`, and the locations in the array given by `desc` and `count`, set the access flags for the target locations. The range must be a fully mapped address range containing all allocations created by [cuMemMap](#) / [cuMemCreate](#).

**Note:**

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ This function exhibits [synchronous](#) behavior for most use cases.

See also:

[cuMemSetAccess](#), [cuMemCreate](#), [:cuMemMap](#)

CUresult cuMemUnmap (CUdeviceptr ptr, size_t size)

Unmap the backing memory of a given address range.

Parameters**ptr**

- Starting address for the virtual address range to unmap

size

- Size of the virtual address range to unmap

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_PERMITTED](#), [CUDA_ERROR_NOT_SUPPORTED](#)

Description

The range must be the entire contiguous address range that was mapped to. In other words, [cuMemUnmap](#) cannot unmap a sub-range of an address range mapped by [cuMemCreate](#) /

[cuMemMap](#). Any backing memory allocations will be freed if there are no existing mappings and there are no unreleased memory handles.

When [cuMemUnmap](#) returns successfully the address range is converted to an address reservation and can be used for a future calls to [cuMemMap](#). Any new mapping to this virtual address will need to have access granted through [cuMemSetAccess](#), as all mappings start with no accessibility setup.



Note:

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ This function exhibits [synchronous](#) behavior for most use cases.

See also:

[cuMemCreate](#), [cuMemAddressReserve](#)

6.13. Stream Ordered Memory Allocator

This section describes the stream ordered memory allocator exposed by the low-level CUDA driver application programming interface.

overview

The asynchronous allocator allows the user to allocate and free in stream order. All asynchronous accesses of the allocation must happen between the stream executions of the allocation and the free. If the memory is accessed outside of the promised stream order, a use before allocation / use after free error will cause undefined behavior.

The allocator is free to reallocate the memory as long as it can guarantee that compliant memory accesses will not overlap temporally. The allocator may refer to internal stream ordering as well as inter-stream dependencies (such as CUDA events and null stream dependencies) when establishing the temporal guarantee. The allocator may also insert inter-stream dependencies to establish the temporal guarantee.

Supported Platforms

Whether or not a device supports the integrated stream ordered memory allocator may be queried by calling [cuDeviceGetAttribute\(\)](#) with the device attribute [CU_DEVICE_ATTRIBUTE_MEMORY_POOLS_SUPPORTED](#)

CUresult cuMemAllocAsync (CUdeviceptr *dptr, size_t bytesize, CUstream hStream)

Allocates memory with stream ordered semantics.

Parameters

dptr

- Returned device pointer

bytesize

- Number of bytes to allocate

hStream

- The stream establishing the stream ordering contract and the memory pool to allocate from

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#) (default stream specified with no current context), [CUDA_ERROR_NOT_SUPPORTED](#), [CUDA_ERROR_OUT_OF_MEMORY](#)

Description

Inserts an allocation operation into `hStream`. A pointer to the allocated memory is returned immediately in `*dptr`. The allocation must not be accessed until the the allocation operation completes. The allocation comes from the memory pool current to the stream's device.

**Note:**

- ▶ The default memory pool of a device contains device memory from that device.
- ▶ Basic stream ordering allows future work submitted into the same stream to use the allocation. Stream query, stream synchronize, and CUDA events can be used to guarantee that the allocation operation completes before work submitted in a separate stream runs.

See also:

[cuMemAllocFromPoolAsync](#), [cuMemFreeAsync](#), [cuDeviceSetMemPool](#), [cuDeviceGetDefaultMemPool](#), [cuDeviceGetMemPool](#), [cuMemPoolCreate](#), [cuMemPoolSetAccess](#), [cuMemPoolSetAttribute](#)

CUresult cuMemAllocFromPoolAsync (CUdeviceptr *dptr, size_t bytesize, CUmemoryPool pool, CUstream hStream)

Allocates memory from a specified pool with stream ordered semantics.

Parameters

dptr

- Returned device pointer

bytesize

- Number of bytes to allocate

pool

- The pool to allocate from

hStream

- The stream establishing the stream ordering semantic

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#) (default stream specified with no current context), [CUDA_ERROR_NOT_SUPPORTED](#), [CUDA_ERROR_OUT_OF_MEMORY](#)

Description

Inserts an allocation operation into `hStream`. A pointer to the allocated memory is returned immediately in `*dptr`. The allocation must not be accessed until the the allocation operation completes. The allocation comes from the specified memory pool.



Note:

- ▶ The specified memory pool may be from a device different than that of the specified `hStream`.

- ▶ Basic stream ordering allows future work submitted into the same stream to use the allocation. Stream query, stream synchronize, and CUDA events can be used to guarantee that the allocation operation completes before work submitted in a separate stream runs.

See also:

[cuMemAllocAsync](#), [cuMemFreeAsync](#), [cuDeviceGetDefaultMemPool](#), [cuDeviceGetMemPool](#), [cuMemPoolCreate](#), [cuMemPoolSetAccess](#), [cuMemPoolSetAttribute](#)

CUresult cuMemFreeAsync (CUdeviceptr dptr, CUstream hStream)

Frees memory with stream ordered semantics.

Parameters

dptr

- memory to free

hStream

- The stream establishing the stream ordering contract.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#) (default stream specified with no current context), [CUDA_ERROR_NOT_SUPPORTED](#)

Description

Inserts a free operation into `hStream`. The allocation must not be accessed after stream execution reaches the free. After this API returns, accessing the memory from any subsequent work launched on the GPU or querying its pointer attributes results in undefined behavior.

CUresult cuMemPoolCreate (CUmemoryPool *pool, const CUmemPoolProps *poolProps)

Creates a memory pool.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_OUT_OF_MEMORY](#), [CUDA_ERROR_NOT_SUPPORTED](#)

Description

Creates a CUDA memory pool and returns the handle in `pool`. The `poolProps` determines the properties of the pool such as the backing device and IPC capabilities.

By default, the pool's memory will be accessible from the device it is allocated on.



Note:

Specifying `CU_MEM_HANDLE_TYPE_NONE` creates a memory pool that will not support IPC.

See also:

[cuDeviceSetMemPool](#), [cuDeviceGetMemPool](#), [cuDeviceGetDefaultMemPool](#),
[cuMemAllocFromPoolAsync](#), [cuMemPoolExportToShareableHandle](#)

CUresult cuMemPoolDestroy (CUmemoryPool pool)

Destroys the specified memory pool.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

If any pointers obtained from this pool haven't been freed or the pool has free operations that haven't completed when [cuMemPoolDestroy](#) is invoked, the function will return immediately and the resources associated with the pool will be released automatically once there are no more outstanding allocations.

Destroying the current mempool of a device sets the default mempool of that device as the current mempool for that device.



Note:

A device's default memory pool cannot be destroyed.

See also:

[cuMemFreeAsync](#), [cuDeviceSetMemPool](#), [cuDeviceGetMemPool](#),
[cuDeviceGetDefaultMemPool](#), [cuMemPoolCreate](#)

CUresult cuMemPoolExportPointer (CUmemoryPoolPtrExportData *shareData_out, CUdeviceptr ptr)

Export data to share a memory pool allocation between processes.

Parameters

shareData_out

- Returned export data

ptr

- pointer to memory being exported

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_OUT_OF_MEMORY](#)

Description

Constructs `shareData_out` for sharing a specific allocation from an already shared memory pool. The recipient process can import the allocation with the [cuMemPoolImportPointer](#) api. The data is not a handle and may be shared through any IPC mechanism.

See also:

[cuMemPoolExportToShareableHandle](#), [cuMemPoolImportFromShareableHandle](#), [cuMemPoolImportPointer](#)

CUresult cuMemPoolExportToShareableHandle (void *handle_out, CUmemoryPool pool, CUmemAllocationHandleType handleType, unsigned long long flags)

Exports a memory pool to the requested handle type.

Parameters

handle_out

- Returned OS handle

pool

- pool to export

handleType

- the type of handle to create

flags

- must be 0

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_OUT_OF_MEMORY](#)

Description

Given an IPC capable mempool, create an OS handle to share the pool with another process. A recipient process can convert the shareable handle into a mempool with [cuMemPoolImportFromShareableHandle](#). Individual pointers can then be shared with the [cuMemPoolExportPointer](#) and [cuMemPoolImportPointer](#) APIs. The implementation of what the shareable handle is and how it can be transferred is defined by the requested handle type.



Note:

: To create an IPC capable mempool, create a mempool with a CUmemAllocationHandleType other than CU_MEM_HANDLE_TYPE_NONE.

See also:

[cuMemPoolImportFromShareableHandle](#), [cuMemPoolExportPointer](#),
[cuMemPoolImportPointer](#), [cuMemAllocAsync](#), [cuMemFreeAsync](#),
[cuDeviceGetDefaultMemPool](#), [cuDeviceGetMemPool](#), [cuMemPoolCreate](#),
[cuMemPoolSetAccess](#), [cuMemPoolSetAttribute](#)

CUresult cuMemPoolGetAccess (CUmemAccess_flags *flags, CUmemoryPool memPool, CUmemLocation *location)

Returns the accessibility of a pool from a device.

Parameters

flags

- the accessibility of the pool from the specified location

memPool

- the pool being queried

location

- the location accessing the pool

Description

Returns the accessibility of the pool's memory from the specified location.

See also:

[cuMemAllocAsync](#), [cuMemFreeAsync](#), [cuDeviceGetDefaultMemPool](#), [cuDeviceGetMemPool](#),
[cuMemPoolCreate](#)

CUresult cuMemPoolGetAttribute (CUmemoryPool pool, CUmemPool_attribute attr, void *value)

Gets attributes of a memory pool.

Parameters

pool

- The memory pool to get attributes of

attr

- The attribute to get

value

- Retrieved value

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Supported attributes are:

- ▶ [CU_MEMPOOL_ATTR_RELEASE_THRESHOLD](#): (value type = `cuuint64_t`) Amount of reserved memory in bytes to hold onto before trying to release memory back to the OS. When more than the release threshold bytes of memory are held by the memory pool, the allocator will try to release memory back to the OS on the next call to stream, event or context synchronize. (default 0)
- ▶ [CU_MEMPOOL_ATTR_REUSE_FOLLOW_EVENT_DEPENDENCIES](#): (value type = `int`) Allow [cuMemAllocAsync](#) to use memory asynchronously freed in another stream as long as a stream ordering dependency of the allocating stream on the free action exists. Cuda events and null stream interactions can create the required stream ordered dependencies. (default enabled)
- ▶ [CU_MEMPOOL_ATTR_REUSE_ALLOW_OPPORTUNISTIC](#): (value type = `int`) Allow reuse of already completed frees when there is no dependency between the free and allocation. (default enabled)
- ▶ [CU_MEMPOOL_ATTR_REUSE_ALLOW_INTERNAL_DEPENDENCIES](#): (value type = `int`) Allow [cuMemAllocAsync](#) to insert new stream dependencies in order to establish the stream ordering required to reuse a piece of memory released by [cuMemFreeAsync](#) (default enabled).
- ▶ [CU_MEMPOOL_ATTR_RESERVED_MEM_CURRENT](#): (value type = `cuuint64_t`) Amount of backing memory currently allocated for the mempool
- ▶ [CU_MEMPOOL_ATTR_RESERVED_MEM_HIGH](#): (value type = `cuuint64_t`) High watermark of backing memory allocated for the mempool since the last time it was reset.
- ▶ [CU_MEMPOOL_ATTR_USED_MEM_CURRENT](#): (value type = `cuuint64_t`) Amount of memory from the pool that is currently in use by the application.
- ▶ [CU_MEMPOOL_ATTR_USED_MEM_HIGH](#): (value type = `cuuint64_t`) High watermark of the amount of memory from the pool that was in use by the application.

See also:

[cuMemAllocAsync](#), [cuMemFreeAsync](#), [cuDeviceGetDefaultMemPool](#), [cuDeviceGetMemPool](#), [cuMemPoolCreate](#)

CUresult cuMemPoolImportFromShareableHandle
(CUmemoryPool *pool_out, void *handle,
CUmemAllocationHandleType handleType, unsigned
long long flags)

imports a memory pool from a shared handle.

Parameters

pool_out

- Returned memory pool

handle

- OS handle of the pool to open

handleType

- The type of handle being imported

flags

- must be 0

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_OUT_OF_MEMORY](#)

Description

Specific allocations can be imported from the imported pool with [cuMemPoolImportPointer](#).

**Note:**

Imported memory pools do not support creating new allocations. As such imported memory pools may not be used in [cuDeviceSetMemPool](#) or [cuMemAllocFromPoolAsync](#) calls.

See also:

[cuMemPoolExportToShareableHandle](#), [cuMemPoolExportPointer](#), [cuMemPoolImportPointer](#)

CUresult cuMemPoolImportPointer (CUdeviceptr *ptr_out, CUmemoryPool pool, CUmemPoolPtrExportData *shareData)

Import a memory pool allocation from another process.

Parameters

ptr_out

- pointer to imported memory

pool

- pool from which to import

shareData

- data specifying the memory to import

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_OUT_OF_MEMORY](#)

Description

Returns in `ptr_out` a pointer to the imported memory. The imported memory must not be accessed before the allocation operation completes in the exporting process. The imported memory must be freed from all importing processes before being freed in the exporting process. The pointer may be freed with `cuMemFree` or `cuMemFreeAsync`. If `cuMemFreeAsync` is used, the free must be completed on the importing process before the free operation on the exporting process.

**Note:**

The `cuMemFreeAsync` api may be used in the exporting process before the `cuMemFreeAsync` operation completes in its stream as long as the `cuMemFreeAsync` in the exporting process specifies a stream with a stream dependency on the importing process's `cuMemFreeAsync`.

See also:

[cuMemPoolExportToShareableHandle](#), [cuMemPoolImportFromShareableHandle](#),
[cuMemPoolExportPointer](#)

CUresult cuMemPoolSetAccess (CUmemoryPool pool, const CUmemAccessDesc *map, size_t count)

Controls visibility of pools between devices.

Parameters

pool

- The pool being modified

map

- Array of access descriptors. Each descriptor instructs the access to enable for a single gpu.

count

- Number of descriptors in the map array.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

See also:

[cuMemAllocAsync](#), [cuMemFreeAsync](#), [cuDeviceGetDefaultMemPool](#), [cuDeviceGetMemPool](#), [cuMemPoolCreate](#)

CUresult cuMemPoolSetAttribute (CUmemoryPool pool, CUmemPool_attribute attr, void *value)

Sets attributes of a memory pool.

Parameters

pool

- The memory pool to modify

attr

- The attribute to modify

value

- Pointer to the value to assign

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Supported attributes are:

- ▶ `CU_MEMPOOL_ATTR_RELEASE_THRESHOLD`: (value type = `cuuint64_t`) Amount of reserved memory in bytes to hold onto before trying to release memory back to the OS. When more than the release threshold bytes of memory are held by the memory pool, the allocator will try to release memory back to the OS on the next call to stream, event or context synchronize. (default 0)
- ▶ `CU_MEMPOOL_ATTR_REUSE_FOLLOW_EVENT_DEPENDENCIES`: (value type = `int`) Allow [cuMemAllocAsync](#) to use memory asynchronously freed in another stream as long as a stream ordering dependency of the allocating stream on the free action exists. Cuda events and null stream interactions can create the required stream ordered dependencies. (default enabled)
- ▶ `CU_MEMPOOL_ATTR_REUSE_ALLOW_OPPORTUNISTIC`: (value type = `int`) Allow reuse of already completed frees when there is no dependency between the free and allocation. (default enabled)
- ▶ `CU_MEMPOOL_ATTR_REUSE_ALLOW_INTERNAL_DEPENDENCIES`: (value type = `int`) Allow [cuMemAllocAsync](#) to insert new stream dependencies in order to establish the stream ordering required to reuse a piece of memory released by [cuMemFreeAsync](#) (default enabled).
- ▶ `CU_MEMPOOL_ATTR_RESERVED_MEM_HIGH`: (value type = `cuuint64_t`) Reset the high watermark that tracks the amount of backing memory that was allocated for the memory pool. It is illegal to set this attribute to a non-zero value.
- ▶ `CU_MEMPOOL_ATTR_USED_MEM_HIGH`: (value type = `cuuint64_t`) Reset the high watermark that tracks the amount of used memory that was allocated for the memory pool.

See also:

[cuMemAllocAsync](#), [cuMemFreeAsync](#), [cuDeviceGetDefaultMemPool](#), [cuDeviceGetMemPool](#), [cuMemPoolCreate](#)

CUresult cuMemPoolTrimTo (CUmemoryPool pool, size_t minBytesToKeep)

Tries to release memory back to the OS.

Parameters

pool

- The memory pool to trim

minBytesToKeep


- If the pool has less than minBytesToKeep reserved, the TrimTo operation is a no-op. Otherwise the pool will be guaranteed to have at least minBytesToKeep bytes reserved after the operation.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Releases memory back to the OS until the pool contains fewer than minBytesToKeep reserved bytes, or there is no more memory that the allocator can safely release. The allocator cannot release OS allocations that back outstanding asynchronous allocations. The OS allocations may happen at different granularity from the user allocations.



Note:

- ▶ : Allocations that have not been freed count as outstanding.
- ▶ : Allocations that have been asynchronously freed but whose completion has not been observed on the host (eg. by a synchronize) can count as outstanding.

See also:

[cuMemAllocAsync](#), [cuMemFreeAsync](#), [cuDeviceGetDefaultMemPool](#), [cuDeviceGetMemPool](#), [cuMemPoolCreate](#)

6.14. Unified Addressing

This section describes the unified addressing functions of the low-level CUDA driver application programming interface.

Overview

CUDA devices can share a unified address space with the host. For these devices there is no distinction between a device pointer and a host pointer -- the same pointer value may be used to access memory from the host program and from a kernel running on the device (with exceptions enumerated below).

Supported Platforms

Whether or not a device supports unified addressing may be queried by calling [cuDeviceGetAttribute\(\)](#) with the device attribute [CU_DEVICE_ATTRIBUTE_UNIFIED_ADDRESSING](#).

Unified addressing is automatically enabled in 64-bit processes

Looking Up Information from Pointer Values

It is possible to look up information about the memory which backs a pointer value. For instance, one may want to know if a pointer points to host or device memory. As another example, in the case of device memory, one may want to know on which CUDA device the memory resides. These properties may be queried using the function [cuPointerGetAttribute\(\)](#)

Since pointers are unique, it is not necessary to specify information about the pointers specified to the various copy functions in the CUDA API. The function [cuMemcpy\(\)](#) may be used to perform a copy between two pointers, ignoring whether they point to host or device memory (making [cuMemcpyHtoD\(\)](#), [cuMemcpyDtoD\(\)](#), and [cuMemcpyDtoH\(\)](#) unnecessary for devices supporting unified addressing). For multidimensional copies, the memory type [CU_MEMORYTYPE_UNIFIED](#) may be used to specify that the CUDA driver should infer the location of the pointer from its value.

Automatic Mapping of Host Allocated Host Memory

All host memory allocated in all contexts using [cuMemAllocHost\(\)](#) and [cuMemHostAlloc\(\)](#) is always directly accessible from all contexts on all devices that support unified addressing. This is the case regardless of whether or not the flags [CU_MEMHOSTALLOC_PORTABLE](#) and [CU_MEMHOSTALLOC_DEVICEMAP](#) are specified.

The pointer value through which allocated host memory may be accessed in kernels on all devices that support unified addressing is the same as the pointer value through which that memory is accessed on the host, so it is not necessary to call [cuMemHostGetDevicePointer\(\)](#) to get the device pointer for these allocations.

Note that this is not the case for memory allocated using the flag [CU_MEMHOSTALLOC_WRITECOMBINED](#), as discussed below.

Automatic Registration of Peer Memory

Upon enabling direct access from a context that supports unified addressing to another peer context that supports unified addressing using [cuCtxEnablePeerAccess\(\)](#) all memory allocated in the peer context using [cuMemAlloc\(\)](#) and [cuMemAllocPitch\(\)](#) will immediately be accessible by the current context. The device pointer value through which any peer memory may be accessed in the current context is the same pointer value through which that memory may be accessed in the peer context.

Exceptions, Disjoint Addressing

Not all memory may be accessed on devices through the same pointer value through which they are accessed on the host. These exceptions are host memory registered using [cuMemHostRegister\(\)](#) and host memory allocated using the flag [CU_MEMHOSTALLOC_WRITECOMBINED](#). For these exceptions, there exists a distinct host and device address for the memory. The device address is guaranteed to not overlap any valid host pointer range and is guaranteed to have the same value across all contexts that support unified addressing.

This device address may be queried using [cuMemHostGetDevicePointer\(\)](#) when a context using unified addressing is current. Either the host or the unified device pointer value may be used to refer to this memory through [cuMemcpy\(\)](#) and similar functions using the [CU_MEMORYTYPE_UNIFIED](#) memory type.

CUresult cuMemAdvise (CUdeviceptr devPtr, size_t count, CUmem_advise advice, CUdevice device)

Advise about the usage of a given memory range.

Parameters

devPtr

- Pointer to memory to set the advice for

count

- Size in bytes of the memory range

advice

- Advice to be applied for the specified memory range

device

- Device to apply the advice for

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_DEVICE](#)

Description

Advise the Unified Memory subsystem about the usage pattern for the memory range starting at `devPtr` with a size of `count` bytes. The start address and end address of the memory range will be rounded down and rounded up respectively to be aligned to CPU page size before the advice is applied. The memory range must refer to managed memory allocated via [cuMemAllocManaged](#) or declared via `__managed__` variables. The memory range could also refer to system-allocated pageable memory provided it represents a valid, host-accessible region of memory and all additional constraints imposed by `advice` as outlined below are also satisfied. Specifying an invalid system-allocated pageable memory range results in an error being returned.

The `advice` parameter can take the following values:

- ▶ [CU_MEM_ADVISE_SET_READ_MAINLY](#): This implies that the data is mostly going to be read from and only occasionally written to. Any read accesses from any processor to this region will create a read-only copy of at least the accessed pages in that processor's memory. Additionally, if [cuMemPrefetchAsync](#) is called on this region, it will create a read-only copy of the data on the destination processor. If any processor writes to this region, all copies of the corresponding page will be invalidated except for the one where the write occurred. The `device` argument is ignored for this advice. Note that for a page to be read-duplicated, the accessing

processor must either be the CPU or a GPU that has a non-zero value for the device attribute [CU_DEVICE_ATTRIBUTE_CONCURRENT_MANAGED_ACCESS](#). Also, if a context is created on a device that does not have the device attribute [CU_DEVICE_ATTRIBUTE_CONCURRENT_MANAGED_ACCESS](#) set, then read-duplication will not occur until all such contexts are destroyed. If the memory region refers to valid system-allocated pageable memory, then the accessing device must have a non-zero value for the device attribute [CU_DEVICE_ATTRIBUTE_PAGEABLE_MEMORY_ACCESS](#) for a read-only copy to be created on that device. Note however that if the accessing device also has a non-zero value for the device attribute [CU_DEVICE_ATTRIBUTE_PAGEABLE_MEMORY_ACCESS_USES_HOST_PAGE_TABLES](#), then setting this advice will not create a read-only copy when that device accesses this memory region.

- ▶ [CU_MEM_ADVISE_UNSET_READ_MOSTLY](#): Undoes the effect of [CU_MEM_ADVISE_SET_READ_MOSTLY](#) and also prevents the Unified Memory driver from attempting heuristic read-duplication on the memory range. Any read-duplicated copies of the data will be collapsed into a single copy. The location for the collapsed copy will be the preferred location if the page has a preferred location and one of the read-duplicated copies was resident at that location. Otherwise, the location chosen is arbitrary.
- ▶ [CU_MEM_ADVISE_SET_PREFERRED_LOCATION](#): This advice sets the preferred location for the data to be the memory belonging to `device`. Passing in `CU_DEVICE_CPU` for `device` sets the preferred location as host memory. If `device` is a GPU, then it must have a non-zero value for the device attribute [CU_DEVICE_ATTRIBUTE_CONCURRENT_MANAGED_ACCESS](#). Setting the preferred location does not cause data to migrate to that location immediately. Instead, it guides the migration policy when a fault occurs on that memory region. If the data is already in its preferred location and the faulting processor can establish a mapping without requiring the data to be migrated, then data migration will be avoided. On the other hand, if the data is not in its preferred location or if a direct mapping cannot be established, then it will be migrated to the processor accessing it. It is important to note that setting the preferred location does not prevent data prefetching done using `cuMemPrefetchAsync`. Having a preferred location can override the page thrash detection and resolution logic in the Unified Memory driver. Normally, if a page is detected to be constantly thrashing between for example host and device memory, the page may eventually be pinned to host memory by the Unified Memory driver. But if the preferred location is set as device memory, then the page will continue to thrash indefinitely. If [CU_MEM_ADVISE_SET_READ_MOSTLY](#) is also set on this memory region or any subset of it, then the policies associated with that advice will override the policies of this advice, unless read accesses from `device` will not result in a read-only copy being created on that device as outlined in description for the advice [CU_MEM_ADVISE_SET_READ_MOSTLY](#). If the memory region refers to valid system-allocated pageable memory, then `device` must have a non-zero value for the device attribute [CU_DEVICE_ATTRIBUTE_PAGEABLE_MEMORY_ACCESS](#). Additionally, if `device` has a non-zero value for the device attribute

- CU_DEVICE_ATTRIBUTE_PAGEABLE_MEMORY_ACCESS_USES_HOST_PAGE_TABLES, then this call has no effect. Note however that this behavior may change in the future.
- ▶ CU_MEM_ADVISE_UNSET_PREFERRED_LOCATION: Undoes the effect of CU_MEM_ADVISE_SET_PREFERRED_LOCATION and changes the preferred location to none.
 - ▶ CU_MEM_ADVISE_SET_ACCESSED_BY: This advice implies that the data will be accessed by `device`. Passing in CU_DEVICE_CPU for `device` will set the advice for the CPU. If `device` is a GPU, then the device attribute CU_DEVICE_ATTRIBUTE_CONCURRENT_MANAGED_ACCESS must be non-zero. This advice does not cause data migration and has no impact on the location of the data per se. Instead, it causes the data to always be mapped in the specified processor's page tables, as long as the location of the data permits a mapping to be established. If the data gets migrated for any reason, the mappings are updated accordingly. This advice is recommended in scenarios where data locality is not important, but avoiding faults is. Consider for example a system containing multiple GPUs with peer-to-peer access enabled, where the data located on one GPU is occasionally accessed by peer GPUs. In such scenarios, migrating data over to the other GPUs is not as important because the accesses are infrequent and the overhead of migration may be too high. But preventing faults can still help improve performance, and so having a mapping set up in advance is useful. Note that on CPU access of this data, the data may be migrated to host memory because the CPU typically cannot access device memory directly. Any GPU that had the CU_MEM_ADVISE_SET_ACCESSED_BY flag set for this data will now have its mapping updated to point to the page in host memory. If CU_MEM_ADVISE_SET_READ_MOSTLY is also set on this memory region or any subset of it, then the policies associated with that advice will override the policies of this advice. Additionally, if the preferred location of this memory region or any subset of it is also `device`, then the policies associated with CU_MEM_ADVISE_SET_PREFERRED_LOCATION will override the policies of this advice. If the memory region refers to valid system-allocated pageable memory, then `device` must have a non-zero value for the device attribute CU_DEVICE_ATTRIBUTE_PAGEABLE_MEMORY_ACCESS. Additionally, if `device` has a non-zero value for the device attribute CU_DEVICE_ATTRIBUTE_PAGEABLE_MEMORY_ACCESS_USES_HOST_PAGE_TABLES, then this call has no effect.
 - ▶ CU_MEM_ADVISE_UNSET_ACCESSED_BY: Undoes the effect of CU_MEM_ADVISE_SET_ACCESSED_BY. Any mappings to the data from `device` may be removed at any time causing accesses to result in non-fatal page faults. If the memory region refers to valid system-allocated pageable memory, then `device` must have a non-zero value for the device attribute CU_DEVICE_ATTRIBUTE_PAGEABLE_MEMORY_ACCESS. Additionally, if `device` has a non-zero value for the device attribute CU_DEVICE_ATTRIBUTE_PAGEABLE_MEMORY_ACCESS_USES_HOST_PAGE_TABLES, then this call has no effect.

**Note:**

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ This function exhibits [asynchronous](#) behavior for most use cases.
- ▶ This function uses standard [default stream](#) semantics.

See also:

[cuMemcpy](#), [cuMemcpyPeer](#), [cuMemcpyAsync](#), [cuMemcpy3DPeerAsync](#), [cuMemPrefetchAsync](#), [cudaMemAdvise](#)

CUresult cuMemPrefetchAsync (CUdeviceptr devPtr, size_t count, CUdevice dstDevice, CUstream hStream)

Prefetches memory to the specified destination device.

Parameters

devPtr

- Pointer to be prefetched

count

- Size in bytes

dstDevice

- Destination device to prefetch to

hStream

- Stream to enqueue prefetch operation

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_DEVICE](#)

Description

Prefetches memory to the specified destination device. `devPtr` is the base device pointer of the memory to be prefetched and `dstDevice` is the destination device. `count` specifies the number of bytes to copy. `hStream` is the stream in which the operation is enqueued. The memory range must refer to managed memory allocated via [cuMemAllocManaged](#) or declared via `__managed__` variables.

Passing in `CU_DEVICE_CPU` for `dstDevice` will prefetch the data to host memory. If `dstDevice` is a GPU, then the device attribute [CU_DEVICE_ATTRIBUTE_CONCURRENT_MANAGED_ACCESS](#) must be non-zero. Additionally, `hStream` must be associated with a device that has a non-zero value for the device attribute [CU_DEVICE_ATTRIBUTE_CONCURRENT_MANAGED_ACCESS](#).

The start address and end address of the memory range will be rounded down and rounded up respectively to be aligned to CPU page size before the prefetch operation is enqueued in the stream.

If no physical memory has been allocated for this region, then this memory region will be populated and mapped on the destination device. If there's insufficient memory to prefetch the desired region, the Unified Memory driver may evict pages from other [cuMemAllocManaged](#) allocations to host memory in order to make room. Device memory allocated using [cuMemAlloc](#) or [cuArrayCreate](#) will not be evicted.

By default, any mappings to the previous location of the migrated pages are removed and mappings for the new location are only setup on `dstDevice`. The exact behavior however also depends on the settings applied to this memory range via [cuMemAdvise](#) as described below:

If [CU_MEM_ADVISE_SET_READ_MOSTLY](#) was set on any subset of this memory range, then that subset will create a read-only copy of the pages on `dstDevice`.

If [CU_MEM_ADVISE_SET_PREFERRED_LOCATION](#) was called on any subset of this memory range, then the pages will be migrated to `dstDevice` even if `dstDevice` is not the preferred location of any pages in the memory range.

If [CU_MEM_ADVISE_SET_ACCESSED_BY](#) was called on any subset of this memory range, then mappings to those pages from all the appropriate processors are updated to refer to the new location if establishing such a mapping is possible. Otherwise, those mappings are cleared.

Note that this API is not required for functionality and only serves to improve performance by allowing the application to migrate data to a suitable location before it is accessed. Memory accesses to this range are always coherent and are allowed even when the data is actively being migrated.

Note that this function is asynchronous with respect to the host and all work on other devices.



Note:

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ This function exhibits [asynchronous](#) behavior for most use cases.
- ▶ This function uses standard [default stream](#) semantics.

See also:

[cuMemcpy](#), [cuMemcpyPeer](#), [cuMemcpyAsync](#), [cuMemcpy3DPeerAsync](#), [cuMemAdvise](#), [cudaMemPrefetchAsync](#)

CUresult cuMemRangeGetAttribute (void *data, size_t dataSize, CUmem_range_attribute attribute, CUdeviceptr devPtr, size_t count)

Query an attribute of a given memory range.

Parameters

data

- A pointers to a memory location where the result of each attribute query will be written to.

dataSize

- Array containing the size of data

attribute

- The attribute to query

devPtr

- Start of the range to query

count

- Size of the range to query

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_DEVICE](#)

Description

Query an attribute about the memory range starting at `devPtr` with a size of `count` bytes. The memory range must refer to managed memory allocated via [cuMemAllocManaged](#) or declared via `__managed__` variables.

The `attribute` parameter can take the following values:

- ▶ [CU_MEM_RANGE_ATTRIBUTE_READ_MOSTLY](#): If this attribute is specified, `data` will be interpreted as a 32-bit integer, and `dataSize` must be 4. The result returned will be 1 if all pages in the given memory range have read-duplication enabled, or 0 otherwise.
- ▶ [CU_MEM_RANGE_ATTRIBUTE_PREFERRED_LOCATION](#): If this attribute is specified, `data` will be interpreted as a 32-bit integer, and `dataSize` must be 4. The result returned will be a GPU device id if all pages in the memory range have that GPU as their preferred location, or it will be `CU_DEVICE_CPU` if all pages in the memory range have the CPU as their preferred location, or it will be `CU_DEVICE_INVALID` if either all the pages don't have the same preferred location or some of the pages don't have a preferred location at all. Note that the actual location of the pages in the memory range at the time of the query may be different from the preferred location.
- ▶ [CU_MEM_RANGE_ATTRIBUTE_ACCESSED_BY](#): If this attribute is specified, `data` will be interpreted as an array of 32-bit integers, and `dataSize` must be a non-zero multiple of 4. The result returned will be a list of device ids that had

[CU_MEM_ADVISE_SET_ACCESSED_BY](#) set for that entire memory range. If any device does not have that advice set for the entire memory range, that device will not be included. If data is larger than the number of devices that have that advice set for that memory range, CU_DEVICE_INVALID will be returned in all the extra space provided. For ex., if dataSize is 12 (i.e. data has 3 elements) and only device 0 has the advice set, then the result returned will be { 0, CU_DEVICE_INVALID, CU_DEVICE_INVALID }. If data is smaller than the number of devices that have that advice set, then only as many devices will be returned as can fit in the array. There is no guarantee on which specific devices will be returned, however.

- ▶ [CU_MEM_RANGE_ATTRIBUTE_LAST_PREFETCH_LOCATION](#): If this attribute is specified, data will be interpreted as a 32-bit integer, and dataSize must be 4. The result returned will be the last location to which all pages in the memory range were prefetched explicitly via [cuMemPrefetchAsync](#). This will either be a GPU id or CU_DEVICE_CPU depending on whether the last location for prefetch was a GPU or the CPU respectively. If any page in the memory range was never explicitly prefetched or if all pages were not prefetched to the same location, CU_DEVICE_INVALID will be returned. Note that this simply returns the last location that the application requested to prefetch the memory range to. It gives no indication as to whether the prefetch operation to that location has completed or even begun.



Note:

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ This function exhibits [asynchronous](#) behavior for most use cases.
- ▶ This function uses standard [default stream](#) semantics.

See also:

[cuMemRangeGetAttributes](#), [cuMemPrefetchAsync](#), [cuMemAdvise](#), [cudaMemRangeGetAttribute](#)

CUresult cuMemRangeGetAttributes (void **data, size_t *dataSizes, CUmem_range_attribute *attributes, size_t numAttributes, CUdeviceptr devPtr, size_t count)

Query attributes of a given memory range.

Parameters

data

- A two-dimensional array containing pointers to memory locations where the result of each attribute query will be written to.

dataSizes

- Array containing the sizes of each result

attributes

- An array of attributes to query (numAttributes and the number of attributes in this array should match)

numAttributes

- Number of attributes to query

devPtr

- Start of the range to query

count

- Size of the range to query

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_DEVICE](#)

Description

Query attributes of the memory range starting at `devPtr` with a size of `count` bytes. The memory range must refer to managed memory allocated via [cuMemAllocManaged](#) or declared via `__managed__` variables. The `attributes` array will be interpreted to have `numAttributes` entries. The `dataSizes` array will also be interpreted to have `numAttributes` entries. The results of the query will be stored in `data`.

The list of supported attributes are given below. Please refer to [cuMemRangeGetAttribute](#) for attribute descriptions and restrictions.

- ▶ [CU_MEM_RANGE_ATTRIBUTE_READ_MOSTLY](#)
- ▶ [CU_MEM_RANGE_ATTRIBUTE_PREFERRED_LOCATION](#)
- ▶ [CU_MEM_RANGE_ATTRIBUTE_ACCESSED_BY](#)
- ▶ [CU_MEM_RANGE_ATTRIBUTE_LAST_PREFETCH_LOCATION](#)

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuMemRangeGetAttribute](#), [cuMemAdvise](#), [cuMemPrefetchAsync](#),
[cudaMemRangeGetAttributes](#)

CUresult cuPointerGetAttribute (void *data, CUpointer_attribute attribute, CUdeviceptr ptr)

Returns information about a pointer.

Parameters

data

- Returned pointer attribute value

attribute

- Pointer attribute to query

ptr

- Pointer

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_INVALID_DEVICE](#)

Description

The supported attributes are:

► [CU_POINTER_ATTRIBUTE_CONTEXT](#):

Returns in *data the [CUcontext](#) in which ptr was allocated or registered. The type of data must be [CUcontext](#) *.

If ptr was not allocated by, mapped by, or registered with a [CUcontext](#) which uses unified virtual addressing then [CUDA_ERROR_INVALID_VALUE](#) is returned.

► [CU_POINTER_ATTRIBUTE_MEMORY_TYPE](#):

Returns in *data the physical memory type of the memory that ptr addresses as a [CUmemorytype](#) enumerated value. The type of data must be unsigned int.

If `ptr` addresses device memory then `*data` is set to `CU_MEMORYTYPE_DEVICE`. The particular `CUdevice` on which the memory resides is the `CUdevice` of the `CUcontext` returned by the `CU_POINTER_ATTRIBUTE_CONTEXT` attribute of `ptr`.

If `ptr` addresses host memory then `*data` is set to `CU_MEMORYTYPE_HOST`.

If `ptr` was not allocated by, mapped by, or registered with a `CUcontext` which uses unified virtual addressing then `CUDA_ERROR_INVALID_VALUE` is returned.

If the current `CUcontext` does not support unified virtual addressing then `CUDA_ERROR_INVALID_CONTEXT` is returned.

► `CU_POINTER_ATTRIBUTE_DEVICE_POINTER`:

Returns in `*data` the device pointer value through which `ptr` may be accessed by kernels running in the current `CUcontext`. The type of `data` must be `CUdeviceptr *`.

If there exists no device pointer value through which kernels running in the current `CUcontext` may access `ptr` then `CUDA_ERROR_INVALID_VALUE` is returned.

If there is no current `CUcontext` then `CUDA_ERROR_INVALID_CONTEXT` is returned.

Except in the exceptional disjoint addressing cases discussed below, the value returned in `*data` will equal the input value `ptr`.

► `CU_POINTER_ATTRIBUTE_HOST_POINTER`:

Returns in `*data` the host pointer value through which `ptr` may be accessed by the host program. The type of `data` must be `void **`. If there exists no host pointer value through which the host program may directly access `ptr` then `CUDA_ERROR_INVALID_VALUE` is returned.

Except in the exceptional disjoint addressing cases discussed below, the value returned in `*data` will equal the input value `ptr`.

► `CU_POINTER_ATTRIBUTE_P2P_TOKENS`:

Returns in `*data` two tokens for use with the `nv-p2p.h` Linux kernel interface. `data` must be a struct of type `CUDA_POINTER_ATTRIBUTE_P2P_TOKENS`.

`ptr` must be a pointer to memory obtained from `:cuMemAlloc()`. Note that `p2pToken` and `vaSpaceToken` are only valid for the lifetime of the source allocation. A subsequent allocation at the same address may return completely different tokens. Querying this attribute has a side effect of setting the attribute `CU_POINTER_ATTRIBUTE_SYNC_MEMOPS` for the region of memory that `ptr` points to.

► `CU_POINTER_ATTRIBUTE_SYNC_MEMOPS`:

A boolean attribute which when set, ensures that synchronous memory operations initiated on the region of memory that `ptr` points to will always synchronize. See further documentation in the section titled "API synchronization behavior" to learn more about cases when synchronous memory operations can exhibit asynchronous behavior.

► `CU_POINTER_ATTRIBUTE_BUFFER_ID`:

Returns in `*data` a buffer ID which is guaranteed to be unique within the process. `data` must point to an unsigned long long.

`ptr` must be a pointer to memory obtained from a CUDA memory allocation API. Every memory allocation from any of the CUDA memory allocation APIs will have a unique ID over a process lifetime. Subsequent allocations do not reuse IDs from previous freed allocations. IDs are only unique within a single process.

► [CU_POINTER_ATTRIBUTE_IS_MANAGED:](#)

Returns in `*data` a boolean that indicates whether the pointer points to managed memory or not.

If `ptr` is not a valid CUDA pointer then [CUDA_ERROR_INVALID_VALUE](#) is returned.

► [CU_POINTER_ATTRIBUTE_DEVICE_ORDINAL:](#)

Returns in `*data` an integer representing a device ordinal of a device against which the memory was allocated or registered.

► [CU_POINTER_ATTRIBUTE_IS_LEGACY_CUDA_IPC_CAPABLE:](#)

Returns in `*data` a boolean that indicates if this pointer maps to an allocation that is suitable for [cudaIpcGetMemHandle](#).

► [CU_POINTER_ATTRIBUTE_RANGE_START_ADDR:](#)

Returns in `*data` the starting address for the allocation referenced by the device pointer `ptr`. Note that this is not necessarily the address of the mapped region, but the address of the mappable address range `ptr` references (e.g. from [cuMemAddressReserve](#)).

► [CU_POINTER_ATTRIBUTE_RANGE_SIZE:](#)

Returns in `*data` the size for the allocation referenced by the device pointer `ptr`. Note that this is not necessarily the size of the mapped region, but the size of the mappable address range `ptr` references (e.g. from [cuMemAddressReserve](#)). To retrieve the size of the mapped region, see [cuMemGetAddressRange](#)

► [CU_POINTER_ATTRIBUTE_MAPPED:](#)

Returns in `*data` a boolean that indicates if this pointer is in a valid address range that is mapped to a backing allocation.

► [CU_POINTER_ATTRIBUTE_ALLOWED_HANDLE_TYPES:](#)

Returns a bitmask of the allowed handle types for an allocation that may be passed to [cuMemExportToShareableHandle](#).

► [CU_POINTER_ATTRIBUTE_MEMPOOL_HANDLE:](#)

Returns in `*data` the handle to the mempool that the allocation was obtained from.

Note that for most allocations in the unified virtual address space the host and device pointer for accessing the allocation will be the same. The exceptions to this are

- ▶ user memory registered using [cuMemHostRegister](#)
- ▶ host memory allocated using [cuMemHostAlloc](#) with the [CU_MEMHOSTALLOC_WRITECOMBINED](#) flag For these types of allocation there will exist separate, disjoint host and device addresses for accessing the allocation. In particular
- ▶ The host address will correspond to an invalid unmapped device address (which will result in an exception if accessed from the device)
- ▶ The device address will correspond to an invalid unmapped host address (which will result in an exception if accessed from the host). For these types of allocations, querying [CU_POINTER_ATTRIBUTE_HOST_POINTER](#) and [CU_POINTER_ATTRIBUTE_DEVICE_POINTER](#) may be used to retrieve the host and device addresses from either address.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuPointerSetAttribute](#), [cuMemAlloc](#), [cuMemFree](#), [cuMemAllocHost](#), [cuMemFreeHost](#), [cuMemHostAlloc](#), [cuMemHostRegister](#), [cuMemHostUnregister](#), [cudaPointerGetAttributes](#)

CUresult cuPointerGetAttributes (unsigned int numAttributes, CUpointer_attribute *attributes, void **data, CUdeviceptr ptr)

Returns information about a pointer.

Parameters

numAttributes

- Number of attributes to query

attributes

- An array of attributes to query (numAttributes and the number of attributes in this array should match)

data

- A two-dimensional array containing pointers to memory locations where the result of each attribute query will be written to.

ptr

- Pointer to query

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_DEVICE](#)

Description

The supported attributes are (refer to [cuPointerGetAttribute](#) for attribute descriptions and restrictions):

- ▶ [CU_POINTER_ATTRIBUTE_CONTEXT](#)
- ▶ [CU_POINTER_ATTRIBUTE_MEMORY_TYPE](#)
- ▶ [CU_POINTER_ATTRIBUTE_DEVICE_POINTER](#)
- ▶ [CU_POINTER_ATTRIBUTE_HOST_POINTER](#)
- ▶ [CU_POINTER_ATTRIBUTE_SYNC_MEMOPS](#)
- ▶ [CU_POINTER_ATTRIBUTE_BUFFER_ID](#)
- ▶ [CU_POINTER_ATTRIBUTE_IS_MANAGED](#)
- ▶ [CU_POINTER_ATTRIBUTE_DEVICE_ORDINAL](#)
- ▶ [CU_POINTER_ATTRIBUTE_RANGE_START_ADDR](#)
- ▶ [CU_POINTER_ATTRIBUTE_RANGE_SIZE](#)
- ▶ [CU_POINTER_ATTRIBUTE_MAPPED](#)
- ▶ [CU_POINTER_ATTRIBUTE_IS_LEGACY_CUDA_IPC_CAPABLE](#)
- ▶ [CU_POINTER_ATTRIBUTE_ALLOWED_HANDLE_TYPES](#)
- ▶ [CU_POINTER_ATTRIBUTE_MEMPOOL_HANDLE](#)

Unlike [cuPointerGetAttribute](#), this function will not return an error when the `ptr` encountered is not a valid CUDA pointer. Instead, the attributes are assigned default NULL values and `CUDA_SUCCESS` is returned.

If `ptr` was not allocated by, mapped by, or registered with a [CUcontext](#) which uses UVA (Unified Virtual Addressing), [CUDA_ERROR_INVALID_CONTEXT](#) is returned.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuPointerGetAttribute](#), [cuPointerSetAttribute](#), [cudaPointerGetAttributes](#)

CUresult cuPointerSetAttribute (const void *value, CUpointer_attribute attribute, CUdeviceptr ptr)

Set attributes on a previously allocated memory region.

Parameters

value

- Pointer to memory containing the value to be set

attribute

- Pointer attribute to set

ptr

- Pointer to a memory region allocated using CUDA memory allocation APIs

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_DEVICE](#)

Description

The supported attributes are:

► [CU_POINTER_ATTRIBUTE_SYNC_MEMOPS](#):

A boolean attribute that can either be set (1) or unset (0). When set, the region of memory that `ptr` points to is guaranteed to always synchronize memory operations that are synchronous. If there are some previously initiated synchronous memory operations that are pending when this attribute is set, the function does not return until those memory operations are complete. See further documentation in the section titled "API synchronization behavior" to learn more about cases when synchronous memory operations can exhibit asynchronous behavior. `value` will be considered as a pointer to an unsigned integer to which this attribute is to be set.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuPointerGetAttribute](#), [cuPointerGetAttributes](#), [cuMemAlloc](#), [cuMemFree](#), [cuMemAllocHost](#), [cuMemFreeHost](#), [cuMemHostAlloc](#), [cuMemHostRegister](#), [cuMemHostUnregister](#)

6.15. Stream Management

This section describes the stream management functions of the low-level CUDA driver application programming interface.

CUresult cuStreamAddCallback (CUstream hStream, CUstreamCallback callback, void *userData, unsigned int flags)

Add a callback to a compute stream.

Parameters

hStream

- Stream to add callback to

callback

- The function to call once preceding stream operations are complete

userData

- User specified data to be passed to the callback function

flags

- Reserved for future use, must be 0

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_NOT_SUPPORTED](#)

Description



Note:

This function is slated for eventual deprecation and removal. If you do not require the callback to execute in case of a device error, consider using [cuLaunchHostFunc](#). Additionally, this function is not supported with [cuStreamBeginCapture](#) and [cuStreamEndCapture](#), unlike [cuLaunchHostFunc](#).

Adds a callback to be called on the host after all currently enqueued items in the stream have completed. For each [cuStreamAddCallback](#) call, the callback will be executed exactly once. The callback will block later work in the stream until it is finished.

The callback may be passed [CUDA_SUCCESS](#) or an error code. In the event of a device error, all subsequently executed callbacks will receive an appropriate [CUresult](#).

Callbacks must not make any CUDA API calls. Attempting to use a CUDA API will result in [CUDA_ERROR_NOT_PERMITTED](#). Callbacks must not perform any synchronization that may depend on outstanding device work or other callbacks that are not mandated to run earlier. Callbacks without a mandated order (in independent streams) execute in undefined order and may be serialized.

For the purposes of Unified Memory, callback execution makes a number of guarantees:

- ▶ The callback stream is considered idle for the duration of the callback. Thus, for example, a callback may always use memory attached to the callback stream.
- ▶ The start of execution of a callback has the same effect as synchronizing an event recorded in the same stream immediately prior to the callback. It thus synchronizes streams which have been "joined" prior to the callback.
- ▶ Adding device work to any stream does not have the effect of making the stream active until all preceding host functions and stream callbacks have executed. Thus, for example, a callback might use global attached memory even if work has been added to another stream, if the work has been ordered behind the callback with an event.
- ▶ Completion of a callback does not cause a stream to become active except as described above. The callback stream will remain idle if no device work follows the callback, and will remain idle across consecutive callbacks without device work in between. Thus, for example, stream synchronization can be done by signaling from a callback at the end of the stream.

**Note:**

- ▶ This function uses standard [default stream](#) semantics.
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuStreamCreate](#), [cuStreamQuery](#), [cuStreamSynchronize](#), [cuStreamWaitEvent](#), [cuStreamDestroy](#), [cuMemAllocManaged](#), [cuStreamAttachMemAsync](#), [cuStreamLaunchHostFunc](#), [cudaStreamAddCallback](#)

CUresult cuStreamAttachMemAsync (CUstream hStream, CUdeviceptr dptr, size_t length, unsigned int flags)

Attach memory to a stream asynchronously.

Parameters

hStream

- Stream in which to enqueue the attach operation

dptr

- Pointer to memory (must be a pointer to managed memory or to a valid host-accessible region of system-allocated pageable memory)

length

- Length of memory

flags

- Must be one of [CUmemAttach_flags](#)

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_NOT_SUPPORTED](#)

Description

Enqueues an operation in `hStream` to specify stream association of `length` bytes of memory starting from `dptr`. This function is a stream-ordered operation, meaning that it is dependent on, and will only take effect when, previous work in stream has completed. Any previous association is automatically replaced.

`dptr` must point to one of the following types of memories:

- ▶ managed memory declared using the `__managed__` keyword or allocated with [cuMemAllocManaged](#).
- ▶ a valid host-accessible region of system-allocated pageable memory. This type of memory may only be specified if the device associated with the stream reports a non-zero value for the device attribute [CU_DEVICE_ATTRIBUTE_PAGEABLE_MEMORY_ACCESS](#).

For managed allocations, `length` must be either zero or the entire allocation's size. Both indicate that the entire allocation's stream association is being changed. Currently, it is not possible to change stream association for a portion of a managed allocation.

For pageable host allocations, `length` must be non-zero.

The stream association is specified using `flags` which must be one of [CUmemAttach_flags](#). If the [CU_MEM_ATTACH_GLOBAL](#) flag is specified, the memory

can be accessed by any stream on any device. If the [CU_MEM_ATTACH_HOST](#) flag is specified, the program makes a guarantee that it won't access the memory on the device from any stream on a device that has a zero value for the device attribute [CU_DEVICE_ATTRIBUTE_CONCURRENT_MANAGED_ACCESS](#). If the [CU_MEM_ATTACH_SINGLE](#) flag is specified and `hStream` is associated with a device that has a zero value for the device attribute [CU_DEVICE_ATTRIBUTE_CONCURRENT_MANAGED_ACCESS](#), the program makes a guarantee that it will only access the memory on the device from `hStream`. It is illegal to attach singly to the NULL stream, because the NULL stream is a virtual global stream and not a specific stream. An error will be returned in this case.

When memory is associated with a single stream, the Unified Memory system will allow CPU access to this memory region so long as all operations in `hStream` have completed, regardless of whether other streams are active. In effect, this constrains exclusive ownership of the managed memory region by an active GPU to per-stream activity instead of whole-GPU activity.

Accessing memory on the device from streams that are not associated with it will produce undefined results. No error checking is performed by the Unified Memory system to ensure that kernels launched into other streams do not access this region.

It is a program's responsibility to order calls to [cuStreamAttachMemAsync](#) via events, synchronization or other means to ensure legal access to memory at all times. Data visibility and coherency will be changed appropriately for all kernels which follow a stream-association change.

If `hStream` is destroyed while data is associated with it, the association is removed and the association reverts to the default visibility of the allocation as specified at [cuMemAllocManaged](#). For `__managed__` variables, the default association is always [CU_MEM_ATTACH_GLOBAL](#). Note that destroying a stream is an asynchronous operation, and as a result, the change to default association won't happen until all work in the stream has completed.



Note:

- ▶ This function uses standard [default stream](#) semantics.
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuStreamCreate](#), [cuStreamQuery](#), [cuStreamSynchronize](#), [cuStreamWaitEvent](#), [cuStreamDestroy](#), [cuMemAllocManaged](#), [cudaStreamAttachMemAsync](#)

CUresult cuStreamBeginCapture (CUstream hStream, CUstreamCaptureMode mode)

Begins graph capture on a stream.

Parameters

hStream

- Stream in which to initiate capture

mode

- Controls the interaction of this capture sequence with other API calls that are potentially unsafe. For more details see [cuThreadExchangeStreamCaptureMode](#).

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Begin graph capture on `hStream`. When a stream is in capture mode, all operations pushed into the stream will not be executed, but will instead be captured into a graph, which will be returned via [cuStreamEndCapture](#). Capture may not be initiated if `stream` is `CU_STREAM_LEGACY`. Capture must be ended on the same stream in which it was initiated, and it may only be initiated if the stream is not already in capture mode. The capture mode may be queried via [cuStreamIsCapturing](#). A unique id representing the capture sequence may be queried via [cuStreamGetCaptureInfo](#).

If `mode` is not `CU_STREAM_CAPTURE_MODE_RELAXED`, [cuStreamEndCapture](#) must be called on this stream from the same thread.



Note:

Kernels captured using this API must not use texture and surface references. Reading or writing through any texture or surface reference is undefined behavior. This restriction does not apply to texture and surface objects.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuStreamCreate](#), [cuStreamIsCapturing](#), [cuStreamEndCapture](#), [cuThreadExchangeStreamCaptureMode](#)

CUresult cuStreamCopyAttributes (CUstream dst, CUstream src)

Copies attributes from source stream to destination stream.

Parameters

dst

Destination stream

src

Source stream For list of attributes see [CUstreamAttrID](#)

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Copies attributes from source stream `src` to destination stream `dst`. Both streams must have the same context.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[CUaccessPolicyWindow](#)

CUresult cuStreamCreate (CUstream *phStream, unsigned int Flags)

Create a stream.

Parameters

phStream

- Returned newly created stream

Flags

- Parameters for stream creation

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_OUT_OF_MEMORY](#)

Description

Creates a stream and returns a handle in `phStream`. The `Flags` argument determines behaviors of the stream.

Valid values for `Flags` are:

- ▶ [CU_STREAM_DEFAULT](#): Default stream creation flag.
- ▶ [CU_STREAM_NON_BLOCKING](#): Specifies that work running in the created stream may run concurrently with work in stream 0 (the NULL stream), and that the created stream should perform no implicit synchronization with stream 0.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuStreamDestroy](#), [cuStreamCreateWithPriority](#), [cuStreamGetPriority](#), [cuStreamGetFlags](#), [cuStreamWaitEvent](#), [cuStreamQuery](#), [cuStreamSynchronize](#), [cuStreamAddCallback](#), [cudaStreamCreate](#), [cudaStreamCreateWithFlags](#)

CUresult cuStreamCreateWithPriority (CUstream *phStream, unsigned int flags, int priority)

Create a stream with the given priority.

Parameters

phStream

- Returned newly created stream

flags

- Flags for stream creation. See [cuStreamCreate](#) for a list of valid flags

priority

- Stream priority. Lower numbers represent higher priorities. See [cuCtxGetStreamPriorityRange](#) for more information about meaningful stream priorities that can be passed.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_OUT_OF_MEMORY](#)

Description

Creates a stream with the specified priority and returns a handle in `phStream`. This API alters the scheduler priority of work in the stream. Work in a higher priority stream may preempt work already executing in a low priority stream.

`priority` follows a convention where lower numbers represent higher priorities. '0' represents default priority. The range of meaningful numerical priorities can be queried using [cuCtxGetStreamPriorityRange](#). If the specified priority is outside the numerical range returned by [cuCtxGetStreamPriorityRange](#), it will automatically be clamped to the lowest or the highest number in the range.



Note:

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ Stream priorities are supported only on GPUs with compute capability 3.5 or higher.
- ▶ In the current implementation, only compute kernels launched in priority streams are affected by the stream's priority. Stream priorities have no effect on host-to-device and device-to-host memory operations.

See also:

[cuStreamDestroy](#), [cuStreamCreate](#), [cuStreamGetPriority](#), [cuCtxGetStreamPriorityRange](#), [cuStreamGetFlags](#), [cuStreamWaitEvent](#), [cuStreamQuery](#), [cuStreamSynchronize](#), [cuStreamAddCallback](#), [cudaStreamCreateWithPriority](#)

CUresult cuStreamDestroy (CUstream hStream)

Destroys a stream.

Parameters

hStream

- Stream to destroy

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_HANDLE](#)

Description

Destroys the stream specified by `hStream`.

In case the device is still doing work in the stream `hStream` when [cuStreamDestroy\(\)](#) is called, the function will return immediately and the resources associated with `hStream` will be released automatically once the device has completed all work in `hStream`.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuStreamCreate](#), [cuStreamWaitEvent](#), [cuStreamQuery](#), [cuStreamSynchronize](#),
[cuStreamAddCallback](#), [cudaStreamDestroy](#)

CUresult cuStreamEndCapture (CUstream hStream, CUgraph *phGraph)

Ends capture on a stream, returning the captured graph.

Parameters

hStream

- Stream to query

phGraph

- The captured graph

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_STREAM_CAPTURE_WRONG_THREAD](#)

Description

End capture on `hStream`, returning the captured graph via `phGraph`. Capture must have been initiated on `hStream` via a call to [cuStreamBeginCapture](#). If capture was invalidated, due to a violation of the rules of stream capture, then a NULL graph will be returned.

If the `mode` argument to [cuStreamBeginCapture](#) was not `CU_STREAM_CAPTURE_MODE_RELAXED`, this call must be from the same thread as [cuStreamBeginCapture](#).

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuStreamCreate](#), [cuStreamBeginCapture](#), [cuStreamIsCapturing](#)

CUresult cuStreamGetAttribute (CUstream hStream, CUstreamAttrID attr, CUstreamAttrValue *value_out)

Queries stream attribute.

Parameters

hStream

attr

value_out

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_HANDLE](#)

Description

Queries attribute `attr` from `hStream` and stores it in corresponding member of `value_out`.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[CUaccessPolicyWindow](#)

CUresult cuStreamGetCaptureInfo (CUstream hStream, CUstreamCaptureStatus *captureStatus_out, cuuint64_t *id_out)

Query capture status of a stream.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_STREAM_CAPTURE_IMPLICIT](#)

Description

Note there is a later version of this API, [cuStreamGetCaptureInfo_v2](#). It will supplant this version in 12.0, which is retained for minor version compatibility.

Query the capture status of a stream and get an id for the capture sequence, which is unique over the lifetime of the process.

If called on [CU_STREAM_LEGACY](#) (the "null stream") while a stream not created with [CU_STREAM_NON_BLOCKING](#) is capturing, returns [CUDA_ERROR_STREAM_CAPTURE_IMPLICIT](#).

A valid id is returned only if both of the following are true:

- ▶ the call returns `CUDA_SUCCESS`
- ▶ `captureStatus` is set to [CU_STREAM_CAPTURE_STATUS_ACTIVE](#)



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuStreamGetCaptureInfo_v2](#), [cuStreamBeginCapture](#), [cuStreamIsCapturing](#)

CUresult cuStreamGetCaptureInfo_v2
(CUstream hStream, CUstreamCaptureStatus
***captureStatus_out, cuuint64_t *id_out, CUgraph**
***graph_out, const CUGraphNode **dependencies_out,**
size_t *numDependencies_out)

Query a stream's capture state (11.3+).

Parameters

hStream

- The stream to query

captureStatus_out

- Location to return the capture status of the stream; required

id_out

- Optional location to return an id for the capture sequence, which is unique over the lifetime of the process

graph_out

- Optional location to return the graph being captured into. All operations other than destroy and node removal are permitted on the graph while the capture sequence is in progress. This API does not transfer ownership of the graph, which is transferred or destroyed at [cuStreamEndCapture](#). Note that the graph handle may be invalidated before end of capture for certain errors. Nodes that are or become unreachable from the original stream at [cuStreamEndCapture](#) due to direct actions on the graph do not trigger [CUDA_ERROR_STREAM_CAPTURE_UNJOINED](#).

dependencies_out

- Optional location to store a pointer to an array of nodes. The next node to be captured in the stream will depend on this set of nodes, absent operations such as event wait which modify this set. The array pointer is valid until the next API call which operates on the stream or until end of capture. The node handles may be copied out and are valid until they or the graph is destroyed. The driver-owned array may also be passed directly to APIs that operate on the graph (not the stream) without copying.

numDependencies_out

- Optional location to store the size of the array returned in dependencies_out.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_STREAM_CAPTURE_IMPLICIT](#)

Description

Query stream state related to stream capture.

If called on [CU_STREAM_LEGACY](#) (the "null stream") while a stream not created with [CU_STREAM_NON_BLOCKING](#) is capturing, returns [CUDA_ERROR_STREAM_CAPTURE_IMPLICIT](#).

Valid data (other than capture status) is returned only if both of the following are true:

- ▶ the call returns [CUDA_SUCCESS](#)
- ▶ the returned capture status is [CU_STREAM_CAPTURE_STATUS_ACTIVE](#)

This version of [cuStreamGetCaptureInfo](#) is introduced in CUDA 11.3 and will supplant the previous version in 12.0. Developers requiring compatibility across minor versions to CUDA 11.0 (driver version 445) should use [cuStreamGetCaptureInfo](#) or include a fallback path.

**Note:**

- ▶ Graph objects are not threadsafe. [More here](#).
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuStreamGetCaptureInfo](#), [cuStreamBeginCapture](#), [cuStreamIsCapturing](#),
[cuStreamUpdateCaptureDependencies](#)

CUresult cuStreamGetCtx (CUstream hStream, CUcontext *pctx)

Query the context associated with a stream.

Parameters

hStream

- Handle to the stream to be queried

pctx

- Returned context associated with the stream

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_HANDLE](#),

Description

Returns the CUDA context that the stream is associated with.

The stream handle `hStream` can refer to any of the following:

- ▶ a stream created via any of the CUDA driver APIs such as [cuStreamCreate](#) and [cuStreamCreateWithPriority](#), or their runtime API equivalents such as [cudaStreamCreate](#), [cudaStreamCreateWithFlags](#) and [cudaStreamCreateWithPriority](#). The returned context is the context that was active in the calling thread when the stream was created. Passing an invalid handle will result in undefined behavior.
- ▶ any of the special streams such as the NULL stream, [CU_STREAM_LEGACY](#) and [CU_STREAM_PER_THREAD](#). The runtime API equivalents of these are also accepted, which are NULL, [cudaStreamLegacy](#) and [cudaStreamPerThread](#) respectively. Specifying any of the special handles will return the context current to the calling thread. If no context is current to the calling thread, [CUDA_ERROR_INVALID_CONTEXT](#) is returned.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuStreamDestroy](#), [cuStreamCreateWithPriority](#), [cuStreamGetPriority](#), [cuStreamGetFlags](#), [cuStreamWaitEvent](#), [cuStreamQuery](#), [cuStreamSynchronize](#), [cuStreamAddCallback](#), [cudaStreamCreate](#), [cudaStreamCreateWithFlags](#)

CUresult cuStreamGetFlags (CUstream hStream, unsigned int *flags)

Query the flags of a given stream.

Parameters

hStream

- Handle to the stream to be queried

flags

- Pointer to an unsigned integer in which the stream's flags are returned. The value returned in `flags` is a logical 'OR' of all flags that were used while creating this stream. See [cuStreamCreate](#) for the list of valid flags.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_OUT_OF_MEMORY](#)

Description

Query the flags of a stream created using [cuStreamCreate](#) or [cuStreamCreateWithPriority](#) and return the flags in `flags`.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuStreamDestroy](#), [cuStreamCreate](#), [cuStreamGetPriority](#), [cudaStreamGetFlags](#)

CUresult cuStreamGetPriority (CUstream hStream, int *priority)

Query the priority of a given stream.

Parameters

hStream

- Handle to the stream to be queried

priority

- Pointer to a signed integer in which the stream's priority is returned

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_OUT_OF_MEMORY](#)

Description

Query the priority of a stream created using [cuStreamCreate](#) or [cuStreamCreateWithPriority](#) and return the priority in `priority`. Note that if the stream was created with a priority outside the numerical range returned by [cuCtxGetStreamPriorityRange](#), this function returns the clamped priority. See [cuStreamCreateWithPriority](#) for details about priority clamping.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuStreamDestroy](#), [cuStreamCreate](#), [cuStreamCreateWithPriority](#),
[cuCtxGetStreamPriorityRange](#), [cuStreamGetFlags](#), [cudaStreamGetPriority](#)

CUresult cuStreamIsCapturing (CUstream hStream, CUstreamCaptureStatus *captureStatus)

Returns a stream's capture status.

Parameters

hStream

- Stream to query

captureStatus

- Returns the stream's capture status

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_STREAM_CAPTURE_IMPLICIT](#)

Description

Return the capture status of `hStream` via `captureStatus`. After a successful call, `*captureStatus` will contain one of the following:

- ▶ [CU_STREAM_CAPTURE_STATUS_NONE](#): The stream is not capturing.
- ▶ [CU_STREAM_CAPTURE_STATUS_ACTIVE](#): The stream is capturing.

- ▶ [CU_STREAM_CAPTURE_STATUS_INVALIDATED](#): The stream was capturing but an error has invalidated the capture sequence. The capture sequence must be terminated with [cuStreamEndCapture](#) on the stream where it was initiated in order to continue using `hStream`.

Note that, if this is called on [CU_STREAM_LEGACY](#) (the "null stream") while a blocking stream in the same context is capturing, it will return [CUDA_ERROR_STREAM_CAPTURE_IMPLICIT](#) and `*captureStatus` is unspecified after the call. The blocking stream capture is not invalidated.

When a blocking stream is capturing, the legacy stream is in an unusable state until the blocking stream capture is terminated. The legacy stream is not supported for stream capture, but attempted use would have an implicit dependency on the capturing stream(s).

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuStreamCreate](#), [cuStreamBeginCapture](#), [cuStreamEndCapture](#)

CUresult cuStreamQuery (CUstream hStream)

Determine status of a compute stream.

Parameters

hStream

- Stream to query status of

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_NOT_READY](#)

Description

Returns [CUDA_SUCCESS](#) if all operations in the stream specified by `hStream` have completed, or [CUDA_ERROR_NOT_READY](#) if not.

For the purposes of Unified Memory, a return value of [CUDA_SUCCESS](#) is equivalent to having called [cuStreamSynchronize\(\)](#).

**Note:**

- ▶ This function uses standard [default stream](#) semantics.
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuStreamCreate](#), [cuStreamWaitEvent](#), [cuStreamDestroy](#), [cuStreamSynchronize](#),
[cuStreamAddCallback](#), [cudaStreamQuery](#)

CUresult cuStreamSetAttribute (CUstream hStream, CUstreamAttrID attr, const CUstreamAttrValue *value)

Sets stream attribute.

Parameters

hStream
attr
value

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_HANDLE](#)

Description

Sets attribute `attr` on `hStream` from corresponding attribute of `value`. The updated attribute will be applied to subsequent work submitted to the stream. It will not affect previously submitted work.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[CUaccessPolicyWindow](#)

CUresult cuStreamSynchronize (CUstream hStream)

Wait until a stream's tasks are completed.

Parameters


hStream
 - Stream to wait for

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_HANDLE](#)

Description

Waits until the device has completed all operations in the stream specified by `hStream`. If the context was created with the [CU_CTX_SCHED_BLOCKING_SYNC](#) flag, the CPU thread will block until the stream is finished with all of its tasks.



Note:

- ▶ This function uses standard [default stream](#) semantics.
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuStreamCreate](#), [cuStreamDestroy](#), [cuStreamWaitEvent](#), [cuStreamQuery](#),
[cuStreamAddCallback](#), [cudaStreamSynchronize](#)

CUresult cuStreamUpdateCaptureDependencies (CUstream hStream, CUGraphNode *dependencies, size_t numDependencies, unsigned int flags)

Update the set of dependencies in a capturing stream (11.3+).

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_ILLEGAL_STATE](#)

Description

Modifies the dependency set of a capturing stream. The dependency set is the set of nodes that the next captured node in the stream will depend on.

Valid flags are [CU_STREAM_ADD_CAPTURE_DEPENDENCIES](#) and [CU_STREAM_SET_CAPTURE_DEPENDENCIES](#). These control whether the set passed to the API is added to the existing set or replaces it. A flags value of 0 defaults to [CU_STREAM_ADD_CAPTURE_DEPENDENCIES](#).

Nodes that are removed from the dependency set via this API do not result in [CUDA_ERROR_STREAM_CAPTURE_UNJOINED](#) if they are unreachable from the stream at [cuStreamEndCapture](#).

Returns [CUDA_ERROR_ILLEGAL_STATE](#) if the stream is not capturing.

This API is new in CUDA 11.3. Developers requiring compatibility across minor versions to CUDA 11.0 should not use this API or provide a fallback.

See also:

[cuStreamBeginCapture](#), [cuStreamGetCaptureInfo](#), [cuStreamGetCaptureInfo_v2](#)

CUresult cuStreamWaitEvent (CUstream hStream, CUevent hEvent, unsigned int Flags)

Make a compute stream wait on an event.

Parameters

hStream

- Stream to wait

hEvent

- Event to wait on (may not be NULL)

Flags

- See [CUevent_capture_flags](#)

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_HANDLE](#),

Description

Makes all future work submitted to `hStream` wait for all work captured in `hEvent`. See [cuEventRecord\(\)](#) for details on what is captured by an event. The synchronization will be performed efficiently on the device when applicable. `hEvent` may be from a different context or device than `hStream`.

flags include:

- ▶ [CU_EVENT_WAIT_DEFAULT](#): Default event creation flag.
- ▶ [CU_EVENT_WAIT_EXTERNAL](#): Event is captured in the graph as an external event node when performing stream capture. This flag is invalid outside of stream capture.



Note:

- ▶ This function uses standard [default stream](#) semantics.
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuStreamCreate](#), [cuEventRecord](#), [cuStreamQuery](#), [cuStreamSynchronize](#),
[cuStreamAddCallback](#), [cuStreamDestroy](#), [cudaStreamWaitEvent](#)

CUresult cuThreadExchangeStreamCaptureMode (CUstreamCaptureMode *mode)

Swaps the stream capture interaction mode for a thread.

Parameters

mode

- Pointer to mode value to swap with the current mode

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_VALUE](#)

Description

Sets the calling thread's stream capture interaction mode to the value contained in *mode, and overwrites *mode with the previous mode for the thread. To facilitate deterministic behavior across function or module boundaries, callers are encouraged to use this API in a push-pop fashion:

```
↑
    CUstreamCaptureMode mode = desiredMode;
    cuThreadExchangeStreamCaptureMode (&mode);
    ...
    cuThreadExchangeStreamCaptureMode (&mode); // restore previous mode
```

During stream capture (see [cuStreamBeginCapture](#)), some actions, such as a call to [cudaMalloc](#), may be unsafe. In the case of [cudaMalloc](#), the operation is not enqueued asynchronously to a stream, and is not observed by stream capture. Therefore, if the sequence of operations captured via [cuStreamBeginCapture](#) depended on the allocation being replayed whenever the graph is launched, the captured graph would be invalid.

Therefore, stream capture places restrictions on API calls that can be made within or concurrently to a [cuStreamBeginCapture-cuStreamEndCapture](#) sequence. This behavior can be controlled via this API and flags to [cuStreamBeginCapture](#).

A thread's mode is one of the following:

- ▶ **CU_STREAM_CAPTURE_MODE_GLOBAL**: This is the default mode. If the local thread has an ongoing capture sequence that was not initiated with **CU_STREAM_CAPTURE_MODE_RELAXED** at [cuStreamBeginCapture](#), or if any other thread has a concurrent capture sequence initiated with **CU_STREAM_CAPTURE_MODE_GLOBAL**, this thread is prohibited from potentially unsafe API calls.
- ▶ **CU_STREAM_CAPTURE_MODE_THREAD_LOCAL**: If the local thread has an ongoing capture sequence not initiated with **CU_STREAM_CAPTURE_MODE_RELAXED**, it is

prohibited from potentially unsafe API calls. Concurrent capture sequences in other threads are ignored.

- ▶ **CU_STREAM_CAPTURE_MODE_RELAXED:** The local thread is not prohibited from potentially unsafe API calls. Note that the thread is still prohibited from API calls which necessarily conflict with stream capture, for example, attempting [cuEventQuery](#) on an event that was last recorded inside a capture sequence.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuStreamBeginCapture](#)

6.16. Event Management

This section describes the event management functions of the low-level CUDA driver application programming interface.

CUresult cuEventCreate (CUevent *phEvent, unsigned int Flags)

Creates an event.

Parameters

phEvent

- Returns newly created event

Flags

- Event creation flags

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_OUT_OF_MEMORY](#)

Description

Creates an event *phEvent for the current context with the flags specified via Flags. Valid flags include:

- ▶ [CU_EVENT_DEFAULT](#): Default event creation flag.

- ▶ [CU_EVENT_BLOCKING_SYNC](#): Specifies that the created event should use blocking synchronization. A CPU thread that uses [cuEventSynchronize\(\)](#) to wait on an event created with this flag will block until the event has actually been recorded.
- ▶ [CU_EVENT_DISABLE_TIMING](#): Specifies that the created event does not need to record timing data. Events created with this flag specified and the [CU_EVENT_BLOCKING_SYNC](#) flag not specified will provide the best performance when used with [cuStreamWaitEvent\(\)](#) and [cuEventQuery\(\)](#).
- ▶ [CU_EVENT_INTERPROCESS](#): Specifies that the created event may be used as an interprocess event by [culpcGetEventHandle\(\)](#). [CU_EVENT_INTERPROCESS](#) must be specified along with [CU_EVENT_DISABLE_TIMING](#).

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuEventRecord](#), [cuEventQuery](#), [cuEventSynchronize](#), [cuEventDestroy](#), [cuEventElapsedTime](#), [cudaEventCreate](#), [cudaEventCreateWithFlags](#)

CUresult cuEventDestroy (CUevent hEvent)

Destroys an event.

Parameters

hEvent

- Event to destroy

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_HANDLE](#)

Description

Destroys the event specified by `hEvent`.

An event may be destroyed before it is complete (i.e., while [cuEventQuery\(\)](#) would return [CUDA_ERROR_NOT_READY](#)). In this case, the call does not block on completion of the event, and any associated resources will automatically be released asynchronously at completion.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuEventCreate](#), [cuEventRecord](#), [cuEventQuery](#), [cuEventSynchronize](#), [cuEventElapsedTime](#), [cudaEventDestroy](#)

CUresult cuEventElapsedTime (float *pMilliseconds, CUevent hStart, CUevent hEnd)

Computes the elapsed time between two events.

Parameters

pMilliseconds

- Time between hStart and hEnd in ms

hStart

- Starting event

hEnd

- Ending event

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_NOT_READY](#)

Description

Computes the elapsed time between two events (in milliseconds with a resolution of around 0.5 microseconds).

If either event was last recorded in a non-NULL stream, the resulting time may be greater than expected (even if both used the same stream handle). This happens because the [cuEventRecord\(\)](#) operation takes place asynchronously and there is no guarantee that the measured latency is actually just between the two events. Any number of other different stream operations could execute in between the two measured events, thus altering the timing in a significant way.

If [cuEventRecord\(\)](#) has not been called on either event then [CUDA_ERROR_INVALID_HANDLE](#) is returned. If [cuEventRecord\(\)](#) has been called on both events but one or both of them has not yet been completed (that is, [cuEventQuery\(\)](#) would return [CUDA_ERROR_NOT_READY](#) on at least one of the events), [CUDA_ERROR_NOT_READY](#) is returned. If either event was created with the [CU_EVENT_DISABLE_TIMING](#) flag, then this function will return [CUDA_ERROR_INVALID_HANDLE](#).



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuEventCreate](#), [cuEventRecord](#), [cuEventQuery](#), [cuEventSynchronize](#), [cuEventDestroy](#), [cudaEventElapsedTime](#)

CUresult cuEventQuery (CUevent hEvent)

Queries an event's status.

Parameters

hEvent

- Event to query

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_NOT_READY](#)

Description

Queries the status of all work currently captured by `hEvent`. See [cuEventRecord\(\)](#) for details on what is captured by an event.

Returns [CUDA_SUCCESS](#) if all captured work has been completed, or [CUDA_ERROR_NOT_READY](#) if any captured work is incomplete.

For the purposes of Unified Memory, a return value of [CUDA_SUCCESS](#) is equivalent to having called [cuEventSynchronize\(\)](#).



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuEventCreate](#), [cuEventRecord](#), [cuEventSynchronize](#), [cuEventDestroy](#), [cuEventElapsedTime](#), [cudaEventQuery](#)

CUresult cuEventRecord (CUevent hEvent, CUstream hStream)

Records an event.

Parameters

hEvent

- Event to record

hStream

- Stream to record event for

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Captures in `hEvent` the contents of `hStream` at the time of this call. `hEvent` and `hStream` must be from the same context. Calls such as [cuEventQuery\(\)](#) or [cuStreamWaitEvent\(\)](#) will then examine or wait for completion of the work that was captured. Uses of `hStream` after this call do not modify `hEvent`. See note on default stream behavior for what is captured in the default case.

[cuEventRecord\(\)](#) can be called multiple times on the same event and will overwrite the previously captured state. Other APIs such as [cuStreamWaitEvent\(\)](#) use the most recently captured state at the time of the API call, and are not affected by later calls to [cuEventRecord\(\)](#). Before the first call to [cuEventRecord\(\)](#), an event represents an empty set of work, so for example [cuEventQuery\(\)](#) would return [CUDA_SUCCESS](#).



Note:

- ▶ This function uses standard [default stream](#) semantics.
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuEventCreate](#), [cuEventQuery](#), [cuEventSynchronize](#), [cuStreamWaitEvent](#), [cuEventDestroy](#), [cuEventElapsedTime](#), [cudaEventRecord](#), [cuEventRecordWithFlags](#)

CUresult cuEventRecordWithFlags (CUevent hEvent, CUstream hStream, unsigned int flags)

Records an event.

Parameters

hEvent

- Event to record

hStream

- Stream to record event for

flags

- See CUevent_capture_flags

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Captures in `hEvent` the contents of `hStream` at the time of this call. `hEvent` and `hStream` must be from the same context. Calls such as [cuEventQuery\(\)](#) or [cuStreamWaitEvent\(\)](#) will then examine or wait for completion of the work that was captured. Uses of `hStream` after this call do not modify `hEvent`. See note on default stream behavior for what is captured in the default case.

[cuEventRecordWithFlags\(\)](#) can be called multiple times on the same event and will overwrite the previously captured state. Other APIs such as [cuStreamWaitEvent\(\)](#) use the most recently captured state at the time of the API call, and are not affected by later calls to [cuEventRecordWithFlags\(\)](#). Before the first call to [cuEventRecordWithFlags\(\)](#), an event represents an empty set of work, so for example [cuEventQuery\(\)](#) would return [CUDA_SUCCESS](#).

flags include:

- ▶ [CU_EVENT_RECORD_DEFAULT](#): Default event creation flag.
- ▶ [CU_EVENT_RECORD_EXTERNAL](#): Event is captured in the graph as an external event node when performing stream capture. This flag is invalid outside of stream capture.



Note:

- ▶ This function uses standard [default stream](#) semantics.
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuEventCreate](#), [cuEventQuery](#), [cuEventSynchronize](#), [cuStreamWaitEvent](#), [cuEventDestroy](#), [cuEventElapsedTime](#), [cuEventRecord](#), [cudaEventRecord](#)

CUresult cuEventSynchronize (CUevent hEvent)

Waits for an event to complete.

Parameters

hEvent

- Event to wait for

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_HANDLE](#)

Description

Waits until the completion of all work currently captured in `hEvent`. See [cuEventRecord\(\)](#) for details on what is captured by an event.

Waiting for an event that was created with the [CU_EVENT_BLOCKING_SYNC](#) flag will cause the calling CPU thread to block until the event has been completed by the device. If the [CU_EVENT_BLOCKING_SYNC](#) flag has not been set, then the CPU thread will busy-wait until the event has been completed by the device.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuEventCreate](#), [cuEventRecord](#), [cuEventQuery](#), [cuEventDestroy](#), [cuEventElapsedTime](#), [cudaEventSynchronize](#)

6.17. External Resource Interoperability

This section describes the external resource interoperability functions of the low-level CUDA driver application programming interface.

CUresult cuDestroyExternalMemory (CUexternalMemory extMem)

Destroys an external memory object.

Parameters

extMem

- External memory object to be destroyed

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_HANDLE](#)

Description

Destroys the specified external memory object. Any existing buffers and CUDA mipmapped arrays mapped onto this object must no longer be used and must be explicitly freed using [cuMemFree](#) and [cuMipmappedArrayDestroy](#) respectively.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuImportExternalMemory](#), [cuExternalMemoryGetMappedBuffer](#),
[cuExternalMemoryGetMappedMipmappedArray](#)

CUresult cuDestroyExternalSemaphore (CUexternalSemaphore extSem)

Destroys an external semaphore.

Parameters

extSem

- External semaphore to be destroyed

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_HANDLE](#)

Description

Destroys an external semaphore object and releases any references to the underlying resource. Any outstanding signals or waits must have completed before the semaphore is destroyed.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuImportExternalSemaphore](#), [cuSignalExternalSemaphoresAsync](#),
[cuWaitExternalSemaphoresAsync](#)

CUresult cuExternalMemoryGetMappedBuffer (CUdeviceptr *devPtr, CUexternalMemory extMem, const CUDA_EXTERNAL_MEMORY_BUFFER_DESC *bufferDesc)

Maps a buffer onto an imported memory object.

Parameters

devPtr

- Returned device pointer to buffer

extMem

- Handle to external memory object

bufferDesc

- Buffer descriptor

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_HANDLE](#)

Description

Maps a buffer onto an imported memory object and returns a device pointer in `devPtr`.

The properties of the buffer being mapped must be described in `bufferDesc`. The `CUDA_EXTERNAL_MEMORY_BUFFER_DESC` structure is defined as follows:

```
↑ typedef struct CUDA_EXTERNAL_MEMORY_BUFFER_DESC_st {
    unsigned long long offset;
    unsigned long long size;
    unsigned int flags;
} CUDA_EXTERNAL_MEMORY_BUFFER_DESC;
```

where `CUDA_EXTERNAL_MEMORY_BUFFER_DESC::offset` is the offset in the memory object where the buffer's base address is. `CUDA_EXTERNAL_MEMORY_BUFFER_DESC::size` is the size of the buffer. `CUDA_EXTERNAL_MEMORY_BUFFER_DESC::flags` must be zero.

The offset and size have to be suitably aligned to match the requirements of the external API. Mapping two buffers whose ranges overlap may or may not result in the same virtual address being returned for the overlapped portion. In such cases, the application must ensure that all accesses to that region from the GPU are volatile. Otherwise writes made via one address are not guaranteed to be visible via the other address, even if they're issued by the same thread. It is recommended that applications map the combined range instead of mapping separate buffers and then apply the appropriate offsets to the returned pointer to derive the individual buffers.

The returned pointer `devPtr` must be freed using [cuMemFree](#).



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuImportExternalMemory](#), [cuDestroyExternalMemory](#),
[cuExternalMemoryGetMappedMipmappedArray](#)

CUresult

```
cuExternalMemoryGetMappedMipmappedArray
(CUmipmappedArray *mipmap,
CUexternalMemory extMem, const
CUDA_EXTERNAL_MEMORY_MIPMAPPED_ARRAY_DESC
*mipmapDesc)
```

Maps a CUDA mipmapped array onto an external memory object.

Parameters

mipmap

- Returned CUDA mipmapped array

extMem

- Handle to external memory object

mipmapDesc

- CUDA array descriptor

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_HANDLE](#)

Description

Maps a CUDA mipmapped array onto an external object and returns a handle to it in `mipmap`.

The properties of the CUDA mipmapped array being mapped must be described in `mipmapDesc`. The structure `CUDA_EXTERNAL_MEMORY_MIPMAPPED_ARRAY_DESC` is defined as follows:

```
↑ typedef struct CUDA_EXTERNAL_MEMORY_MIPMAPPED_ARRAY_DESC_st {
    unsigned long long offset;
    CUDA_ARRAY3D_DESCRIPTOR arrayDesc;
    unsigned int numLevels;
} CUDA_EXTERNAL_MEMORY_MIPMAPPED_ARRAY_DESC;
```

where [CUDA_EXTERNAL_MEMORY_MIPMAPPED_ARRAY_DESC::offset](#) is the offset in the memory object where the base level of the mipmap chain is. [CUDA_EXTERNAL_MEMORY_MIPMAPPED_ARRAY_DESC::arrayDesc](#) describes the format, dimensions and type of the base level of the mipmap chain. For further details on these parameters, please refer to the documentation for [cuMipmappedArrayCreate](#). Note that if the mipmapped array is bound as a color target in the graphics API, then the flag [CUDA_ARRAY3D_COLOR_ATTACHMENT](#) must be specified in `CUDA_EXTERNAL_MEMORY_MIPMAPPED_ARRAY_DESC::arrayDesc::Flags`. [CUDA_EXTERNAL_MEMORY_MIPMAPPED_ARRAY_DESC::numLevels](#) specifies the total number of levels in the mipmap chain.

If `extMem` was imported from a handle of type [CU_EXTERNAL_MEMORY_HANDLE_TYPE_NVSCIBUF](#), then [CUDA_EXTERNAL_MEMORY_MIPMAPPED_ARRAY_DESC::numLevels](#) must be equal to 1.

The returned CUDA mipmapped array must be freed using [cuMipmappedArrayDestroy](#).



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuImportExternalMemory](#), [cuDestroyExternalMemory](#), [cuExternalMemoryGetMappedBuffer](#)

CUresult cuImportExternalMemory (CUexternalMemory *extMem_out, const CUDA_EXTERNAL_MEMORY_HANDLE_DESC *memHandleDesc)

Imports an external memory object.

Parameters

extMem_out

- Returned handle to an external memory object

memHandleDesc

- Memory import handle descriptor

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_HANDLE](#)

Description

Imports an externally allocated memory object and returns a handle to that in `extMem_out`.

The properties of the handle being imported must be described in `memHandleDesc`. The `CUDA_EXTERNAL_MEMORY_HANDLE_DESC` structure is defined as follows:

```
↑
typedef struct CUDA_EXTERNAL_MEMORY_HANDLE_DESC_st {
    CUexternalMemoryHandleType type;
    union {
        int fd;
        struct {
            void *handle;
            const void *name;
        } win32;
        const void *nvSciBufObject;
    } handle;
    unsigned long long size;
    unsigned int flags;
} CUDA_EXTERNAL_MEMORY_HANDLE_DESC;
```

where `CUDA_EXTERNAL_MEMORY_HANDLE_DESC::type` specifies the type of handle being imported. `CUexternalMemoryHandleType` is defined as:

```
↑
typedef enum CUexternalMemoryHandleType_enum {
    CU_EXTERNAL_MEMORY_HANDLE_TYPE_OPAQUE_FD = 1,
    CU_EXTERNAL_MEMORY_HANDLE_TYPE_OPAQUE_WIN32 = 2,
    CU_EXTERNAL_MEMORY_HANDLE_TYPE_OPAQUE_WIN32_KMT = 3,
    CU_EXTERNAL_MEMORY_HANDLE_TYPE_D3D12_HEAP = 4,
    CU_EXTERNAL_MEMORY_HANDLE_TYPE_D3D12_RESOURCE = 5,
    CU_EXTERNAL_MEMORY_HANDLE_TYPE_D3D11_RESOURCE = 6,
    CU_EXTERNAL_MEMORY_HANDLE_TYPE_D3D11_RESOURCE_KMT = 7,
    CU_EXTERNAL_MEMORY_HANDLE_TYPE_NVSCIBUF = 8
} CUexternalMemoryHandleType;
```

If `CUDA_EXTERNAL_MEMORY_HANDLE_DESC::type` is `CU_EXTERNAL_MEMORY_HANDLE_TYPE_OPAQUE_FD`, then

`CUDA_EXTERNAL_MEMORY_HANDLE_DESC::handle::fd` must be a valid file descriptor referencing a memory object. Ownership of the file descriptor is transferred to the CUDA driver when the handle is imported successfully. Performing any operations on the file descriptor after it is imported results in undefined behavior.

If `CUDA_EXTERNAL_MEMORY_HANDLE_DESC::type` is `CU_EXTERNAL_MEMORY_HANDLE_TYPE_OPAQUE_WIN32`, then exactly one of `CUDA_EXTERNAL_MEMORY_HANDLE_DESC::handle::win32::handle` and `CUDA_EXTERNAL_MEMORY_HANDLE_DESC::handle::win32::name` must not be NULL. If `CUDA_EXTERNAL_MEMORY_HANDLE_DESC::handle::win32::handle` is not NULL, then it must represent a valid shared NT handle that references a memory object. Ownership of this handle is not transferred to CUDA after the import operation, so the application must release the handle using the appropriate system call. If `CUDA_EXTERNAL_MEMORY_HANDLE_DESC::handle::win32::name` is not NULL, then it must point to a NULL-terminated array of UTF-16 characters that refers to a memory object.

If `CUDA_EXTERNAL_MEMORY_HANDLE_DESC::type` is `CU_EXTERNAL_MEMORY_HANDLE_TYPE_OPAQUE_WIN32_KMT`, then `CUDA_EXTERNAL_MEMORY_HANDLE_DESC::handle::win32::handle` must be non-NULL and `CUDA_EXTERNAL_MEMORY_HANDLE_DESC::handle::win32::name` must be NULL. The handle specified must be a globally shared KMT handle. This handle does not hold a reference to the underlying object, and thus will be invalid when all references to the memory object are destroyed.

If `CUDA_EXTERNAL_MEMORY_HANDLE_DESC::type` is `CU_EXTERNAL_MEMORY_HANDLE_TYPE_D3D12_HEAP`, then exactly one of `CUDA_EXTERNAL_MEMORY_HANDLE_DESC::handle::win32::handle` and `CUDA_EXTERNAL_MEMORY_HANDLE_DESC::handle::win32::name` must not be NULL. If `CUDA_EXTERNAL_MEMORY_HANDLE_DESC::handle::win32::handle` is not NULL, then it must represent a valid shared NT handle that is returned by `ID3D12Device::CreateSharedHandle` when referring to a `ID3D12Heap` object. This handle holds a reference to the underlying object. If `CUDA_EXTERNAL_MEMORY_HANDLE_DESC::handle::win32::name` is not NULL, then it must point to a NULL-terminated array of UTF-16 characters that refers to a `ID3D12Heap` object.

If `CUDA_EXTERNAL_MEMORY_HANDLE_DESC::type` is `CU_EXTERNAL_MEMORY_HANDLE_TYPE_D3D12_RESOURCE`, then exactly one of `CUDA_EXTERNAL_MEMORY_HANDLE_DESC::handle::win32::handle` and `CUDA_EXTERNAL_MEMORY_HANDLE_DESC::handle::win32::name` must not be NULL. If `CUDA_EXTERNAL_MEMORY_HANDLE_DESC::handle::win32::handle` is not NULL, then it must represent a valid shared NT handle that is returned by `ID3D12Device::CreateSharedHandle` when referring to a `ID3D12Resource` object. This handle holds a reference to the underlying object. If `CUDA_EXTERNAL_MEMORY_HANDLE_DESC::handle::win32::name` is not NULL, then it must point to a NULL-terminated array of UTF-16 characters that refers to a `ID3D12Resource` object.

If [CUDA_EXTERNAL_MEMORY_HANDLE_DESC::type](#) is [CU_EXTERNAL_MEMORY_HANDLE_TYPE_D3D11_RESOURCE](#), then [CUDA_EXTERNAL_MEMORY_HANDLE_DESC::handle::win32::handle](#) must represent a valid shared NT handle that is returned by `IDXGIResource1::CreateSharedHandle` when referring to a `ID3D11Resource` object. If [CUDA_EXTERNAL_MEMORY_HANDLE_DESC::handle::win32::name](#) is not NULL, then it must point to a NULL-terminated array of UTF-16 characters that refers to a `ID3D11Resource` object.

If [CUDA_EXTERNAL_MEMORY_HANDLE_DESC::type](#) is [CU_EXTERNAL_MEMORY_HANDLE_TYPE_D3D11_RESOURCE_KMT](#), then [CUDA_EXTERNAL_MEMORY_HANDLE_DESC::handle::win32::handle](#) must represent a valid shared KMT handle that is returned by `IDXGIResource::GetSharedHandle` when referring to a `ID3D11Resource` object and [CUDA_EXTERNAL_MEMORY_HANDLE_DESC::handle::win32::name](#) must be NULL.

If [CUDA_EXTERNAL_MEMORY_HANDLE_DESC::type](#) is [CU_EXTERNAL_MEMORY_HANDLE_TYPE_NVSCIBUF](#), then [CUDA_EXTERNAL_MEMORY_HANDLE_DESC::handle::nvSciBufObject](#) must be non-NULL and reference a valid `NvSciBuf` object. If the `NvSciBuf` object imported into CUDA is also mapped by other drivers, then the application must use [cuWaitExternalSemaphoresAsync](#) or [cuSignalExternalSemaphoresAsync](#) as appropriate barriers to maintain coherence between CUDA and the other drivers.

The size of the memory object must be specified in [CUDA_EXTERNAL_MEMORY_HANDLE_DESC::size](#).

Specifying the flag [CUDA_EXTERNAL_MEMORY_DEDICATED](#) in [CUDA_EXTERNAL_MEMORY_HANDLE_DESC::flags](#) indicates that the resource is a dedicated resource. The definition of what a dedicated resource is outside the scope of this extension. This flag must be set if [CUDA_EXTERNAL_MEMORY_HANDLE_DESC::type](#) is one of the following: [CU_EXTERNAL_MEMORY_HANDLE_TYPE_D3D12_RESOURCE](#), [CU_EXTERNAL_MEMORY_HANDLE_TYPE_D3D11_RESOURCE](#), [CU_EXTERNAL_MEMORY_HANDLE_TYPE_D3D11_RESOURCE_KMT](#)



Note:

- ▶ Note that this function may also return error codes from previous, asynchronous launches.
- ▶ If the Vulkan memory imported into CUDA is mapped on the CPU then the application must use `vkInvalidateMappedMemoryRanges/vkFlushMappedMemoryRanges` as well as appropriate Vulkan pipeline barriers to maintain coherence between CPU and GPU. For more information on these APIs, please refer to "Synchronization and Cache Control" chapter from Vulkan specification.

See also:

[cuDestroyExternalMemory](#), [cuExternalMemoryGetMappedBuffer](#),
[cuExternalMemoryGetMappedMipmappedArray](#)

CUresult cuImportExternalSemaphore (CUexternalSemaphore *extSem_out, const CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC *semHandleDesc)

Imports an external semaphore.

Parameters

extSem_out

- Returned handle to an external semaphore

semHandleDesc

- Semaphore import handle descriptor

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_NOT_SUPPORTED](#),
[CUDA_ERROR_INVALID_HANDLE](#)

Description

Imports an externally allocated synchronization object and returns a handle to that in extSem_out.

The properties of the handle being imported must be described in semHandleDesc. The CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC is defined as follows:

```
↑ typedef struct CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC_st {
    CUexternalSemaphoreHandleType type;
    union {
        int fd;
        struct {
            void *handle;
            const void *name;
        } win32;
        const void* NvSciSyncObj;
    } handle;
    unsigned int flags;
} CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC;
```

where [CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC::type](#) specifies the type of handle being imported. [CUexternalSemaphoreHandleType](#) is defined as:

```
↑ typedef enum CUexternalSemaphoreHandleType_enum {
    CUDA_EXTERNAL_SEMAPHORE_HANDLE_TYPE_OPAQUE_FD = 1,
    CUDA_EXTERNAL_SEMAPHORE_HANDLE_TYPE_OPAQUE_WIN32 = 2,
    CUDA_EXTERNAL_SEMAPHORE_HANDLE_TYPE_OPAQUE_WIN32_KMT = 3,
    CUDA_EXTERNAL_SEMAPHORE_HANDLE_TYPE_D3D12_FENCE = 4,
    CUDA_EXTERNAL_SEMAPHORE_HANDLE_TYPE_D3D11_FENCE = 5,
    CUDA_EXTERNAL_SEMAPHORE_HANDLE_TYPE_NVSCISYNC = 6,
    CUDA_EXTERNAL_SEMAPHORE_HANDLE_TYPE_D3D11_KEYED_MUTEX = 7,
```

```

    CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_D3D11_KEYED_MUTEX_KMT = 8,
    CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_TIMELINE_SEMAPHORE_FD = 9,
    CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_TIMELINE_SEMAPHORE_WIN32 = 10
} CUexternalSemaphoreHandleType;

```

If [CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC::type](#) is [CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_OPAQUE_FD](#), then `CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC::handle::fd` must be a valid file descriptor referencing a synchronization object. Ownership of the file descriptor is transferred to the CUDA driver when the handle is imported successfully. Performing any operations on the file descriptor after it is imported results in undefined behavior.

If [CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC::type](#) is [CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_OPAQUE_WIN32](#), then exactly one of `CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC::handle::win32::handle` and `CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC::handle::win32::name` must not be NULL. If `CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC::handle::win32::handle` is not NULL, then it must represent a valid shared NT handle that references a synchronization object. Ownership of this handle is not transferred to CUDA after the import operation, so the application must release the handle using the appropriate system call. If `CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC::handle::win32::name` is not NULL, then it must name a valid synchronization object.

If [CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC::type](#) is [CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_OPAQUE_WIN32_KMT](#), then `CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC::handle::win32::handle` must be non-NULL and `CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC::handle::win32::name` must be NULL. The handle specified must be a globally shared KMT handle. This handle does not hold a reference to the underlying object, and thus will be invalid when all references to the synchronization object are destroyed.

If [CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC::type](#) is [CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_D3D12_FENCE](#), then exactly one of `CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC::handle::win32::handle` and `CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC::handle::win32::name` must not be NULL. If `CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC::handle::win32::handle` is not NULL, then it must represent a valid shared NT handle that is returned by `ID3D12Device::CreateSharedHandle` when referring to a `ID3D12Fence` object. This handle holds a reference to the underlying object. If `CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC::handle::win32::name` is not NULL, then it must name a valid synchronization object that refers to a valid `ID3D12Fence` object.

If [CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC::type](#) is [CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_D3D11_FENCE](#), then `CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC::handle::win32::handle` represents a valid shared NT handle that is returned by `ID3D11Fence::CreateSharedHandle`. If `CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC::handle::win32::name` is not NULL, then it must name a valid synchronization object that refers to a valid `ID3D11Fence` object.

If [CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC::type](#) is [CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_NVSCISYNC](#), then `CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC::handle::nvSciSyncObj` represents a valid `NvSciSyncObj`.

[CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_D3D11_KEYED_MUTEX](#), then `CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC::handle::win32::handle` represents a valid shared NT handle that is returned by `IDXGIResource1::CreateSharedHandle` when referring to a `IDXGIKeyedMutex` object. If `CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC::handle::win32::name` is not `NULL`, then it must name a valid synchronization object that refers to a valid `IDXGIKeyedMutex` object.

If [CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC::type](#) is [CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_D3D11_KEYED_MUTEX_KMT](#), then `CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC::handle::win32::handle` represents a valid shared KMT handle that is returned by `IDXGIResource::GetSharedHandle` when referring to a `IDXGIKeyedMutex` object and `CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC::handle::win32::name` must be `NULL`.

If [CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC::type](#) is [CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_TIMELINE_SEMAPHORE_FD](#), then `CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC::handle::fd` must be a valid file descriptor referencing a synchronization object. Ownership of the file descriptor is transferred to the CUDA driver when the handle is imported successfully. Performing any operations on the file descriptor after it is imported results in undefined behavior.

If [CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC::type](#) is [CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_TIMELINE_SEMAPHORE_WIN32](#), then exactly one of `CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC::handle::win32::handle` and `CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC::handle::win32::name` must not be `NULL`. If `CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC::handle::win32::handle` is not `NULL`, then it must represent a valid shared NT handle that references a synchronization object. Ownership of this handle is not transferred to CUDA after the import operation, so the application must release the handle using the appropriate system call. If `CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC::handle::win32::name` is not `NULL`, then it must name a valid synchronization object.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuDestroyExternalSemaphore](#), [cuSignalExternalSemaphoresAsync](#), [cuWaitExternalSemaphoresAsync](#)

```
CUresult cuSignalExternalSemaphoresAsync
(const CUexternalSemaphore *extSemArray, const
CUDA_EXTERNAL_SEMAPHORE_SIGNAL_PARAMS
*paramsArray, unsigned int numExtSems, CUstream
stream)
```

Signals a set of external semaphore objects.

Parameters

extSemArray

- Set of external semaphores to be signaled

paramsArray

- Array of semaphore parameters

numExtSems

- Number of semaphores to signal

stream

- Stream to enqueue the signal operations in

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_HANDLE](#),
[CUDA_ERROR_NOT_SUPPORTED](#)

Description

Enqueues a signal operation on a set of externally allocated semaphore object in the specified stream. The operations will be executed when all prior operations in the stream complete.

The exact semantics of signaling a semaphore depends on the type of the object.

If the semaphore object is any one of the following types:

[CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_OPAQUE_FD](#),

[CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_OPAQUE_WIN32](#),

[CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_OPAQUE_WIN32_KMT](#) then signaling the semaphore will set it to the signaled state.

If the semaphore object is any one of the following types:

[CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_D3D12_FENCE](#),

[CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_D3D11_FENCE](#),

[CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_TIMELINE_SEMAPHORE_FD](#),

[CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_TIMELINE_SEMAPHORE_WIN32](#)

then the semaphore will be set to the value specified in

[CUDA_EXTERNAL_SEMAPHORE_SIGNAL_PARAMS::params::fence::value](#).

If the semaphore object is of the type [CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_NVSCISYNC](#) this API sets `CUDA_EXTERNAL_SEMAPHORE_SIGNAL_PARAMS::params::nvSciSync::fence` to a value that can be used by subsequent waiters of the same `NvSciSync` object to order operations with those currently submitted in `stream`. Such an update will overwrite previous contents of `CUDA_EXTERNAL_SEMAPHORE_SIGNAL_PARAMS::params::nvSciSync::fence`. By default, signaling such an external semaphore object causes appropriate memory synchronization operations to be performed over all external memory objects that are imported as [CU_EXTERNAL_MEMORY_HANDLE_TYPE_NVSCIBUF](#). This ensures that any subsequent accesses made by other importers of the same set of `NvSciBuf` memory object(s) are coherent. These operations can be skipped by specifying the flag [CUDA_EXTERNAL_SEMAPHORE_SIGNAL_SKIP_NVSCIBUF_MEMSYNC](#), which can be used as a performance optimization when data coherency is not required. But specifying this flag in scenarios where data coherency is required results in undefined behavior. Also, for semaphore object of the type [CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_NVSCISYNC](#), if the `NvSciSyncAttrList` used to create the `NvSciSyncObj` had not set the flags in [cuDeviceGetNvSciSyncAttributes](#) to `CUDA_NVSCISYNC_ATTR_SIGNAL`, this API will return `CUDA_ERROR_NOT_SUPPORTED`.

If the semaphore object is any one of the following types: [CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_D3D11_KEYED_MUTEX](#), [CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_D3D11_KEYED_MUTEX_KMT](#) then the keyed mutex will be released with the key specified in `CUDA_EXTERNAL_SEMAPHORE_PARAMS::params::keyedmutex::key`.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuImportExternalSemaphore](#), [cuDestroyExternalSemaphore](#),
[cuWaitExternalSemaphoresAsync](#)

```
CUresult cuWaitExternalSemaphoresAsync (const
CUexternalSemaphore *extSemArray, const
CUDA_EXTERNAL_SEMAPHORE_WAIT_PARAMS
*paramsArray, unsigned int numExtSems, CUstream
stream)
```

Waits on a set of external semaphore objects.

Parameters

extSemArray

- External semaphores to be waited on

paramsArray

- Array of semaphore parameters

numExtSems

- Number of semaphores to wait on

stream

- Stream to enqueue the wait operations in

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_HANDLE](#),
[CUDA_ERROR_NOT_SUPPORTED](#), [CUDA_ERROR_TIMEOUT](#)

Description

Enqueues a wait operation on a set of externally allocated semaphore object in the specified stream. The operations will be executed when all prior operations in the stream complete.

The exact semantics of waiting on a semaphore depends on the type of the object.

If the semaphore object is any one of the following types:

[CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_OPAQUE_FD](#),

[CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_OPAQUE_WIN32](#),

[CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_OPAQUE_WIN32_KMT](#) then waiting on the

semaphore will wait until the semaphore reaches the signaled state. The semaphore will then be reset to the unsignaled state. Therefore for every signal operation, there can only be one wait operation.

If the semaphore object is any one of the following types:

[CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_D3D12_FENCE](#),

[CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_D3D11_FENCE](#),

[CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_TIMELINE_SEMAPHORE_FD](#),

[CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_TIMELINE_SEMAPHORE_WIN32](#) then waiting

on the semaphore will wait until the value of the semaphore is greater than or equal to `CUDA_EXTERNAL_SEMAPHORE_WAIT_PARAMS::params::fence::value`.

If the semaphore object is of the type [CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_NVSCISYNC](#) then, waiting on the semaphore will wait until the `CUDA_EXTERNAL_SEMAPHORE_SIGNAL_PARAMS::params::nvSciSync::fence` is signaled by the signaler of the `NvSciSyncObj` that was associated with this semaphore object. By default, waiting on such an external semaphore object causes appropriate memory synchronization operations to be performed over all external memory objects that are imported as [CU_EXTERNAL_MEMORY_HANDLE_TYPE_NVSCIBUF](#). This ensures that any subsequent accesses made by other importers of the same set of `NvSciBuf` memory object(s) are coherent. These operations can be skipped by specifying the flag [CUDA_EXTERNAL_SEMAPHORE_WAIT_SKIP_NVSCIBUF_MEMSYNC](#), which can be used as a performance optimization when data coherency is not required. But specifying this flag in scenarios where data coherency is required results in undefined behavior. Also, for semaphore object of the type [CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_NVSCISYNC](#), if the `NvSciSyncAttrList` used to create the `NvSciSyncObj` had not set the flags in [cuDeviceGetNvSciSyncAttributes](#) to `CUDA_NVSCISYNC_ATTR_WAIT`, this API will return `CUDA_ERROR_NOT_SUPPORTED`.

If the semaphore object is any one of the following types: [CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_D3D11_KEYED_MUTEX](#), [CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_D3D11_KEYED_MUTEX_KMT](#) then the keyed mutex will be acquired when it is released with the key specified in `CUDA_EXTERNAL_SEMAPHORE_WAIT_PARAMS::params::keyedmutex::key` or until the timeout specified by `CUDA_EXTERNAL_SEMAPHORE_WAIT_PARAMS::params::keyedmutex::timeoutMs` has lapsed. The timeout interval can either be a finite value specified in milliseconds or an infinite value. In case an infinite value is specified the timeout never elapses. The windows `INFINITE` macro must be used to specify infinite timeout.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuImportExternalSemaphore](#), [cuDestroyExternalSemaphore](#),
[cuSignalExternalSemaphoresAsync](#)

6.18. Stream memory operations

This section describes the stream memory operations of the low-level CUDA driver application programming interface.

The whole set of operations is disabled by default. Users are required to explicitly enable them, e.g. on Linux by passing the kernel module parameter shown below: `modprobe nvidia NVreg_EnableStreamMemOPs=1` There is currently no way to enable these operations on other operating systems.

Users can programmatically query whether the device supports these operations with `cuDeviceGetAttribute()` and `CU_DEVICE_ATTRIBUTE_CAN_USE_STREAM_MEM_OPS`.

Support for the `CU_STREAM_WAIT_VALUE_NOR` flag can be queried with `CU_DEVICE_ATTRIBUTE_CAN_USE_STREAM_WAIT_VALUE_NOR`.

Support for the `cuStreamWriteValue64()` and `cuStreamWaitValue64()` functions, as well as for the `CU_STREAM_MEM_OP_WAIT_VALUE_64` and `CU_STREAM_MEM_OP_WRITE_VALUE_64` flags, can be queried with `CU_DEVICE_ATTRIBUTE_CAN_USE_64_BIT_STREAM_MEM_OPS`.

Support for both `CU_STREAM_WAIT_VALUE_FLUSH` and `CU_STREAM_MEM_OP_FLUSH_REMOTE_WRITES` requires dedicated platform hardware features and can be queried with `cuDeviceGetAttribute()` and `CU_DEVICE_ATTRIBUTE_CAN_FLUSH_REMOTE_WRITES`.

Note that all memory pointers passed as parameters to these operations are device pointers. Where necessary a device pointer should be obtained, for example with `cuMemHostGetDevicePointer()`.

None of the operations accepts pointers to managed memory buffers (`cuMemAllocManaged`).

CUresult cuStreamBatchMemOp (CUstream stream, unsigned int count, CUstreamBatchMemOpParams *paramArray, unsigned int flags)

Batch operations to synchronize the stream via memory operations.

Parameters

stream

The stream to enqueue the operations in.

count

The number of operations in the array. Must be less than 256.

paramArray

The types and parameters of the individual operations.

flags

Reserved for future expansion; must be 0.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_NOT_SUPPORTED](#)

Description

This is a batch version of [cuStreamWaitValue32\(\)](#) and [cuStreamWriteValue32\(\)](#). Batching operations may avoid some performance overhead in both the API call and the device execution versus adding them to the stream in separate API calls. The operations are enqueued in the order they appear in the array.

See [CUstreamBatchMemOpType](#) for the full set of supported operations, and [cuStreamWaitValue32\(\)](#), [cuStreamWaitValue64\(\)](#), [cuStreamWriteValue32\(\)](#), and [cuStreamWriteValue64\(\)](#) for details of specific operations.

Basic support for this can be queried with [cuDeviceGetAttribute\(\)](#) and [CU_DEVICE_ATTRIBUTE_CAN_USE_STREAM_MEM_OPS](#). See related APIs for details on querying support for specific operations.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuStreamWaitValue32](#), [cuStreamWaitValue64](#), [cuStreamWriteValue32](#), [cuStreamWriteValue64](#), [cuMemHostRegister](#)

CUresult cuStreamWaitValue32 (CUstream stream, CUdeviceptr addr, cuuint32_t value, unsigned int flags)

Wait on a memory location.

Parameters**stream**

The stream to synchronize on the memory location.

addr

The memory location to wait on.

value

The value to compare with the memory location.

flags

See [CUstreamWaitValue_flags](#).

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_NOT_SUPPORTED](#)

Description

Enqueues a synchronization of the stream on the given memory location. Work ordered after the operation will block until the given condition on the memory is satisfied. By default, the condition is to wait for $(\text{int32_t})(*\text{addr} - \text{value}) \geq 0$, a cyclic greater-or-equal. Other condition types can be specified via `flags`.

If the memory was registered via [cuMemHostRegister\(\)](#), the device pointer should be obtained with [cuMemHostGetDevicePointer\(\)](#). This function cannot be used with managed memory ([cuMemAllocManaged](#)).

Support for this can be queried with [cuDeviceGetAttribute\(\)](#) and [CU_DEVICE_ATTRIBUTE_CAN_USE_STREAM_MEM_OPS](#).

Support for [CU_STREAM_WAIT_VALUE_NOR](#) can be queried with [cuDeviceGetAttribute\(\)](#) and [CU_DEVICE_ATTRIBUTE_CAN_USE_STREAM_WAIT_VALUE_NOR](#).

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuStreamWaitValue64](#), [cuStreamWriteValue32](#), [cuStreamWriteValue64](#),
[cuStreamBatchMemOp](#), [cuMemHostRegister](#), [cuStreamWaitEvent](#)

CUresult cuStreamWaitValue64 (CUstream stream, CUdeviceptr addr, cuuint64_t value, unsigned int flags)

Wait on a memory location.

Parameters**stream**

The stream to synchronize on the memory location.

addr

The memory location to wait on.

value

The value to compare with the memory location.

flags

See [CUstreamWaitValue_flags](#).

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_NOT_SUPPORTED](#)

Description

Enqueues a synchronization of the stream on the given memory location. Work ordered after the operation will block until the given condition on the memory is satisfied. By default, the condition is to wait for $(\text{int64_t})(*\text{addr} - \text{value}) \geq 0$, a cyclic greater-or-equal. Other condition types can be specified via `flags`.

If the memory was registered via [cuMemHostRegister\(\)](#), the device pointer should be obtained with [cuMemHostGetDevicePointer\(\)](#).

Support for this can be queried with [cuDeviceGetAttribute\(\)](#) and [CU_DEVICE_ATTRIBUTE_CAN_USE_64_BIT_STREAM_MEM_OPS](#).

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuStreamWaitValue32](#), [cuStreamWriteValue32](#), [cuStreamWriteValue64](#), [cuStreamBatchMemOp](#), [cuMemHostRegister](#), [cuStreamWaitEvent](#)

CUresult cuStreamWriteValue32 (CUstream stream, CUdeviceptr addr, cuuint32_t value, unsigned int flags)

Write a value to memory.

Parameters**stream**

The stream to do the write in.

addr

The device address to write to.

value

The value to write.

flags

See [CUstreamWriteValue_flags](#).

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_NOT_SUPPORTED](#)

Description

Write a value to memory. Unless the [CU_STREAM_WRITE_VALUE_NO_MEMORY_BARRIER](#) flag is passed, the write is preceded by a system-wide memory fence, equivalent to a `__threadfence_system()` but scoped to the stream rather than a CUDA thread.

If the memory was registered via [cuMemHostRegister\(\)](#), the device pointer should be obtained with [cuMemHostGetDevicePointer\(\)](#). This function cannot be used with managed memory ([cuMemAllocManaged](#)).

Support for this can be queried with [cuDeviceGetAttribute\(\)](#) and [CU_DEVICE_ATTRIBUTE_CAN_USE_STREAM_MEM_OPS](#).

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuStreamWriteValue64](#), [cuStreamWaitValue32](#), [cuStreamWaitValue64](#), [cuStreamBatchMemOp](#), [cuMemHostRegister](#), [cuEventRecord](#)

CUresult cuStreamWriteValue64 (CUstream stream, CUdeviceptr addr, cuuint64_t value, unsigned int flags)

Write a value to memory.

Parameters**stream**

The stream to do the write in.

addr

The device address to write to.

value

The value to write.

flags

See [CUstreamWriteValue_flags](#).

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_NOT_SUPPORTED](#)

Description

Write a value to memory. Unless the [CU_STREAM_WRITE_VALUE_NO_MEMORY_BARRIER](#) flag is passed, the write is preceded by a system-wide memory fence, equivalent to a `__threadfence_system()` but scoped to the stream rather than a CUDA thread.

If the memory was registered via [cuMemHostRegister\(\)](#), the device pointer should be obtained with [cuMemHostGetDevicePointer\(\)](#).

Support for this can be queried with [cuDeviceGetAttribute\(\)](#) and [CU_DEVICE_ATTRIBUTE_CAN_USE_64_BIT_STREAM_MEM_OPS](#).



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuStreamWriteValue32](#), [cuStreamWaitValue32](#), [cuStreamWaitValue64](#), [cuStreamBatchMemOp](#), [cuMemHostRegister](#), [cuEventRecord](#)

6.19. Execution Control

This section describes the execution control functions of the low-level CUDA driver application programming interface.

CUresult cuFuncGetAttribute (int *pi, CUfunction_attribute attrib, CUfunction hfunc)

Returns information about a function.

Parameters

pi

- Returned attribute value

attrib

- Attribute requested

hfunc

- Function to query attribute of

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Returns in `*pi` the integer value of the attribute `attrib` on the kernel given by `hfunc`. The supported attributes are:

- ▶ [CU_FUNC_ATTRIBUTE_MAX_THREADS_PER_BLOCK](#): The maximum number of threads per block, beyond which a launch of the function would fail. This number depends on both the function and the device on which the function is currently loaded.
- ▶ [CU_FUNC_ATTRIBUTE_SHARED_SIZE_BYTES](#): The size in bytes of statically-allocated shared memory per block required by this function. This does not include dynamically-allocated shared memory requested by the user at runtime.
- ▶ [CU_FUNC_ATTRIBUTE_CONST_SIZE_BYTES](#): The size in bytes of user-allocated constant memory required by this function.
- ▶ [CU_FUNC_ATTRIBUTE_LOCAL_SIZE_BYTES](#): The size in bytes of local memory used by each thread of this function.
- ▶ [CU_FUNC_ATTRIBUTE_NUM_REGS](#): The number of registers used by each thread of this function.
- ▶ [CU_FUNC_ATTRIBUTE_PTX_VERSION](#): The PTX virtual architecture version for which the function was compiled. This value is the major PTX version * 10 + the minor PTX version, so a PTX version 1.3 function would return the value 13. Note that this may return the undefined value of 0 for cubins compiled prior to CUDA 3.0.
- ▶ [CU_FUNC_ATTRIBUTE_BINARY_VERSION](#): The binary architecture version for which the function was compiled. This value is the major binary version * 10 + the minor binary version, so a binary version 1.3 function would return the value 13. Note that this will return a value of 10 for legacy cubins that do not have a properly-encoded binary architecture version.
- ▶ `CU_FUNC_CACHE_MODE_CA`: The attribute to indicate whether the function has been compiled with user specified option "-Xptxas --dlcm=ca" set .
- ▶ [CU_FUNC_ATTRIBUTE_MAX_DYNAMIC_SHARED_SIZE_BYTES](#): The maximum size in bytes of dynamically-allocated shared memory.
- ▶ [CU_FUNC_ATTRIBUTE_PREFERRED_SHARED_MEMORY_CARVEOUT](#): Preferred shared memory-L1 cache split ratio in percent of total shared memory.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuCtxGetCacheConfig](#), [cuCtxSetCacheConfig](#), [cuFuncSetCacheConfig](#), [cuLaunchKernel](#),
[cudaFuncGetAttributes](#), [cudaFuncSetAttribute](#)

CUresult cuFuncGetModule (CUmodule *hmod, CUfunction hfunc)

Returns a module handle.

Parameters

hmod

- Returned module handle

hfunc

- Function to retrieve module for

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_NOT_FOUND](#)

Description

Returns in *hmod the handle of the module that function hfunc is located in. The lifetime of the module corresponds to the lifetime of the context it was loaded in or until the module is explicitly unloaded.

The CUDA runtime manages its own modules loaded into the primary context. If the handle returned by this API refers to a module loaded by the CUDA runtime, calling [cuModuleUnload\(\)](#) on that module will result in undefined behavior.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

CUresult cuFuncSetAttribute (CUfunction hfunc, CUfunction_attribute attrib, int value)

Sets information about a function.

Parameters

hfunc

- Function to query attribute of

attrib

- Attribute requested

value

- The value to set

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_HANDLE](#),
[CUDA_ERROR_INVALID_VALUE](#)

Description

This call sets the value of a specified attribute `attrib` on the kernel given by `hfunc` to an integer value specified by `val`. This function returns `CUDA_SUCCESS` if the new value of the attribute could be successfully set. If the set fails, this call will return an error. Not all attributes can have values set. Attempting to set a value on a read-only attribute will result in an error (`CUDA_ERROR_INVALID_VALUE`)

Supported attributes for the `cuFuncSetAttribute` call are:

- ▶ [CU_FUNC_ATTRIBUTE_MAX_DYNAMIC_SHARED_SIZE_BYTES](#): This maximum size in bytes of dynamically-allocated shared memory. The value should contain the requested maximum size of dynamically-allocated shared memory. The sum of this value and the function attribute [CU_FUNC_ATTRIBUTE_SHARED_SIZE_BYTES](#) cannot exceed the device attribute [CU_DEVICE_ATTRIBUTE_MAX_SHARED_MEMORY_PER_BLOCK_OPTIN](#). The maximal size of requestable dynamic shared memory may differ by GPU architecture.
- ▶ [CU_FUNC_ATTRIBUTE_PREFERRED_SHARED_MEMORY_CARVEOUT](#): On devices where the L1 cache and shared memory use the same hardware resources, this sets the shared memory carveout preference, in percent of the total shared memory. See [CU_DEVICE_ATTRIBUTE_MAX_SHARED_MEMORY_PER_MULTIPROCESSOR](#). This is only a hint, and the driver can choose a different ratio if required to execute the function.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuCtxGetCacheConfig](#), [cuCtxSetCacheConfig](#), [cuFuncSetCacheConfig](#), [cuLaunchKernel](#),
[cudaFuncGetAttributes](#), [cudaFuncSetAttribute](#)

CUresult cuFuncSetCacheConfig (CUfunction hfunc, CUfunc_cache config)

Sets the preferred cache configuration for a device function.

Parameters

hfunc

- Kernel to configure cache for

config

- Requested cache configuration

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#)

Description

On devices where the L1 cache and shared memory use the same hardware resources, this sets through `config` the preferred cache configuration for the device function `hfunc`. This is only a preference. The driver will use the requested configuration if possible, but it is free to choose a different configuration if required to execute `hfunc`. Any context-wide preference set via [cuCtxSetCacheConfig\(\)](#) will be overridden by this per-function setting unless the per-function setting is [CU_FUNC_CACHE_PREFER_NONE](#). In that case, the current context-wide setting will be used.

This setting does nothing on devices where the size of the L1 cache and shared memory are fixed.

Launching a kernel with a different preference than the most recent preference setting may insert a device-side synchronization point.

The supported cache configurations are:

- ▶ [CU_FUNC_CACHE_PREFER_NONE](#): no preference for shared memory or L1 (default)
- ▶ [CU_FUNC_CACHE_PREFER_SHARED](#): prefer larger shared memory and smaller L1 cache
- ▶ [CU_FUNC_CACHE_PREFER_L1](#): prefer larger L1 cache and smaller shared memory
- ▶ [CU_FUNC_CACHE_PREFER_EQUAL](#): prefer equal sized L1 cache and shared memory



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuCtxGetCacheConfig](#), [cuCtxSetCacheConfig](#), [cuFuncGetAttribute](#), [cuLaunchKernel](#), [cudaFuncSetCacheConfig](#)

CUresult cuFuncSetSharedMemConfig (CUfunction hfunc, CUsharedconfig config)

Sets the shared memory configuration for a device function.

Parameters

hfunc

- kernel to be given a shared memory config

config

- requested shared memory configuration

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#)

Description

On devices with configurable shared memory banks, this function will force all subsequent launches of the specified device function to have the given shared memory bank size configuration. On any given launch of the function, the shared memory configuration of the device will be temporarily changed if needed to suit the function's preferred configuration. Changes in shared memory configuration between subsequent launches of functions, may introduce a device side synchronization point.

Any per-function setting of shared memory bank size set via [cuFuncSetSharedMemConfig](#) will override the context wide setting set with [cuCtxSetSharedMemConfig](#).

Changing the shared memory bank size will not increase shared memory usage or affect occupancy of kernels, but may have major effects on performance. Larger bank sizes will allow for greater potential bandwidth to shared memory, but will change what kinds of accesses to shared memory will result in bank conflicts.

This function will do nothing on devices with fixed shared memory bank size.

The supported bank configurations are:

- ▶ [CU_SHARED_MEM_CONFIG_DEFAULT_BANK_SIZE](#): use the context's shared memory configuration when launching this function.
- ▶ [CU_SHARED_MEM_CONFIG_FOUR_BYTE_BANK_SIZE](#): set shared memory bank width to be natively four bytes when launching this function.
- ▶ [CU_SHARED_MEM_CONFIG_EIGHT_BYTE_BANK_SIZE](#): set shared memory bank width to be natively eight bytes when launching this function.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuCtxGetCacheConfig](#), [cuCtxSetCacheConfig](#), [cuCtxGetSharedMemConfig](#),
[cuCtxSetSharedMemConfig](#), [cuFuncGetAttribute](#), [cuLaunchKernel](#),
[cudaFuncSetSharedMemConfig](#)

CUresult cuLaunchCooperativeKernel (CUfunction f, unsigned int gridDimX, unsigned int gridDimY, unsigned int gridDimZ, unsigned int blockDimX, unsigned int blockDimY, unsigned int blockDimZ, unsigned int sharedMemBytes, CUstream hStream, void **kernelParams)

Launches a CUDA function where thread blocks can cooperate and synchronize as they execute.

Parameters**f**

- Kernel to launch

gridDimX

- Width of grid in blocks

gridDimY

- Height of grid in blocks

gridDimZ

- Depth of grid in blocks

blockDimX

- X dimension of each thread block

blockDimY

- Y dimension of each thread block

blockDimZ

- Z dimension of each thread block

sharedMemBytes

- Dynamic shared-memory size per thread block in bytes

hStream

- Stream identifier

kernelParams

- Array of pointers to kernel parameters

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_HANDLE](#),
[CUDA_ERROR_INVALID_IMAGE](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_LAUNCH_FAILED](#), [CUDA_ERROR_LAUNCH_OUT_OF_RESOURCES](#),
[CUDA_ERROR_LAUNCH_TIMEOUT](#), [CUDA_ERROR_LAUNCH_INCOMPATIBLE_TEXTURING](#),
[CUDA_ERROR_COOPERATIVE_LAUNCH_TOO_LARGE](#),
[CUDA_ERROR_SHARED_OBJECT_INIT_FAILED](#)

Description

Invokes the kernel `f` on a `gridDimX x gridDimY x gridDimZ` grid of blocks. Each block contains `blockDimX x blockDimY x blockDimZ` threads.

`sharedMemBytes` sets the amount of dynamic shared memory that will be available to each thread block.

The device on which this kernel is invoked must have a non-zero value for the device attribute [CU_DEVICE_ATTRIBUTE_COOPERATIVE_LAUNCH](#).

The total number of blocks launched cannot exceed the maximum number of blocks per multiprocessor as returned by [cuOccupancyMaxActiveBlocksPerMultiprocessor](#) (or [cuOccupancyMaxActiveBlocksPerMultiprocessorWithFlags](#)) times the number of multiprocessors as specified by the device attribute [CU_DEVICE_ATTRIBUTE_MULTIPROCESSOR_COUNT](#).

The kernel cannot make use of CUDA dynamic parallelism.

Kernel parameters must be specified via `kernelParams`. If `f` has `N` parameters, then `kernelParams` needs to be an array of `N` pointers. Each of `kernelParams[0]` through `kernelParams[N-1]` must point to a region of memory from which the actual kernel parameter will be copied. The number of kernel parameters and their offsets and sizes do not need to be specified as that information is retrieved directly from the kernel's image.

Calling [cuLaunchCooperativeKernel\(\)](#) sets persistent function state that is the same as function state set through [cuLaunchKernel](#) API

When the kernel `f` is launched via [cuLaunchCooperativeKernel\(\)](#), the previous block shape, shared size and parameter info associated with `f` is overwritten.

Note that to use [cuLaunchCooperativeKernel\(\)](#), the kernel `f` must either have been compiled with toolchain version 3.2 or later so that it will contain kernel parameter information, or have no kernel parameters. If either of these conditions is not met, then [cuLaunchCooperativeKernel\(\)](#) will return [CUDA_ERROR_INVALID_IMAGE](#).



Note:

- ▶ This function uses standard [default stream](#) semantics.
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuCtxGetCacheConfig](#), [cuCtxSetCacheConfig](#), [cuFuncSetCacheConfig](#), [cuFuncGetAttribute](#), [cuLaunchCooperativeKernelMultiDevice](#), [cudaLaunchCooperativeKernel](#)

CUresult cuLaunchCooperativeKernelMultiDevice (CUDA_LAUNCH_PARAMS *launchParamsList, unsigned int numDevices, unsigned int flags)

Launches CUDA functions on multiple devices where thread blocks can cooperate and synchronize as they execute.

Parameters

launchParamsList

- List of launch parameters, one per device

numDevices

- Size of the `launchParamsList` array

flags

- Flags to control launch behavior

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_INVALID_IMAGE](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_LAUNCH_FAILED](#), [CUDA_ERROR_LAUNCH_OUT_OF_RESOURCES](#), [CUDA_ERROR_LAUNCH_TIMEOUT](#), [CUDA_ERROR_LAUNCH_INCOMPATIBLE_TEXTURING](#), [CUDA_ERROR_COOPERATIVE_LAUNCH_TOO_LARGE](#), [CUDA_ERROR_SHARED_OBJECT_INIT_FAILED](#)

Description

Deprecated This function is deprecated as of CUDA 11.3.

Invokes kernels as specified in the `launchParamsList` array where each element of the array specifies all the parameters required to perform a single kernel launch. These kernels can cooperate and synchronize as they execute. The size of the array is specified by `numDevices`.

No two kernels can be launched on the same device. All the devices targeted by this multi-device launch must be identical. All devices must have a non-zero value for the device attribute [CU_DEVICE_ATTRIBUTE_COOPERATIVE_MULTI_DEVICE_LAUNCH](#).

All kernels launched must be identical with respect to the compiled code. Note that any `__device__`, `__constant__` or `__managed__` variables present in the module that owns the kernel launched on each device, are independently instantiated on every device. It is the application's responsibility to ensure these variables are initialized and used appropriately.

The size of the grids as specified in blocks, the size of the blocks themselves and the amount of shared memory used by each thread block must also match across all launched kernels.

The streams used to launch these kernels must have been created via either [cuStreamCreate](#) or [cuStreamCreateWithPriority](#). The NULL stream or [CU_STREAM_LEGACY](#) or [CU_STREAM_PER_THREAD](#) cannot be used.

The total number of blocks launched per kernel cannot exceed the maximum number of blocks per multiprocessor as returned by [cuOccupancyMaxActiveBlocksPerMultiprocessor](#) (or [cuOccupancyMaxActiveBlocksPerMultiprocessorWithFlags](#)) times the number of multiprocessors as specified by the device attribute [CU_DEVICE_ATTRIBUTE_MULTIPROCESSOR_COUNT](#). Since the total number of blocks launched per device has to match across all devices, the maximum number of blocks that can be launched per device will be limited by the device with the least number of multiprocessors.

The kernels cannot make use of CUDA dynamic parallelism.

The `CUDA_LAUNCH_PARAMS` structure is defined as:

```
↑
typedef struct CUDA_LAUNCH_PARAMS_st
{
    CUfunction function;
    unsigned int gridDimX;
    unsigned int gridDimY;
    unsigned int gridDimZ;
    unsigned int blockDimX;
    unsigned int blockDimY;
    unsigned int blockDimZ;
    unsigned int sharedMemBytes;
    CUstream hStream;
    void **kernelParams;
} CUDA_LAUNCH_PARAMS;
```

where:

- ▶ [CUDA_LAUNCH_PARAMS::function](#) specifies the kernel to be launched. All functions must be identical with respect to the compiled code.
- ▶ [CUDA_LAUNCH_PARAMS::gridDimX](#) is the width of the grid in blocks. This must match across all kernels launched.
- ▶ [CUDA_LAUNCH_PARAMS::gridDimY](#) is the height of the grid in blocks. This must match across all kernels launched.
- ▶ [CUDA_LAUNCH_PARAMS::gridDimZ](#) is the depth of the grid in blocks. This must match across all kernels launched.
- ▶ [CUDA_LAUNCH_PARAMS::blockDimX](#) is the X dimension of each thread block. This must match across all kernels launched.
- ▶ [CUDA_LAUNCH_PARAMS::blockDimY](#) is the Y dimension of each thread block. This must match across all kernels launched.

- ▶ [CUDA_LAUNCH_PARAMS::blockDimZ](#) is the Z dimension of each thread block. This must match across all kernels launched.
- ▶ [CUDA_LAUNCH_PARAMS::sharedMemBytes](#) is the dynamic shared-memory size per thread block in bytes. This must match across all kernels launched.
- ▶ [CUDA_LAUNCH_PARAMS::hStream](#) is the handle to the stream to perform the launch in. This cannot be the NULL stream or [CU_STREAM_LEGACY](#) or [CU_STREAM_PER_THREAD](#). The CUDA context associated with this stream must match that associated with [CUDA_LAUNCH_PARAMS::function](#).
- ▶ [CUDA_LAUNCH_PARAMS::kernelParams](#) is an array of pointers to kernel parameters. If [CUDA_LAUNCH_PARAMS::function](#) has N parameters, then [CUDA_LAUNCH_PARAMS::kernelParams](#) needs to be an array of N pointers. Each of [CUDA_LAUNCH_PARAMS::kernelParams\[0\]](#) through [CUDA_LAUNCH_PARAMS::kernelParams\[N-1\]](#) must point to a region of memory from which the actual kernel parameter will be copied. The number of kernel parameters and their offsets and sizes do not need to be specified as that information is retrieved directly from the kernel's image.

By default, the kernel won't begin execution on any GPU until all prior work in all the specified streams has completed. This behavior can be overridden by specifying the flag [CUDA_COOPERATIVE_LAUNCH_MULTI_DEVICE_NO_PRE_LAUNCH_SYNC](#). When this flag is specified, each kernel will only wait for prior work in the stream corresponding to that GPU to complete before it begins execution.

Similarly, by default, any subsequent work pushed in any of the specified streams will not begin execution until the kernels on all GPUs have completed. This behavior can be overridden by specifying the flag [CUDA_COOPERATIVE_LAUNCH_MULTI_DEVICE_NO_POST_LAUNCH_SYNC](#). When this flag is specified, any subsequent work pushed in any of the specified streams will only wait for the kernel launched on the GPU corresponding to that stream to complete before it begins execution.

Calling [cuLaunchCooperativeKernelMultiDevice\(\)](#) sets persistent function state that is the same as function state set through [cuLaunchKernel](#) API when called individually for each element in `launchParamsList`.

When kernels are launched via [cuLaunchCooperativeKernelMultiDevice\(\)](#), the previous block shape, shared size and parameter info associated with each [CUDA_LAUNCH_PARAMS::function](#) in `launchParamsList` is overwritten.

Note that to use [cuLaunchCooperativeKernelMultiDevice\(\)](#), the kernels must either have been compiled with toolchain version 3.2 or later so that it will contain kernel parameter information, or have no kernel parameters. If either of these conditions is not met, then [cuLaunchCooperativeKernelMultiDevice\(\)](#) will return [CUDA_ERROR_INVALID_IMAGE](#).

**Note:**

- ▶ This function uses standard [default stream](#) semantics.
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuCtxGetCacheConfig](#), [cuCtxSetCacheConfig](#), [cuFuncSetCacheConfig](#), [cuFuncGetAttribute](#), [cuLaunchCooperativeKernel](#), [cudaLaunchCooperativeKernelMultiDevice](#)

CUresult cuLaunchHostFunc (CUstream hStream, CUhostFn fn, void *userData)

Enqueues a host function call in a stream.

Parameters

hStream

- Stream to enqueue function call in

fn

- The function to call once preceding stream operations are complete

userData

- User-specified data to be passed to the function

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_NOT_SUPPORTED](#)

Description

Enqueues a host function to run in a stream. The function will be called after currently enqueued work and will block work added after it.


The host function must not make any CUDA API calls. Attempting to use a CUDA API may result in [CUDA_ERROR_NOT_PERMITTED](#), but this is not required. The host function must not perform any synchronization that may depend on outstanding CUDA work not mandated to run earlier. Host functions without a mandated order (such as in independent streams) execute in undefined order and may be serialized.

For the purposes of Unified Memory, execution makes a number of guarantees:

- ▶ The stream is considered idle for the duration of the function's execution. Thus, for example, the function may always use memory attached to the stream it was enqueued in.

- ▶ The start of execution of the function has the same effect as synchronizing an event recorded in the same stream immediately prior to the function. It thus synchronizes streams which have been "joined" prior to the function.
- ▶ Adding device work to any stream does not have the effect of making the stream active until all preceding host functions and stream callbacks have executed. Thus, for example, a function might use global attached memory even if work has been added to another stream, if the work has been ordered behind the function call with an event.
- ▶ Completion of the function does not cause a stream to become active except as described above. The stream will remain idle if no device work follows the function, and will remain idle across consecutive host functions or stream callbacks without device work in between. Thus, for example, stream synchronization can be done by signaling from a host function at the end of the stream.

Note that, in contrast to [cuStreamAddCallback](#), the function will not be called in the event of an error in the CUDA context.



Note:

- ▶ This function uses standard [default stream](#) semantics.
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuStreamCreate](#), [cuStreamQuery](#), [cuStreamSynchronize](#), [cuStreamWaitEvent](#), [cuStreamDestroy](#), [cuMemAllocManaged](#), [cuStreamAttachMemAsync](#), [cuStreamAddCallback](#)

```
CUresult cuLaunchKernel (CUfunction f, unsigned
int gridDimX, unsigned int gridDimY, unsigned
int gridDimZ, unsigned int blockDimX, unsigned
int blockDimY, unsigned int blockDimZ, unsigned
int sharedMemBytes, CUstream hStream, void
**kernelParams, void **extra)
```

Launches a CUDA function.

Parameters

f

- Kernel to launch

gridDimX

- Width of grid in blocks

gridDimY

- Height of grid in blocks

gridDimZ

- Depth of grid in blocks

blockDimX

- X dimension of each thread block

blockDimY

- Y dimension of each thread block

blockDimZ

- Z dimension of each thread block

sharedMemBytes

- Dynamic shared-memory size per thread block in bytes

hStream

- Stream identifier

kernelParams

- Array of pointers to kernel parameters

extra

- Extra options

Returns

CUDA_SUCCESS, CUDA_ERROR_DEINITIALIZED, CUDA_ERROR_NOT_INITIALIZED,
CUDA_ERROR_INVALID_CONTEXT, CUDA_ERROR_INVALID_HANDLE,
CUDA_ERROR_INVALID_IMAGE, CUDA_ERROR_INVALID_VALUE,
CUDA_ERROR_LAUNCH_FAILED, CUDA_ERROR_LAUNCH_OUT_OF_RESOURCES,
CUDA_ERROR_LAUNCH_TIMEOUT, CUDA_ERROR_LAUNCH_INCOMPATIBLE_TEXTURING,
CUDA_ERROR_SHARED_OBJECT_INIT_FAILED

Description

Invokes the kernel `f` on a `gridDimX` x `gridDimY` x `gridDimZ` grid of blocks. Each block contains `blockDimX` x `blockDimY` x `blockDimZ` threads.

`sharedMemBytes` sets the amount of dynamic shared memory that will be available to each thread block.

Kernel parameters to `f` can be specified in one of two ways:

- 1) Kernel parameters can be specified via `kernelParams`. If `f` has `N` parameters, then `kernelParams` needs to be an array of `N` pointers. Each of `kernelParams[0]` through `kernelParams[N-1]` must point to a region of memory from which the actual kernel parameter will be copied. The number of kernel parameters and their offsets and sizes do not need to be specified as that information is retrieved directly from the kernel's image.
- 2) Kernel parameters can also be packaged by the application into a single buffer that is passed in via the `extra` parameter. This places the burden on the application of knowing each

kernel parameter's size and alignment/padding within the buffer. Here is an example of using the `extra` parameter in this manner:

```
↑
    size_t argBufferSize;
    char argBuffer[256];

    // populate argBuffer and argBufferSize

    void *config[] = {
        CU_LAUNCH_PARAM_BUFFER_POINTER, argBuffer,
        CU_LAUNCH_PARAM_BUFFER_SIZE,   &argBufferSize,
        CU_LAUNCH_PARAM_END
    };
    status = cuLaunchKernel(f, gx, gy, gz, bx, by, bz, sh, s, NULL, config);
```

The `extra` parameter exists to allow `cuLaunchKernel` to take additional less commonly used arguments. `extra` specifies a list of names of extra settings and their corresponding values. Each extra setting name is immediately followed by the corresponding value. The list must be terminated with either `NULL` or `CU_LAUNCH_PARAM_END`.

- ▶ `CU_LAUNCH_PARAM_END`, which indicates the end of the `extra` array;
- ▶ `CU_LAUNCH_PARAM_BUFFER_POINTER`, which specifies that the next value in `extra` will be a pointer to a buffer containing all the kernel parameters for launching kernel `f`;
- ▶ `CU_LAUNCH_PARAM_BUFFER_SIZE`, which specifies that the next value in `extra` will be a pointer to a `size_t` containing the size of the buffer specified with `CU_LAUNCH_PARAM_BUFFER_POINTER`;

The error `CUDA_ERROR_INVALID_VALUE` will be returned if kernel parameters are specified with both `kernelParams` and `extra` (i.e. both `kernelParams` and `extra` are non-`NULL`).

Calling `cuLaunchKernel()` invalidates the persistent function state set through the following deprecated APIs: `cuFuncSetBlockShape()`, `cuFuncSetSharedSize()`, `cuParamSetSize()`, `cuParamSeti()`, `cuParamSetf()`, `cuParamSetv()`.

Note that to use `cuLaunchKernel()`, the kernel `f` must either have been compiled with toolchain version 3.2 or later so that it will contain kernel parameter information, or have no kernel parameters. If either of these conditions is not met, then `cuLaunchKernel()` will return `CUDA_ERROR_INVALID_IMAGE`.



Note:

- ▶ This function uses standard [default stream](#) semantics.
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuCtxGetCacheConfig](#), [cuCtxSetCacheConfig](#), [cuFuncSetCacheConfig](#), [cuFuncGetAttribute](#), [cudaLaunchKernel](#)

6.20. Execution Control [DEPRECATED]

This section describes the deprecated execution control functions of the low-level CUDA driver application programming interface.

CUresult cuFuncSetBlockShape (CUfunction hfunc, int x, int y, int z)

Sets the block-dimensions for the function.

Parameters

hfunc

- Kernel to specify dimensions of

x

- X dimension

y

- Y dimension

z

- Z dimension

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

[Deprecated](#)

Specifies the x , y , and z dimensions of the thread blocks that are created when the kernel given by `hfunc` is launched.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuFuncSetSharedSize](#), [cuFuncSetCacheConfig](#), [cuFuncGetAttribute](#), [cuParamSetSize](#), [cuParamSeti](#), [cuParamSetf](#), [cuParamSetv](#), [cuLaunch](#), [cuLaunchGrid](#), [cuLaunchGridAsync](#), [cuLaunchKernel](#)

CUresult cuFuncSetSharedSize (CUfunction hfunc, unsigned int bytes)

Sets the dynamic shared-memory size for the function.

Parameters

hfunc

- Kernel to specify dynamic shared-memory size for

bytes

- Dynamic shared-memory size per thread in bytes

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_HANDLE](#),
[CUDA_ERROR_INVALID_VALUE](#)

Description

[Deprecated](#)

Sets through `bytes` the amount of dynamic shared memory that will be available to each thread block when the kernel given by `hfunc` is launched.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuFuncSetBlockShape](#), [cuFuncSetCacheConfig](#), [cuFuncGetAttribute](#), [cuParamSetSize](#),
[cuParamSeti](#), [cuParamSetf](#), [cuParamSetv](#), [cuLaunch](#), [cuLaunchGrid](#), [cuLaunchGridAsync](#),
[cuLaunchKernel](#)

CUresult cuLaunch (CUfunction f)

Launches a CUDA function.

Parameters

f

- Kernel to launch

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_LAUNCH_FAILED](#), [CUDA_ERROR_LAUNCH_OUT_OF_RESOURCES](#), [CUDA_ERROR_LAUNCH_TIMEOUT](#), [CUDA_ERROR_LAUNCH_INCOMPATIBLE_TEXTURING](#), [CUDA_ERROR_SHARED_OBJECT_INIT_FAILED](#)

Description

Deprecated

Invokes the kernel f on a $1 \times 1 \times 1$ grid of blocks. The block contains the number of threads specified by a previous call to [cuFuncSetBlockShape\(\)](#).

The block shape, dynamic shared memory size, and parameter information must be set using [cuFuncSetBlockShape\(\)](#), [cuFuncSetSharedSize\(\)](#), [cuParamSetSize\(\)](#), [cuParamSeti\(\)](#), [cuParamSetf\(\)](#), and [cuParamSetv\(\)](#) prior to calling this function.

Launching a function via [cuLaunchKernel\(\)](#) invalidates the function's block shape, dynamic shared memory size, and parameter information. After launching via [cuLaunchKernel](#), this state must be re-initialized prior to calling this function. Failure to do so results in undefined behavior.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuFuncSetBlockShape](#), [cuFuncSetSharedSize](#), [cuFuncGetAttribute](#), [cuParamSetSize](#), [cuParamSetf](#), [cuParamSeti](#), [cuParamSetv](#), [cuLaunchGrid](#), [cuLaunchGridAsync](#), [cuLaunchKernel](#)

CUresult cuLaunchGrid (CUfunction f, int grid_width, int grid_height)

Launches a CUDA function.

Parameters

f

- Kernel to launch

grid_width

- Width of grid in blocks

grid_height

- Height of grid in blocks

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_LAUNCH_FAILED](#), [CUDA_ERROR_LAUNCH_OUT_OF_RESOURCES](#),
[CUDA_ERROR_LAUNCH_TIMEOUT](#), [CUDA_ERROR_LAUNCH_INCOMPATIBLE_TEXTURING](#),
[CUDA_ERROR_SHARED_OBJECT_INIT_FAILED](#)

DescriptionDeprecated

Invokes the kernel `f` on a `grid_width` x `grid_height` grid of blocks. Each block contains the number of threads specified by a previous call to [cuFuncSetBlockShape\(\)](#).

The block shape, dynamic shared memory size, and parameter information must be set using [cuFuncSetBlockShape\(\)](#), [cuFuncSetSharedSize\(\)](#), [cuParamSetSize\(\)](#), [cuParamSeti\(\)](#), [cuParamSetf\(\)](#), and [cuParamSetv\(\)](#) prior to calling this function.

Launching a function via [cuLaunchKernel\(\)](#) invalidates the function's block shape, dynamic shared memory size, and parameter information. After launching via `cuLaunchKernel`, this state must be re-initialized prior to calling this function. Failure to do so results in undefined behavior.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuFuncSetBlockShape](#), [cuFuncSetSharedSize](#), [cuFuncGetAttribute](#), [cuParamSetSize](#),
[cuParamSetf](#), [cuParamSeti](#), [cuParamSetv](#), [cuLaunch](#), [cuLaunchGridAsync](#), [cuLaunchKernel](#)

CUresult cuLaunchGridAsync (CUfunction f, int grid_width, int grid_height, CUstream hStream)

Launches a CUDA function.

Parameters**f**

- Kernel to launch

grid_width

- Width of grid in blocks

grid_height

- Height of grid in blocks

hStream

- Stream identifier

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_HANDLE](#),
[CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_LAUNCH_FAILED](#),
[CUDA_ERROR_LAUNCH_OUT_OF_RESOURCES](#), [CUDA_ERROR_LAUNCH_TIMEOUT](#),
[CUDA_ERROR_LAUNCH_INCOMPATIBLE_TEXTURING](#),
[CUDA_ERROR_SHARED_OBJECT_INIT_FAILED](#)

Description

Deprecated

Invokes the kernel `f` on a `grid_width` x `grid_height` grid of blocks. Each block contains the number of threads specified by a previous call to [cuFuncSetBlockShape\(\)](#).

The block shape, dynamic shared memory size, and parameter information must be set using [cuFuncSetBlockShape\(\)](#), [cuFuncSetSharedSize\(\)](#), [cuParamSetSize\(\)](#), [cuParamSeti\(\)](#), [cuParamSetf\(\)](#), and [cuParamSetv\(\)](#) prior to calling this function.

Launching a function via [cuLaunchKernel\(\)](#) invalidates the function's block shape, dynamic shared memory size, and parameter information. After launching via `cuLaunchKernel`, this state must be re-initialized prior to calling this function. Failure to do so results in undefined behavior.

**Note:**

- ▶ In certain cases where cubins are created with no ABI (i.e., using `ptxas --abi-compile no`), this function may serialize kernel launches. The CUDA driver retains asynchronous behavior by growing the per-thread stack as needed per launch and not shrinking it afterwards.
- ▶ This function uses standard [default stream](#) semantics.
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuFuncSetBlockShape](#), [cuFuncSetSharedSize](#), [cuFuncGetAttribute](#), [cuParamSetSize](#),
[cuParamSetf](#), [cuParamSeti](#), [cuParamSetv](#), [cuLaunch](#), [cuLaunchGrid](#), [cuLaunchKernel](#)

CUresult cuParamSetf (CUfunction hfunc, int offset, float value)

Adds a floating-point parameter to the function's argument list.

Parameters

hfunc

- Kernel to add parameter to

offset

- Offset to add parameter to argument list

value

- Value of parameter

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Deprecated

Sets a floating-point parameter that will be specified the next time the kernel corresponding to `hfunc` will be invoked. `offset` is a byte offset.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuFuncSetBlockShape](#), [cuFuncSetSharedSize](#), [cuFuncGetAttribute](#), [cuParamSetSize](#), [cuParamSeti](#), [cuParamSetv](#), [cuLaunch](#), [cuLaunchGrid](#), [cuLaunchGridAsync](#), [cuLaunchKernel](#)

CUresult cuParamSeti (CUfunction hfunc, int offset, unsigned int value)

Adds an integer parameter to the function's argument list.

Parameters

hfunc

- Kernel to add parameter to

offset

- Offset to add parameter to argument list

value

- Value of parameter

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

[Deprecated](#)

Sets an integer parameter that will be specified the next time the kernel corresponding to `hfunc` will be invoked. `offset` is a byte offset.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuFuncSetBlockShape](#), [cuFuncSetSharedSize](#), [cuFuncGetAttribute](#), [cuParamSetSize](#),
[cuParamSetf](#), [cuParamSetv](#), [cuLaunch](#), [cuLaunchGrid](#), [cuLaunchGridAsync](#), [cuLaunchKernel](#)

CUresult cuParamSetSize (CUfunction hfunc, unsigned int numbytes)

Sets the parameter size for the function.

Parameters**hfunc**

- Kernel to set parameter size for

numbytes

- Size of parameter list in bytes

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

[Deprecated](#)

Sets through `numbytes` the total size in bytes needed by the function parameters of the kernel corresponding to `hfunc`.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuFuncSetBlockShape](#), [cuFuncSetSharedSize](#), [cuFuncGetAttribute](#), [cuParamSetf](#), [cuParamSeti](#), [cuParamSetv](#), [cuLaunch](#), [cuLaunchGrid](#), [cuLaunchGridAsync](#), [cuLaunchKernel](#)

CUresult cuParamSetTexRef (CUfunction hfunc, int texunit, CUtexref hTexRef)

Adds a texture-reference to the function's argument list.

Parameters

hfunc

- Kernel to add texture-reference to

texunit

- Texture unit (must be [CU_PARAM_TR_DEFAULT](#))

hTexRef

- Texture-reference to add to argument list

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Deprecated

Makes the CUDA array or linear memory bound to the texture reference `hTexRef` available to a device program as a texture. In this version of CUDA, the texture-reference must be obtained via [cuModuleGetTexRef\(\)](#) and the `texunit` parameter must be set to [CU_PARAM_TR_DEFAULT](#).

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

CUresult cuParamSetv (CUfunction hfunc, int offset, void *ptr, unsigned int numbytes)

Adds arbitrary data to the function's argument list.

Parameters

hfunc

- Kernel to add data to

offset

- Offset to add data to argument list

ptr

- Pointer to arbitrary data

numbytes

- Size of data to copy in bytes

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Deprecated

Copies an arbitrary amount of data (specified in `numbytes`) from `ptr` into the parameter space of the kernel corresponding to `hfunc`. `offset` is a byte offset.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuFuncSetBlockShape](#), [cuFuncSetSharedSize](#), [cuFuncGetAttribute](#), [cuParamSetSize](#), [cuParamSetf](#), [cuParamSeti](#), [cuLaunch](#), [cuLaunchGrid](#), [cuLaunchGridAsync](#), [cuLaunchKernel](#)

6.21. Graph Management

This section describes the graph management functions of the low-level CUDA driver application programming interface.

```
CUresult cuGraphAddChildGraphNode (CUgraphNode
*phGraphNode, CUgraph hGraph, const CUgraphNode
*dependencies, size_t numDependencies, CUgraph
childGraph)
```

Creates a child graph node and adds it to a graph.

Parameters

phGraphNode

- Returns newly created node

hGraph

- Graph to which to add the node

dependencies

- Dependencies of the node

numDependencies

- Number of dependencies

childGraph

- The graph to clone into this node


Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_VALUE](#),

Description

Creates a new node which executes an embedded graph, and adds it to `hGraph` with `numDependencies` dependencies specified via `dependencies`. It is possible for `numDependencies` to be 0, in which case the node will be placed at the root of the graph. `dependencies` may not have any duplicate entries. A handle to the new node will be returned in `phGraphNode`.

The node executes an embedded child graph. The child graph is cloned in this call.



Note:

- ▶ Graph objects are not threadsafe. [More here](#).
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphChildGraphNodeGetGraph](#), [cuGraphCreate](#), [cuGraphDestroyNode](#),
[cuGraphAddEmptyNode](#), [cuGraphAddKernelNode](#), [cuGraphAddHostNode](#),
[cuGraphAddMemcpyNode](#), [cuGraphAddMemsetNode](#), [cuGraphClone](#)

CUresult cuGraphAddDependencies (CUgraph hGraph, const CUgraphNode *from, const CUgraphNode *to, size_t numDependencies)

Adds dependency edges to a graph.

Parameters

hGraph

- Graph to which dependencies are added

from

- Array of nodes that provide the dependencies

to

- Array of dependent nodes

numDependencies

- Number of dependencies to be added

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

The number of dependencies to be added is defined by `numDependencies`. Elements in `from` and `to` at corresponding indices define a dependency. Each node in `from` and `to` must belong to `hGraph`.

If `numDependencies` is 0, elements in `from` and `to` will be ignored. Specifying an existing dependency will return an error.



Note:

- ▶ Graph objects are not threadsafe. [More here](#).
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphRemoveDependencies](#), [cuGraphGetEdges](#), [cuGraphNodeGetDependencies](#),
[cuGraphNodeGetDependentNodes](#)

CUresult cuGraphAddEmptyNode (CUgraphNode *phGraphNode, CUgraph hGraph, const CUgraphNode *dependencies, size_t numDependencies)

Creates an empty node and adds it to a graph.

Parameters

phGraphNode

- Returns newly created node

hGraph

- Graph to which to add the node

dependencies

- Dependencies of the node

numDependencies

- Number of dependencies

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_VALUE](#),

Description

Creates a new node which performs no operation, and adds it to hGraph with numDependencies dependencies specified via dependencies. It is possible for numDependencies to be 0, in which case the node will be placed at the root of the graph. dependencies may not have any duplicate entries. A handle to the new node will be returned in phGraphNode.

An empty node performs no operation during execution, but can be used for transitive ordering. For example, a phased execution graph with 2 groups of n nodes with a barrier between them can be represented using an empty node and 2*n dependency edges, rather than no empty node and n^2 dependency edges.



Note:

- ▶ Graph objects are not threadsafe. [More here](#).
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphCreate](#), [cuGraphDestroyNode](#), [cuGraphAddChildGraphNode](#), [cuGraphAddKernelNode](#), [cuGraphAddHostNode](#), [cuGraphAddMemcpyNode](#), [cuGraphAddMemsetNode](#)

```
CUresult cuGraphAddEventRecordNode
(CUgraphNode *phGraphNode, CUgraph hGraph,
const CUgraphNode *dependencies, size_t
numDependencies, CUevent event)
```

Creates an event record node and adds it to a graph.

Parameters

phGraphNode

- Returns newly created node

hGraph

- Graph to which to add the node

dependencies

- Dependencies of the node

numDependencies

- Number of dependencies

event

- Event for the node


Returns

CUDA_SUCCESS, CUDA_ERROR_DEINITIALIZED, CUDA_ERROR_NOT_INITIALIZED,
CUDA_ERROR_NOT_SUPPORTED, CUDA_ERROR_INVALID_VALUE

Description

Creates a new event record node and adds it to `hGraph` with `numDependencies` dependencies specified via `dependencies` and event specified in `event`. It is possible for `numDependencies` to be 0, in which case the node will be placed at the root of the graph. `dependencies` may not have any duplicate entries. A handle to the new node will be returned in `phGraphNode`.

Each launch of the graph will record `event` to capture execution of the node's dependencies.



Note:

- ▶ Graph objects are not threadsafe. [More here.](#)
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphAddEventWaitNode](#), [cuEventRecordWithFlags](#), [cuStreamWaitEvent](#), [cuGraphCreate](#), [cuGraphDestroyNode](#), [cuGraphAddChildGraphNode](#), [cuGraphAddEmptyNode](#), [cuGraphAddKernelNode](#), [cuGraphAddMemcpyNode](#), [cuGraphAddMemsetNode](#),

CUresult cuGraphAddEventWaitNode (CUgraphNode *phGraphNode, CUgraph hGraph, const CUgraphNode *dependencies, size_t numDependencies, CUevent event)

Creates an event wait node and adds it to a graph.

Parameters

phGraphNode

- Returns newly created node

hGraph

- Graph to which to add the node

dependencies

- Dependencies of the node

numDependencies

- Number of dependencies

event

- Event for the node

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_NOT_SUPPORTED](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Creates a new event wait node and adds it to hGraph with numDependencies dependencies specified via dependencies and event specified in event. It is possible for numDependencies to be 0, in which case the node will be placed at the root of the graph. dependencies may not have any duplicate entries. A handle to the new node will be returned in phGraphNode.

The graph node will wait for all work captured in event. See [cuEventRecord\(\)](#) for details on what is captured by an event. event may be from a different context or device than the launch stream.



Note:

▶ Graph objects are not threadsafe. [More here.](#)

► Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphAddEventRecordNode](#), [cuEventRecordWithFlags](#), [cuStreamWaitEvent](#), [cuGraphCreate](#), [cuGraphDestroyNode](#), [cuGraphAddChildGraphNode](#), [cuGraphAddEmptyNode](#), [cuGraphAddKernelNode](#), [cuGraphAddMemcpyNode](#), [cuGraphAddMemsetNode](#),

CUresult

```
cuGraphAddExternalSemaphoresSignalNode
(CUgraphNode *phGraphNode, CUgraph
hGraph, const CUgraphNode *dependencies,
size_t numDependencies, const
CUDA_EXT_SEM_SIGNAL_NODE_PARAMS
*nodeParams)
```

Creates an external semaphore signal node and adds it to a graph.

Parameters

phGraphNode

- Returns newly created node

hGraph

- Graph to which to add the node

dependencies

- Dependencies of the node

numDependencies

- Number of dependencies

nodeParams

- Parameters for the node

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_NOT_SUPPORTED](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Creates a new external semaphore signal node and adds it to hGraph with numDependencies dependencies specified via dependencies and arguments specified in nodeParams. It is possible for numDependencies to be 0, in which case the node will be placed at the root of the graph. dependencies may not have any duplicate entries. A handle to the new node will be returned in phGraphNode.

Performs a signal operation on a set of externally allocated semaphore objects when the node is launched. The operation(s) will occur after all of the node's dependencies have completed.

**Note:**

- ▶ Graph objects are not threadsafe. [More here.](#)
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphExternalSemaphoresSignalNodeGetParams](#),
[cuGraphExternalSemaphoresSignalNodeSetParams](#),
[cuGraphExecExternalSemaphoresSignalNodeSetParams](#),
[cuGraphAddExternalSemaphoresWaitNode](#), [cuImportExternalSemaphore](#),
[cuSignalExternalSemaphoresAsync](#), [cuWaitExternalSemaphoresAsync](#), [cuGraphCreate](#),
[cuGraphDestroyNode](#), [cuGraphAddEventRecordNode](#), [cuGraphAddEventWaitNode](#),
[cuGraphAddChildGraphNode](#), [cuGraphAddEmptyNode](#), [cuGraphAddKernelNode](#),
[cuGraphAddMemcpyNode](#), [cuGraphAddMemsetNode](#),

CUresult cuGraphAddExternalSemaphoresWaitNode
(CUgraphNode *phGraphNode, CUgraph
hGraph, const CUgraphNode *dependencies,
size_t numDependencies, const
CUDA_EXT_SEM_WAIT_NODE_PARAMS
***nodeParams)**

Creates an external semaphore wait node and adds it to a graph.

Parameters**phGraphNode**

- Returns newly created node

hGraph

- Graph to which to add the node

dependencies

- Dependencies of the node

numDependencies

- Number of dependencies

nodeParams

- Parameters for the node

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_NOT_SUPPORTED](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Creates a new external semaphore wait node and adds it to `hGraph` with `numDependencies` dependencies specified via `dependencies` and arguments specified in `nodeParams`. It is possible for `numDependencies` to be 0, in which case the node will be placed at the root of the graph. `dependencies` may not have any duplicate entries. A handle to the new node will be returned in `phGraphNode`.

Performs a wait operation on a set of externally allocated semaphore objects when the node is launched. The node's dependencies will not be launched until the wait operation has completed.



Note:

- ▶ Graph objects are not threadsafe. [More here](#).
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphExternalSemaphoresWaitNodeGetParams](#),
[cuGraphExternalSemaphoresWaitNodeSetParams](#),
[cuGraphExecExternalSemaphoresWaitNodeSetParams](#),
[cuGraphAddExternalSemaphoresSignalNode](#), [cuImportExternalSemaphore](#),
[cuSignalExternalSemaphoresAsync](#), [cuWaitExternalSemaphoresAsync](#), [cuGraphCreate](#),
[cuGraphDestroyNode](#), [cuGraphAddEventRecordNode](#), [cuGraphAddEventWaitNode](#),
[cuGraphAddChildGraphNode](#), [cuGraphAddEmptyNode](#), [cuGraphAddKernelNode](#),
[cuGraphAddMemcpyNode](#), [cuGraphAddMemsetNode](#),

```
CUresult cuGraphAddHostNode (CUgraphNode
*phGraphNode, CUgraph hGraph, const CUgraphNode
*dependencies, size_t numDependencies, const
CUDA_HOST_NODE_PARAMS *nodeParams)
```

Creates a host execution node and adds it to a graph.

Parameters

phGraphNode

- Returns newly created node

hGraph

- Graph to which to add the node

dependencies

- Dependencies of the node

numDependencies

- Number of dependencies

nodeParams

- Parameters for the host node

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_NOT_SUPPORTED](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Creates a new CPU execution node and adds it to `hGraph` with `numDependencies` dependencies specified via `dependencies` and arguments specified in `nodeParams`. It is possible for `numDependencies` to be 0, in which case the node will be placed at the root of the graph. `dependencies` may not have any duplicate entries. A handle to the new node will be returned in `phGraphNode`.

When the graph is launched, the node will invoke the specified CPU function. Host nodes are not supported under MPS with pre-Volta GPUs.



Note:

- ▶ Graph objects are not threadsafe. [More here](#).
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuLaunchHostFunc](#), [cuGraphHostNodeGetParams](#), [cuGraphHostNodeSetParams](#),
[cuGraphCreate](#), [cuGraphDestroyNode](#), [cuGraphAddChildGraphNode](#), [cuGraphAddEmptyNode](#),
[cuGraphAddKernelNode](#), [cuGraphAddMemcpyNode](#), [cuGraphAddMemsetNode](#)

CUresult cuGraphAddKernelNode (CUgraphNode *phGraphNode, CUgraph hGraph, const CUgraphNode *dependencies, size_t numDependencies, const CUDA_KERNEL_NODE_PARAMS *nodeParams)

Creates a kernel execution node and adds it to a graph.

Parameters

phGraphNode

- Returns newly created node

hGraph

- Graph to which to add the node

dependencies

- Dependencies of the node

numDependencies

- Number of dependencies

nodeParams

- Parameters for the GPU execution node

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_VALUE](#)

Description

Creates a new kernel execution node and adds it to hGraph with numDependencies dependencies specified via dependencies and arguments specified in nodeParams. It is possible for numDependencies to be 0, in which case the node will be placed at the root of the graph. dependencies may not have any duplicate entries. A handle to the new node will be returned in phGraphNode.

The CUDA_KERNEL_NODE_PARAMS structure is defined as:

```
↑ typedef struct CUDA_KERNEL_NODE_PARAMS_st {
    CUfunction func;
    unsigned int gridDimX;
    unsigned int gridDimY;
    unsigned int gridDimZ;
    unsigned int blockDimX;
    unsigned int blockDimY;
    unsigned int blockDimZ;
    unsigned int sharedMemBytes;
    void **kernelParams;
```

```
void **extra;
} CUDA\_KERNEL\_NODE\_PARAMS;
```

When the graph is launched, the node will invoke kernel `func` on a (`gridDimX` x `gridDimY` x `gridDimZ`) grid of blocks. Each block contains (`blockDimX` x `blockDimY` x `blockDimZ`) threads.

`sharedMemBytes` sets the amount of dynamic shared memory that will be available to each thread block.

Kernel parameters to `func` can be specified in one of two ways:

- 1) Kernel parameters can be specified via `kernelParams`. If the kernel has `N` parameters, then `kernelParams` needs to be an array of `N` pointers. Each pointer, from `kernelParams[0]` to `kernelParams[N-1]`, points to the region of memory from which the actual parameter will be copied. The number of kernel parameters and their offsets and sizes do not need to be specified as that information is retrieved directly from the kernel's image.
- 2) Kernel parameters for non-cooperative kernels can also be packaged by the application into a single buffer that is passed in via `extra`. This places the burden on the application of knowing each kernel parameter's size and alignment/padding within the buffer. The `extra` parameter exists to allow this function to take additional less commonly used arguments. `extra` specifies a list of names of extra settings and their corresponding values. Each extra setting name is immediately followed by the corresponding value. The list must be terminated with either `NULL` or `CU_LAUNCH_PARAM_END`.

- ▶ [CU_LAUNCH_PARAM_END](#), which indicates the end of the `extra` array;
- ▶ [CU_LAUNCH_PARAM_BUFFER_POINTER](#), which specifies that the next value in `extra` will be a pointer to a buffer containing all the kernel parameters for launching kernel `func`;
- ▶ [CU_LAUNCH_PARAM_BUFFER_SIZE](#), which specifies that the next value in `extra` will be a pointer to a `size_t` containing the size of the buffer specified with [CU_LAUNCH_PARAM_BUFFER_POINTER](#);

The error [CUDA_ERROR_INVALID_VALUE](#) will be returned if kernel parameters are specified with both `kernelParams` and `extra` (i.e. both `kernelParams` and `extra` are non-NULL). [CUDA_ERROR_INVALID_VALUE](#) will be returned if `extra` is used for a cooperative kernel.

The `kernelParams` or `extra` array, as well as the argument values it points to, are copied during this call.



Note:

Kernels launched using graphs must not use texture and surface references. Reading or writing through any texture or surface reference is undefined behavior. This restriction does not apply to texture and surface objects.

**Note:**

- ▶ Graph objects are not threadsafe. [More here.](#)
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuLaunchKernel](#), [cuLaunchCooperativeKernel](#), [cuGraphKernelNodeGetParams](#),
[cuGraphKernelNodeSetParams](#), [cuGraphCreate](#), [cuGraphDestroyNode](#),
[cuGraphAddChildGraphNode](#), [cuGraphAddEmptyNode](#), [cuGraphAddHostNode](#),
[cuGraphAddMemcpyNode](#), [cuGraphAddMemsetNode](#)

```
CUresult cuGraphAddMemcpyNode (CUgraphNode
*phGraphNode, CUgraph hGraph, const CUgraphNode
*dependencies, size_t numDependencies, const
CUDA_MEMCPY3D *copyParams, CUcontext ctx)
```

Creates a memcpy node and adds it to a graph.

Parameters**phGraphNode**

- Returns newly created node

hGraph

- Graph to which to add the node

dependencies

- Dependencies of the node

numDependencies

- Number of dependencies

copyParams

- Parameters for the memory copy

ctx

- Context on which to run the node

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_VALUE](#)

Description

Creates a new memcpy node and adds it to hGraph with numDependencies dependencies specified via dependencies. It is possible for numDependencies to be 0, in which case

the node will be placed at the root of the graph. `dependencies` may not have any duplicate entries. A handle to the new node will be returned in `phGraphNode`.

When the graph is launched, the node will perform the memcopy described by `copyParams`. See [cuMemcpy3D\(\)](#) for a description of the structure and its restrictions.

Memcpy nodes have some additional restrictions with regards to managed memory, if the system contains at least one device which has a zero value for the device attribute [CU_DEVICE_ATTRIBUTE_CONCURRENT_MANAGED_ACCESS](#). If one or more of the operands refer to managed memory, then using the memory type [CU_MEMORYTYPE_UNIFIED](#) is disallowed for those operand(s). The managed memory will be treated as residing on either the host or the device, depending on which memory type is specified.



Note:

- ▶ Graph objects are not threadsafe. [More here.](#)
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuMemcpy3D](#), [cuGraphMemcpyNodeGetParams](#), [cuGraphMemcpyNodeSetParams](#), [cuGraphCreate](#), [cuGraphDestroyNode](#), [cuGraphAddChildGraphNode](#), [cuGraphAddEmptyNode](#), [cuGraphAddKernelNode](#), [cuGraphAddHostNode](#), [cuGraphAddMemsetNode](#)

```
CUresult cuGraphAddMemsetNode (CUgraphNode
*phGraphNode, CUgraph hGraph, const CUgraphNode
*dependencies, size_t numDependencies, const
CUDA_MEMSET_NODE_PARAMS *memsetParams,
CUcontext ctx)
```

Creates a memset node and adds it to a graph.

Parameters

phGraphNode

- Returns newly created node

hGraph

- Graph to which to add the node

dependencies

- Dependencies of the node

numDependencies

- Number of dependencies

memsetParams

- Parameters for the memory set

ctx

- Context on which to run the node


Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_CONTEXT](#)

Description

Creates a new memset node and adds it to `hGraph` with `numDependencies` dependencies specified via `dependencies`. It is possible for `numDependencies` to be 0, in which case the node will be placed at the root of the graph. `dependencies` may not have any duplicate entries. A handle to the new node will be returned in `phGraphNode`.

The element size must be 1, 2, or 4 bytes. When the graph is launched, the node will perform the memset described by `memsetParams`.



Note:

- ▶ Graph objects are not threadsafe. [More here](#).
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuMemsetD2D32](#), [cuGraphMemsetNodeGetParams](#), [cuGraphMemsetNodeSetParams](#), [cuGraphCreate](#), [cuGraphDestroyNode](#), [cuGraphAddChildGraphNode](#), [cuGraphAddEmptyNode](#), [cuGraphAddKernelNode](#), [cuGraphAddHostNode](#), [cuGraphAddMemcpyNode](#)

CUresult cuGraphChildGraphNodeGetGraph (CUgraphNode hNode, CUgraph *phGraph)

Gets a handle to the embedded graph of a child graph node.

Parameters**hNode**

- Node to get the embedded graph for

phGraph

- Location to store a handle to the graph

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_VALUE](#),

Description

Gets a handle to the embedded graph in a child graph node. This call does not clone the graph. Changes to the graph will be reflected in the node, and the node retains ownership of the graph.



Note:

- ▶ Graph objects are not threadsafe. [More here](#).
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphAddChildGraphNode](#), [cuGraphNodeFindInClone](#)

CUresult cuGraphClone (CUgraph *phGraphClone, CUgraph originalGraph)

Clones a graph.

Parameters

phGraphClone

- Returns newly created cloned graph

originalGraph

- Graph to clone

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_OUT_OF_MEMORY](#)

Description

This function creates a copy of `originalGraph` and returns it in `phGraphClone`. All parameters are copied into the cloned graph. The original graph may be modified after this call without affecting the clone.

Child graph nodes in the original graph are recursively copied into the clone.

**Note:**

- ▶ Graph objects are not threadsafe. [More here.](#)
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphCreate](#), [cuGraphNodeFindInClone](#)

CUresult cuGraphCreate (CUgraph *phGraph, unsigned int flags)

Creates a graph.

Parameters

phGraph

- Returns newly created graph

flags

- Graph creation flags, must be 0

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_OUT_OF_MEMORY](#)

Description

Creates an empty graph, which is returned via phGraph.

**Note:**

- ▶ Graph objects are not threadsafe. [More here.](#)
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphAddChildGraphNode](#), [cuGraphAddEmptyNode](#), [cuGraphAddKernelNode](#), [cuGraphAddHostNode](#), [cuGraphAddMemcpyNode](#), [cuGraphAddMemsetNode](#), [cuGraphInstantiate](#), [cuGraphDestroy](#), [cuGraphGetNodes](#), [cuGraphGetRootNodes](#), [cuGraphGetEdges](#), [cuGraphClone](#)

CUresult cuGraphDebugDotPrint (CUgraph hGraph, const char *path, unsigned int flags)

Write a DOT file describing graph structure.

Parameters

hGraph

- The graph to create a DOT file from

path

- The path to write the DOT file to

flags

- Flags from CUgraphDebugDot_flags for specifying which additional node information to write

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_OPERATING_SYSTEM](#)

Description

Using the provided `hGraph`, write to `path` a DOT formatted description of the graph. By default this includes the graph topology, node types, node id, kernel names and memcpy direction. `flags` can be specified to write more detailed information about each node type such as parameter values, kernel attributes, node and function handles.

CUresult cuGraphDestroy (CUgraph hGraph)

Destroys a graph.

Parameters

hGraph

- Graph to destroy

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Destroys the graph specified by `hGraph`, as well as all of its nodes.



Note:

- ▶ Graph objects are not threadsafe. [More here.](#)
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphCreate](#)

CUresult cuGraphDestroyNode (CUgraphNode hNode)

Remove a node from the graph.

Parameters

hNode

- Node to remove

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Removes hNode from its graph. This operation also severs any dependencies of other nodes on hNode and vice versa.

**Note:**

- ▶ Graph objects are not threadsafe. [More here.](#)
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphAddChildGraphNode](#), [cuGraphAddEmptyNode](#), [cuGraphAddKernelNode](#),
[cuGraphAddHostNode](#), [cuGraphAddMemcpyNode](#), [cuGraphAddMemsetNode](#)

CUresult cuGraphEventRecordNodeGetEvent (CUgraphNode hNode, CUevent *event_out)

Returns the event associated with an event record node.

Parameters

hNode

- Node to get the event for

event_out

- Pointer to return the event

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Returns the event of event record node `hNode` in `event_out`.



Note:

- ▶ Graph objects are not threadsafe. [More here](#).
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphAddEventRecordNode](#), [cuGraphEventRecordNodeSetEvent](#),
[cuGraphEventWaitNodeGetEvent](#), [cuEventRecordWithFlags](#), [cuStreamWaitEvent](#)

CUresult cuGraphEventRecordNodeSetEvent (CUgraphNode hNode, CUevent event)

Sets an event record node's event.

Parameters

hNode

- Node to set the event for

event

- Event to use

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_HANDLE](#),
[CUDA_ERROR_OUT_OF_MEMORY](#)

Description

Sets the event of event record node `hNode` to `event`.



Note:

- ▶ Graph objects are not threadsafe. [More here](#).
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphAddEventRecordNode](#), [cuGraphEventRecordNodeGetEvent](#),
[cuGraphEventWaitNodeSetEvent](#), [cuEventRecordWithFlags](#), [cuStreamWaitEvent](#)

CUresult cuGraphEventWaitNodeGetEvent (CUgraphNode hNode, CUevent *event_out)

Returns the event associated with an event wait node.

Parameters**hNode**

- Node to get the event for

event_out

- Pointer to return the event

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_VALUE](#)

Description

Returns the event of event wait node hNode in event_out.

**Note:**

- ▶ Graph objects are not threadsafe. [More here](#).
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphAddEventWaitNode](#), [cuGraphEventWaitNodeSetEvent](#),
[cuGraphEventRecordNodeGetEvent](#), [cuEventRecordWithFlags](#), [cuStreamWaitEvent](#)

CUresult cuGraphEventWaitNodeSetEvent (CUgraphNode hNode, CUevent event)

Sets an event wait node's event.

Parameters**hNode**

- Node to set the event for

event

- Event to use

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_OUT_OF_MEMORY](#)

Description

Sets the event of event wait node `hNode` to `event`.

**Note:**

- ▶ Graph objects are not threadsafe. [More here](#).
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphAddEventWaitNode](#), [cuGraphEventWaitNodeGetEvent](#),
[cuGraphEventRecordNodeSetEvent](#), [cuEventRecordWithFlags](#), [cuStreamWaitEvent](#)

CUresult cuGraphExecChildGraphNodeSetParams (CUgraphExec hGraphExec, CUgraphNode hNode, CUgraph childGraph)

Updates node parameters in the child graph node in the given graphExec.

Parameters**hGraphExec**

- The executable graph in which to set the specified node

hNode

- Host node from the graph which was used to instantiate graphExec

childGraph

- The graph supplying the updated parameters

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#),

Description

Updates the work represented by `hNode` in `hGraphExec` as though the nodes contained in `hNode`'s graph had the parameters contained in `childGraph`'s nodes at instantiation.

`hNode` must remain in the graph which was used to instantiate `hGraphExec`. Changed edges to and from `hNode` are ignored.

The modifications only affect future launches of `hGraphExec`. Already enqueued or running launches of `hGraphExec` are not affected by this call. `hNode` is also not modified by this call.

The topology of `childGraph`, as well as the node insertion order, must match that of the graph contained in `hNode`. See [cuGraphExecUpdate\(\)](#) for a list of restrictions on what can be updated in an instantiated graph. The update is recursive, so child graph nodes contained within the top level child graph will also be updated.



Note:

- ▶ Graph objects are not threadsafe. [More here.](#)
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphAddChildGraphNode](#), [cuGraphChildGraphNodeGetGraph](#),
[cuGraphExecKernelNodeSetParams](#), [cuGraphExecMemcpyNodeSetParams](#),
[cuGraphExecMemsetNodeSetParams](#), [cuGraphExecHostNodeSetParams](#),
[cuGraphExecEventRecordNodeSetEvent](#), [cuGraphExecEventWaitNodeSetEvent](#),
[cuGraphExecExternalSemaphoresSignalNodeSetParams](#),
[cuGraphExecExternalSemaphoresWaitNodeSetParams](#), [cuGraphExecUpdate](#),
[cuGraphInstantiate](#)

CUresult cuGraphExecDestroy (CUgraphExec hGraphExec)

Destroys an executable graph.

Parameters

hGraphExec

- Executable graph to destroy

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_VALUE](#)

Description

Destroys the executable graph specified by `hGraphExec`, as well as all of its executable nodes. If the executable graph is in-flight, it will not be terminated, but rather freed asynchronously on completion.

**Note:**

- ▶ Graph objects are not threadsafe. [More here.](#)
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphInstantiate](#), [cuGraphUpload](#), [cuGraphLaunch](#)

CUresult cuGraphExecEventRecordNodeSetEvent (CUgraphExec hGraphExec, CUgraphNode hNode, CUevent event)

Sets the event for an event record node in the given graphExec.

Parameters

hGraphExec

- The executable graph in which to set the specified node

hNode

- event record node from the graph from which graphExec was instantiated

event

- Updated event to use

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#),

Description

Sets the event of an event record node in an executable graph `hGraphExec`. The node is identified by the corresponding node `hNode` in the non-executable graph, from which the executable graph was instantiated.

The modifications only affect future launches of `hGraphExec`. Already enqueued or running launches of `hGraphExec` are not affected by this call. `hNode` is also not modified by this call.

**Note:**

- ▶ Graph objects are not threadsafe. [More here.](#)
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphAddEventRecordNode](#), [cuGraphEventRecordNodeGetEvent](#),
[cuGraphEventWaitNodeSetEvent](#), [cuEventRecordWithFlags](#), [cuStreamWaitEvent](#),
[cuGraphExecKernelNodeSetParams](#), [cuGraphExecMemcpyNodeSetParams](#),
[cuGraphExecMemsetNodeSetParams](#), [cuGraphExecHostNodeSetParams](#),
[cuGraphExecChildGraphNodeSetParams](#), [cuGraphExecEventWaitNodeSetEvent](#),
[cuGraphExecExternalSemaphoresSignalNodeSetParams](#),
[cuGraphExecExternalSemaphoresWaitNodeSetParams](#), [cuGraphExecUpdate](#),
[cuGraphInstantiate](#)

CUresult cuGraphExecEventWaitNodeSetEvent (CUgraphExec hGraphExec, CUgraphNode hNode, CUevent event)

Sets the event for an event wait node in the given graphExec.

Parameters

hGraphExec

- The executable graph in which to set the specified node

hNode

- event wait node from the graph from which graphExec was instantiated

event

- Updated event to use


Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#),

Description

Sets the event of an event wait node in an executable graph `hGraphExec`. The node is identified by the corresponding node `hNode` in the non-executable graph, from which the executable graph was instantiated.

The modifications only affect future launches of `hGraphExec`. Already enqueued or running launches of `hGraphExec` are not affected by this call. `hNode` is also not modified by this call.



Note:

- ▶ Graph objects are not threadsafe. [More here](#).
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphAddEventWaitNode](#), [cuGraphEventWaitNodeGetEvent](#),
[cuGraphEventRecordNodeSetEvent](#), [cuEventRecordWithFlags](#), [cuStreamWaitEvent](#),
[cuGraphExecKernelNodeSetParams](#), [cuGraphExecMemcpyNodeSetParams](#),
[cuGraphExecMemsetNodeSetParams](#), [cuGraphExecHostNodeSetParams](#),
[cuGraphExecChildGraphNodeSetParams](#), [cuGraphExecEventRecordNodeSetEvent](#),
[cuGraphExecExternalSemaphoresSignalNodeSetParams](#),
[cuGraphExecExternalSemaphoresWaitNodeSetParams](#), [cuGraphExecUpdate](#),
[cuGraphInstantiate](#)

CUresult

cuGraphExecExternalSemaphoresSignalNodeSetParams
 (CUgraphExec hGraphExec, CUgraphNode hNode,
 const CUDA_EXT_SEM_SIGNAL_NODE_PARAMS
 *nodeParams)

Sets the parameters for an external semaphore signal node in the given graphExec.

Parameters

hGraphExec

- The executable graph in which to set the specified node

hNode

- semaphore signal node from the graph from which graphExec was instantiated

nodeParams

- Updated Parameters to set

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#),

Description

Sets the parameters of an external semaphore signal node in an executable graph `hGraphExec`. The node is identified by the corresponding node `hNode` in the non-executable graph, from which the executable graph was instantiated.

`hNode` must not have been removed from the original graph.

The modifications only affect future launches of `hGraphExec`. Already enqueued or running launches of `hGraphExec` are not affected by this call. `hNode` is also not modified by this call.

Changing `nodeParams->numExtSems` is not supported.



Note:

- ▶ Graph objects are not threadsafe. [More here](#).
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphAddExternalSemaphoresSignalNode](#), [cuImportExternalSemaphore](#), [cuSignalExternalSemaphoresAsync](#), [cuWaitExternalSemaphoresAsync](#), [cuGraphExecKernelNodeSetParams](#), [cuGraphExecMemcpyNodeSetParams](#), [cuGraphExecMemsetNodeSetParams](#), [cuGraphExecHostNodeSetParams](#), [cuGraphExecChildGraphNodeSetParams](#), [cuGraphExecEventRecordNodeSetEvent](#), [cuGraphExecEventWaitNodeSetEvent](#), [cuGraphExecExternalSemaphoresWaitNodeSetParams](#), [cuGraphExecUpdate](#), [cuGraphInstantiate](#)

CUresult

cuGraphExecExternalSemaphoresWaitNodeSetParams
 (CUgraphExec hGraphExec, CUgraphNode hNode,
 const CUDA_EXT_SEM_WAIT_NODE_PARAMS
 *nodeParams)

Sets the parameters for an external semaphore wait node in the given graphExec.

Parameters

hGraphExec

- The executable graph in which to set the specified node

hNode

- semaphore wait node from the graph from which graphExec was instantiated

nodeParams

- Updated Parameters to set

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#),

Description

Sets the parameters of an external semaphore wait node in an executable graph `hGraphExec`. The node is identified by the corresponding node `hNode` in the non-executable graph, from which the executable graph was instantiated.

`hNode` must not have been removed from the original graph.

The modifications only affect future launches of `hGraphExec`. Already enqueued or running launches of `hGraphExec` are not affected by this call. `hNode` is also not modified by this call.

Changing `nodeParams->numExtSems` is not supported.

**Note:**

- ▶ Graph objects are not threadsafe. [More here.](#)
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphAddExternalSemaphoresWaitNode](#), [cuImportExternalSemaphore](#),
[cuSignalExternalSemaphoresAsync](#), [cuWaitExternalSemaphoresAsync](#),
[cuGraphExecKernelNodeSetParams](#), [cuGraphExecMemcpyNodeSetParams](#),
[cuGraphExecMemsetNodeSetParams](#), [cuGraphExecHostNodeSetParams](#),
[cuGraphExecChildGraphNodeSetParams](#), [cuGraphExecEventRecordNodeSetEvent](#),
[cuGraphExecEventWaitNodeSetEvent](#),
[cuGraphExecExternalSemaphoresSignalNodeSetParams](#), [cuGraphExecUpdate](#),
[cuGraphInstantiate](#)

CUresult cuGraphExecHostNodeSetParams (CUgraphExec hGraphExec, CUgraphNode hNode, const CUDA_HOST_NODE_PARAMS *nodeParams)

Sets the parameters for a host node in the given graphExec.

Parameters

hGraphExec

- The executable graph in which to set the specified node

hNode

- Host node from the graph which was used to instantiate graphExec

nodeParams

- The updated parameters to set

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#),

Description

Updates the work represented by hNode in hGraphExec as though hNode had contained nodeParams at instantiation. hNode must remain in the graph which was used to instantiate hGraphExec. Changed edges to and from hNode are ignored.

The modifications only affect future launches of hGraphExec. Already enqueued or running launches of hGraphExec are not affected by this call. hNode is also not modified by this call.

**Note:**

- ▶ Graph objects are not threadsafe. [More here](#).
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphAddHostNode](#), [cuGraphHostNodeSetParams](#),
[cuGraphExecKernelNodeSetParams](#), [cuGraphExecMemcpyNodeSetParams](#),
[cuGraphExecMemsetNodeSetParams](#), [cuGraphExecChildGraphNodeSetParams](#),
[cuGraphExecEventRecordNodeSetEvent](#), [cuGraphExecEventWaitNodeSetEvent](#),
[cuGraphExecExternalSemaphoresSignalNodeSetParams](#),
[cuGraphExecExternalSemaphoresWaitNodeSetParams](#), [cuGraphExecUpdate](#),
[cuGraphInstantiate](#)

CUresult cuGraphExecKernelNodeSetParams (CUgraphExec hGraphExec, CUgraphNode hNode, const CUDA_KERNEL_NODE_PARAMS *nodeParams)

Sets the parameters for a kernel node in the given graphExec.

Parameters

hGraphExec

- The executable graph in which to set the specified node

hNode

- kernel node from the graph from which graphExec was instantiated

nodeParams

- Updated Parameters to set

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#),

Description

Sets the parameters of a kernel node in an executable graph hGraphExec. The node is identified by the corresponding node hNode in the non-executable graph, from which the executable graph was instantiated.

hNode must not have been removed from the original graph. The func field of nodeParams cannot be modified and must match the original value. All other values can be modified.

The modifications only affect future launches of hGraphExec. Already enqueued or running launches of hGraphExec are not affected by this call. hNode is also not modified by this call.

**Note:**

- ▶ Graph objects are not threadsafe. [More here.](#)
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphAddKernelNode](#), [cuGraphKernelNodeSetParams](#),
[cuGraphExecMemcpyNodeSetParams](#), [cuGraphExecMemsetNodeSetParams](#),
[cuGraphExecHostNodeSetParams](#), [cuGraphExecChildGraphNodeSetParams](#),
[cuGraphExecEventRecordNodeSetEvent](#), [cuGraphExecEventWaitNodeSetEvent](#),
[cuGraphExecExternalSemaphoresSignalNodeSetParams](#),
[cuGraphExecExternalSemaphoresWaitNodeSetParams](#), [cuGraphExecUpdate](#),
[cuGraphInstantiate](#)

CUresult cuGraphExecMemcpyNodeSetParams (CUgraphExec hGraphExec, CUgraphNode hNode, const CUDA_MEMCPY3D *copyParams, CUcontext ctx)

Sets the parameters for a memcpy node in the given graphExec.

Parameters

hGraphExec

- The executable graph in which to set the specified node

hNode

- Memcpy node from the graph which was used to instantiate graphExec

copyParams

- The updated parameters to set

ctx

- Context on which to run the node

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#),

Description

Updates the work represented by hNode in hGraphExec as though hNode had contained copyParams at instantiation. hNode must remain in the graph which was used to instantiate hGraphExec. Changed edges to and from hNode are ignored.

The source and destination memory in `copyParams` must be allocated from the same contexts as the original source and destination memory. Both the instantiation-time memory operands and the memory operands in `copyParams` must be 1-dimensional. Zero-length operations are not supported.

The modifications only affect future launches of `hGraphExec`. Already enqueued or running launches of `hGraphExec` are not affected by this call. `hNode` is also not modified by this call.

Returns `CUDA_ERROR_INVALID_VALUE` if the memory operands' mappings changed or either the original or new memory operands are multidimensional.



Note:

- ▶ Graph objects are not threadsafe. [More here.](#)
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphAddMemcpyNode](#), [cuGraphMemcpyNodeSetParams](#),
[cuGraphExecKernelNodeSetParams](#), [cuGraphExecMemsetNodeSetParams](#),
[cuGraphExecHostNodeSetParams](#), [cuGraphExecChildGraphNodeSetParams](#),
[cuGraphExecEventRecordNodeSetEvent](#), [cuGraphExecEventWaitNodeSetEvent](#),
[cuGraphExecExternalSemaphoresSignalNodeSetParams](#),
[cuGraphExecExternalSemaphoresWaitNodeSetParams](#), [cuGraphExecUpdate](#),
[cuGraphInstantiate](#)

CUresult cuGraphExecMemsetNodeSetParams
(CUgraphExec hGraphExec, CUgraphNode
hNode, const CUDA_MEMSET_NODE_PARAMS
***memsetParams, CUcontext ctx)**

Sets the parameters for a memset node in the given graphExec.

Parameters

hGraphExec

- The executable graph in which to set the specified node

hNode

- Memset node from the graph which was used to instantiate graphExec

memsetParams

- The updated parameters to set

ctx

- Context on which to run the node

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#),

Description

Updates the work represented by `hNode` in `hGraphExec` as though `hNode` had contained `memsetParams` at instantiation. `hNode` must remain in the graph which was used to instantiate `hGraphExec`. Changed edges to and from `hNode` are ignored.

The destination memory in `memsetParams` must be allocated from the same contexts as the original destination memory. Both the instantiation-time memory operand and the memory operand in `memsetParams` must be 1-dimensional. Zero-length operations are not supported.

The modifications only affect future launches of `hGraphExec`. Already enqueued or running launches of `hGraphExec` are not affected by this call. `hNode` is also not modified by this call.

Returns `CUDA_ERROR_INVALID_VALUE` if the memory operand's mappings changed or either the original or new memory operand are multidimensional.



Note:

- ▶ Graph objects are not threadsafe. [More here](#).
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphAddMemsetNode](#), [cuGraphMemsetNodeSetParams](#),
[cuGraphExecKernelNodeSetParams](#), [cuGraphExecMemcpyNodeSetParams](#),
[cuGraphExecHostNodeSetParams](#), [cuGraphExecChildGraphNodeSetParams](#),
[cuGraphExecEventRecordNodeSetEvent](#), [cuGraphExecEventWaitNodeSetEvent](#),
[cuGraphExecExternalSemaphoresSignalNodeSetParams](#),
[cuGraphExecExternalSemaphoresWaitNodeSetParams](#), [cuGraphExecUpdate](#),
[cuGraphInstantiate](#)

CUresult cuGraphExecUpdate (CUgraphExec hGraphExec, CUgraph hGraph, CUgraphNode *hErrorNode_out, CUgraphExecUpdateResult *updateResult_out)

Check whether an executable graph can be updated with a graph and perform the update if possible.

Parameters

hGraphExec

The instantiated graph to be updated

hGraph

The graph containing the updated parameters

hErrorNode_out

The node which caused the permissibility check to forbid the update, if any

updateResult_out

Whether the graph update was permitted. If was forbidden, the reason why

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_GRAPH_EXEC_UPDATE_FAILURE](#),

Description

Updates the node parameters in the instantiated graph specified by `hGraphExec` with the node parameters in a topologically identical graph specified by `hGraph`.

Limitations:

- ▶ Kernel nodes:
 - ▶ The owning context of the function cannot change.
 - ▶ A node whose function originally did not use CUDA dynamic parallelism cannot be updated to a function which uses CDP
- ▶ Memset and memcpy nodes:
 - ▶ The CUDA device(s) to which the operand(s) was allocated/mapped cannot change.
 - ▶ The source/destination memory must be allocated from the same contexts as the original source/destination memory.
 - ▶ Only 1D memsets can be changed.
- ▶ Additional memcpy node restrictions:
 - ▶ Changing either the source or destination memory type (i.e. `CU_MEMORYTYPE_DEVICE`, `CU_MEMORYTYPE_ARRAY`, etc.) is not supported.

- ▶ External semaphore wait nodes and record nodes:
 - ▶ Changing the number of semaphores is not supported.

Note: The API may add further restrictions in future releases. The return code should always be checked.

cuGraphExecUpdate sets `updateResult_out` to `CU_GRAPH_EXEC_UPDATE_ERROR_TOPOLOGY_CHANGED` under the following conditions:

- ▶ The count of nodes directly in `hGraphExec` and `hGraph` differ, in which case `hErrorNode_out` is NULL.
- ▶ A node is deleted in `hGraph` but not its pair from `hGraphExec`, in which case `hErrorNode_out` is NULL.
- ▶ A node is deleted in `hGraphExec` but not its pair from `hGraph`, in which case `hErrorNode_out` is the pairless node from `hGraph`.
- ▶ The dependent nodes of a pair differ, in which case `hErrorNode_out` is the node from `hGraph`.

cuGraphExecUpdate sets `updateResult_out` to:

- ▶ `CU_GRAPH_EXEC_UPDATE_ERROR` if passed an invalid value.
- ▶ `CU_GRAPH_EXEC_UPDATE_ERROR_TOPOLOGY_CHANGED` if the graph topology changed
- ▶ `CU_GRAPH_EXEC_UPDATE_ERROR_NODE_TYPE_CHANGED` if the type of a node changed, in which case `hErrorNode_out` is set to the node from `hGraph`.
- ▶ `CU_GRAPH_EXEC_UPDATE_ERROR_UNSUPPORTED_FUNCTION_CHANGE` if the function changed in an unsupported way(see note above), in which case `hErrorNode_out` is set to the node from `hGraph`
- ▶ `CU_GRAPH_EXEC_UPDATE_ERROR_PARAMETERS_CHANGED` if any parameters to a node changed in a way that is not supported, in which case `hErrorNode_out` is set to the node from `hGraph`.
- ▶ `CU_GRAPH_EXEC_UPDATE_ERROR_NOT_SUPPORTED` if something about a node is unsupported, like the node's type or configuration, in which case `hErrorNode_out` is set to the node from `hGraph`

If `updateResult_out` isn't set in one of the situations described above, the update check passes and `cuGraphExecUpdate` updates `hGraphExec` to match the contents of `hGraph`. If an error happens during the update, `updateResult_out` will be set to `CU_GRAPH_EXEC_UPDATE_ERROR`; otherwise, `updateResult_out` is set to `CU_GRAPH_EXEC_UPDATE_SUCCESS`.

`cuGraphExecUpdate` returns `CUDA_SUCCESS` when the update was performed successfully. It returns `CUDA_ERROR_GRAPH_EXEC_UPDATE_FAILURE` if the graph update was not performed because it included changes which violated constraints specific to instantiated graph update.

**Note:**

- ▶ Graph objects are not threadsafe. [More here.](#)
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphInstantiate](#),

CUresult cuGraphExternalSemaphoresSignalNodeGetParams (CUgraphNode hNode, CUDA_EXT_SEM_SIGNAL_NODE_PARAMS *params_out)

Returns an external semaphore signal node's parameters.

Parameters

hNode

- Node to get the parameters for

params_out

- Pointer to return the parameters

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_VALUE](#)

Description

Returns the parameters of an external semaphore signal node `hNode` in `params_out`. The `extSemArray` and `paramsArray` returned in `params_out`, are owned by the node. This memory remains valid until the node is destroyed or its parameters are modified, and should not be modified directly. Use [cuGraphExternalSemaphoresSignalNodeSetParams](#) to update the parameters of this node.

**Note:**

- ▶ Graph objects are not threadsafe. [More here.](#)
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuLaunchKernel](#), [cuGraphAddExternalSemaphoresSignalNode](#),
[cuGraphExternalSemaphoresSignalNodeSetParams](#),
[cuGraphAddExternalSemaphoresWaitNode](#), [cuSignalExternalSemaphoresAsync](#),
[cuWaitExternalSemaphoresAsync](#)

CUresult

cuGraphExternalSemaphoresSignalNodeSetParams
 (CUgraphNode hNode, const
 CUDA_EXT_SEM_SIGNAL_NODE_PARAMS
 *nodeParams)

Sets an external semaphore signal node's parameters.

Parameters

hNode

- Node to set the parameters for

nodeParams

- Parameters to copy

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_HANDLE](#),
[CUDA_ERROR_OUT_OF_MEMORY](#)

Description

Sets the parameters of an external semaphore signal node hNode to nodeParams.

**Note:**

- ▶ Graph objects are not threadsafe. [More here](#).
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphAddExternalSemaphoresSignalNode](#),
[cuGraphExternalSemaphoresSignalNodeSetParams](#),
[cuGraphAddExternalSemaphoresWaitNode](#), [cuSignalExternalSemaphoresAsync](#),
[cuWaitExternalSemaphoresAsync](#)

CUresult
cuGraphExternalSemaphoresWaitNodeGetParams
 (CUgraphNode hNode,
 CUDA_EXT_SEM_WAIT_NODE_PARAMS
 *params_out)

Returns an external semaphore wait node's parameters.

Parameters

hNode

- Node to get the parameters for

params_out

- Pointer to return the parameters

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_VALUE](#)

Description

Returns the parameters of an external semaphore wait node `hNode` in `params_out`. The `extSemArray` and `paramsArray` returned in `params_out`, are owned by the node. This memory remains valid until the node is destroyed or its parameters are modified, and should not be modified directly. Use [cuGraphExternalSemaphoresSignalNodeSetParams](#) to update the parameters of this node.



Note:

- ▶ Graph objects are not threadsafe. [More here](#).
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuLaunchKernel](#), [cuGraphAddExternalSemaphoresWaitNode](#),
[cuGraphExternalSemaphoresWaitNodeSetParams](#),
[cuGraphAddExternalSemaphoresWaitNode](#), [cuSignalExternalSemaphoresAsync](#),
[cuWaitExternalSemaphoresAsync](#)

CUresult
 cuGraphExternalSemaphoresWaitNodeSetParams
 (CUgraphNode hNode, const
 CUDA_EXT_SEM_WAIT_NODE_PARAMS
 *nodeParams)

Sets an external semaphore wait node's parameters.

Parameters

hNode

- Node to set the parameters for

nodeParams

- Parameters to copy

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_HANDLE](#),
[CUDA_ERROR_OUT_OF_MEMORY](#)

Description

Sets the parameters of an external semaphore wait node hNode to nodeParams.



Note:

- ▶ Graph objects are not threadsafe. [More here](#).
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphAddExternalSemaphoresWaitNode](#),
[cuGraphExternalSemaphoresWaitNodeSetParams](#),
[cuGraphAddExternalSemaphoresWaitNode](#), [cuSignalExternalSemaphoresAsync](#),
[cuWaitExternalSemaphoresAsync](#)

CUresult cuGraphGetEdges (CUgraph hGraph, CUgraphNode *from, CUgraphNode *to, size_t *numEdges)

Returns a graph's dependency edges.

Parameters

hGraph

- Graph to get the edges from

from

- Location to return edge endpoints

to

- Location to return edge endpoints

numEdges

- See description

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Returns a list of `hGraph`'s dependency edges. Edges are returned via corresponding indices in `from` and `to`; that is, the node in `to[i]` has a dependency on the node in `from[i]`. `from` and `to` may both be `NULL`, in which case this function only returns the number of edges in `numEdges`. Otherwise, `numEdges` entries will be filled in. If `numEdges` is higher than the actual number of edges, the remaining entries in `from` and `to` will be set to `NULL`, and the number of edges actually returned will be written to `numEdges`.



Note:

- ▶ Graph objects are not threadsafe. [More here](#).
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphGetNodes](#), [cuGraphGetRootNodes](#), [cuGraphAddDependencies](#), [cuGraphRemoveDependencies](#), [cuGraphNodeGetDependencies](#), [cuGraphNodeGetDependentNodes](#)

CUresult cuGraphGetNodes (CUgraph hGraph, CUgraphNode *nodes, size_t *numNodes)

Returns a graph's nodes.

Parameters

hGraph

- Graph to query

nodes

- Pointer to return the nodes

numNodes

- See description

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Returns a list of `hGraph`'s nodes. `nodes` may be NULL, in which case this function will return the number of nodes in `numNodes`. Otherwise, `numNodes` entries will be filled in. If `numNodes` is higher than the actual number of nodes, the remaining entries in `nodes` will be set to NULL, and the number of nodes actually obtained will be returned in `numNodes`.



Note:

- ▶ Graph objects are not threadsafe. [More here](#).
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphCreate](#), [cuGraphGetRootNodes](#), [cuGraphGetEdges](#), [cuGraphNodeGetType](#), [cuGraphNodeGetDependencies](#), [cuGraphNodeGetDependentNodes](#)

CUresult cuGraphGetRootNodes (CUgraph hGraph, CUgraphNode *rootNodes, size_t *numRootNodes)

Returns a graph's root nodes.

Parameters

hGraph

- Graph to query

rootNodes

- Pointer to return the root nodes

numRootNodes

- See description

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Returns a list of `hGraph`'s root nodes. `rootNodes` may be NULL, in which case this function will return the number of root nodes in `numRootNodes`. Otherwise, `numRootNodes` entries will be filled in. If `numRootNodes` is higher than the actual number of root nodes, the remaining entries in `rootNodes` will be set to NULL, and the number of nodes actually obtained will be returned in `numRootNodes`.

**Note:**

- ▶ Graph objects are not threadsafe. [More here](#).
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphCreate](#), [cuGraphGetNodes](#), [cuGraphGetEdges](#), [cuGraphNodeGetType](#), [cuGraphNodeGetDependencies](#), [cuGraphNodeGetDependentNodes](#)

CUresult cuGraphHostNodeGetParams (CUgraphNode hNode, CUDA_HOST_NODE_PARAMS *nodeParams)

Returns a host node's parameters.

Parameters**hNode**

- Node to get the parameters for

nodeParams

- Pointer to return the parameters

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Returns the parameters of host node `hNode` in `nodeParams`.



Note:

- ▶ Graph objects are not threadsafe. [More here](#).
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuLaunchHostFunc](#), [cuGraphAddHostNode](#), [cuGraphHostNodeSetParams](#)

CUresult cuGraphHostNodeSetParams (CUgraphNode hNode, const CUDA_HOST_NODE_PARAMS *nodeParams)

Sets a host node's parameters.

Parameters

hNode

- Node to set the parameters for

nodeParams

- Parameters to copy

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_VALUE](#)

Description

Sets the parameters of host node `hNode` to `nodeParams`.



Note:

- ▶ Graph objects are not threadsafe. [More here](#).
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuLaunchHostFunc](#), [cuGraphAddHostNode](#), [cuGraphHostNodeGetParams](#)

CUresult cuGraphInstantiate (CUgraphExec *phGraphExec, CUgraph hGraph, CUgraphNode *phErrorNode, char *logBuffer, size_t bufferSize)

Creates an executable graph from a graph.

Parameters

phGraphExec

- Returns instantiated graph

hGraph

- Graph to instantiate

phErrorNode

- In case of an instantiation error, this may be modified to indicate a node contributing to the error

logBuffer

- A character buffer to store diagnostic messages

bufferSize

- Size of the log buffer in bytes

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Instantiates `hGraph` as an executable graph. The graph is validated for any structural constraints or intra-node constraints which were not previously validated. If instantiation is successful, a handle to the instantiated graph is returned in `graphExec`.

If there are any errors, diagnostic information may be returned in `errorNode` and `logBuffer`. This is the primary way to inspect instantiation errors. The output will be null terminated unless the diagnostics overflow the buffer. In this case, they will be truncated, and the last byte can be inspected to determine if truncation occurred.



Note:

- ▶ Graph objects are not threadsafe. [More here](#).
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphCreate](#), [cuGraphUpload](#), [cuGraphLaunch](#), [cuGraphExecDestroy](#)

CUresult cuGraphKernelNodeCopyAttributes (CUgraphNode dst, CUgraphNode src)

Copies attributes from source node to destination node.

Parameters

dst

Destination node

src

Source node For list of attributes see [CUkernelNodeAttrID](#)

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Copies attributes from source node `src` to destination node `dst`. Both node must have the same context.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[CUaccessPolicyWindow](#)

CUresult cuGraphKernelNodeGetAttribute (CUgraphNode hNode, CUkernelNodeAttrID attr, CUkernelNodeAttrValue *value_out)

Queries node attribute.

Parameters

hNode

attr

value_out

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_HANDLE](#)

Description

Queries attribute `attr` from node `hNode` and stores it in corresponding member of `value_out`.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

`CUaccessPolicyWindow`

CUresult cuGraphKernelNodeGetParams (CUgraphNode hNode, CUDA_KERNEL_NODE_PARAMS *nodeParams)

Returns a kernel node's parameters.

Parameters

hNode

- Node to get the parameters for

nodeParams

- Pointer to return the parameters

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_VALUE](#)

Description

Returns the parameters of kernel node `hNode` in `nodeParams`. The `kernelParams` or `extra` array returned in `nodeParams`, as well as the argument values it points to, are owned by the node. This memory remains valid until the node is destroyed or its parameters are modified, and should not be modified directly. Use [cuGraphKernelNodeSetParams](#) to update the parameters of this node.

The params will contain either `kernelParams` or `extra`, according to which of these was most recently set on the node.



Note:

- ▶ Graph objects are not threadsafe. [More here.](#)
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuLaunchKernel](#), [cuGraphAddKernelNode](#), [cuGraphKernelNodeSetParams](#)

CUresult cuGraphKernelNodeSetAttribute (CUgraphNode hNode, CUkernelNodeAttrID attr, const CUkernelNodeAttrValue *value)

Sets node attribute.

Parameters

hNode**attr****value**

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_HANDLE](#)

Description

Sets attribute `attr` on node `hNode` from corresponding attribute of `value`.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[CUaccessPolicyWindow](#)

CUresult cuGraphKernelNodeSetParams (CUgraphNode hNode, const CUDA_KERNEL_NODE_PARAMS *nodeParams)

Sets a kernel node's parameters.

Parameters

hNode

- Node to set the parameters for

nodeParams

- Parameters to copy

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_HANDLE](#),
[CUDA_ERROR_OUT_OF_MEMORY](#)

Description

Sets the parameters of kernel node `hNode` to `nodeParams`.

**Note:**

- ▶ Graph objects are not threadsafe. [More here](#).
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuLaunchKernel](#), [cuGraphAddKernelNode](#), [cuGraphKernelNodeGetParams](#)

CUresult cuGraphLaunch (CUgraphExec hGraphExec, CUstream hStream)

Launches an executable graph in a stream.

Parameters**hGraphExec**

- Executable graph to launch

hStream

- Stream in which to launch the graph

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_VALUE](#)

Description

Executes `hGraphExec` in `hStream`. Only one instance of `hGraphExec` may be executing at a time. Each launch is ordered behind both any previous work in `hStream` and any previous launches of `hGraphExec`. To execute a graph concurrently, it must be instantiated multiple times into multiple executable graphs.

**Note:**

- ▶ Graph objects are not threadsafe. [More here.](#)
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphInstantiate](#), [cuGraphUpload](#), [cuGraphExecDestroy](#)

CUresult cuGraphMemcpyNodeGetParams (CUgraphNode hNode, CUDA_MEMCPY3D *nodeParams)

Returns a memcpy node's parameters.

Parameters

hNode

- Node to get the parameters for

nodeParams

- Pointer to return the parameters

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_VALUE](#)

Description

Returns the parameters of memcpy node hNode in nodeParams.

**Note:**

- ▶ Graph objects are not threadsafe. [More here.](#)
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuMemcpy3D](#), [cuGraphAddMemcpyNode](#), [cuGraphMemcpyNodeSetParams](#)

CUresult cuGraphMemcpyNodeSetParams (CUgraphNode hNode, const CUDA_MEMCPY3D *nodeParams)

Sets a memcpy node's parameters.

Parameters

hNode

- Node to set the parameters for

nodeParams

- Parameters to copy

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_VALUE](#),

Description

Sets the parameters of memcpy node hNode to nodeParams.



Note:

- ▶ Graph objects are not threadsafe. [More here](#).
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuMemcpy3D](#), [cuGraphAddMemcpyNode](#), [cuGraphMemcpyNodeGetParams](#)

CUresult cuGraphMemsetNodeGetParams (CUgraphNode hNode, CUDA_MEMSET_NODE_PARAMS *nodeParams)

Returns a memset node's parameters.

Parameters

hNode

- Node to get the parameters for

nodeParams

- Pointer to return the parameters

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Returns the parameters of memset node `hNode` in `nodeParams`.



Note:

- ▶ Graph objects are not threadsafe. [More here.](#)
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuMemsetD2D32](#), [cuGraphAddMemsetNode](#), [cuGraphMemsetNodeSetParams](#)

CUresult cuGraphMemsetNodeSetParams (CUgraphNode hNode, const CUDA_MEMSET_NODE_PARAMS *nodeParams)

Sets a memset node's parameters.

Parameters

hNode

- Node to set the parameters for

nodeParams

- Parameters to copy

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Sets the parameters of memset node `hNode` to `nodeParams`.



Note:

- ▶ Graph objects are not threadsafe. [More here.](#)
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuMemsetD2D32](#), [cuGraphAddMemsetNode](#), [cuGraphMemsetNodeGetParams](#)

CUresult cuGraphNodeFindInClone (CUgraphNode *phNode, CUgraphNode hOriginalNode, CUgraph hClonedGraph)

Finds a cloned version of a node.

Parameters

phNode

- Returns handle to the cloned node

hOriginalNode

- Handle to the original node

hClonedGraph

- Cloned graph to query

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#),

Description

This function returns the node in `hClonedGraph` corresponding to `hOriginalNode` in the original graph.

`hClonedGraph` must have been cloned from `hOriginalGraph` via [cuGraphClone](#). `hOriginalNode` must have been in `hOriginalGraph` at the time of the call to [cuGraphClone](#), and the corresponding cloned node in `hClonedGraph` must not have been removed. The cloned node is then returned via `phClonedNode`.

**Note:**

- ▶ Graph objects are not threadsafe. [More here](#).
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphClone](#)

CUresult cuGraphNodeGetDependencies (CUgraphNode hNode, CUgraphNode *dependencies, size_t *numDependencies)

Returns a node's dependencies.

Parameters

hNode

- Node to query

dependencies

- Pointer to return the dependencies

numDependencies

- See description

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_VALUE](#)

Description

Returns a list of node 's dependencies. `dependencies` may be NULL, in which case this function will return the number of dependencies in `numDependencies`. Otherwise, `numDependencies` entries will be filled in. If `numDependencies` is higher than the actual number of dependencies, the remaining entries in `dependencies` will be set to NULL, and the number of nodes actually obtained will be returned in `numDependencies`.



Note:

- ▶ Graph objects are not threadsafe. [More here](#).
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphNodeGetDependentNodes](#), [cuGraphGetNodes](#), [cuGraphGetRootNodes](#),
[cuGraphGetEdges](#), [cuGraphAddDependencies](#), [cuGraphRemoveDependencies](#)

CUresult cuGraphNodeGetDependentNodes (CUgraphNode hNode, CUgraphNode *dependentNodes, size_t *numDependentNodes)

Returns a node's dependent nodes.

Parameters

hNode

- Node to query

dependentNodes

- Pointer to return the dependent nodes

numDependentNodes

- See description

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_VALUE](#)

Description

Returns a list of node 's dependent nodes. `dependentNodes` may be NULL, in which case this function will return the number of dependent nodes in `numDependentNodes`. Otherwise, `numDependentNodes` entries will be filled in. If `numDependentNodes` is higher than the actual number of dependent nodes, the remaining entries in `dependentNodes` will be set to NULL, and the number of nodes actually obtained will be returned in `numDependentNodes`.



Note:

- ▶ Graph objects are not threadsafe. [More here.](#)
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphNodeGetDependencies](#), [cuGraphGetNodes](#), [cuGraphGetRootNodes](#),
[cuGraphGetEdges](#), [cuGraphAddDependencies](#), [cuGraphRemoveDependencies](#)

CUresult cuGraphNodeGetType (CUgraphNode hNode, CUgraphNodeType *type)

Returns a node's type.

Parameters

hNode

- Node to query

type

- Pointer to return the node type

Returns

CUDA_SUCCESS, CUDA_ERROR_DEINITIALIZED, CUDA_ERROR_NOT_INITIALIZED, CUDA_ERROR_INVALID_VALUE

Description

Returns the node type of hNode in type.



Note:

- ▶ Graph objects are not threadsafe. [More here](#).
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphGetNodes](#), [cuGraphGetRootNodes](#), [cuGraphChildGraphNodeGetGraph](#), [cuGraphKernelNodeGetParams](#), [cuGraphKernelNodeSetParams](#), [cuGraphHostNodeGetParams](#), [cuGraphHostNodeSetParams](#), [cuGraphMemcpyNodeGetParams](#), [cuGraphMemcpyNodeSetParams](#), [cuGraphMemsetNodeGetParams](#), [cuGraphMemsetNodeSetParams](#)

CUresult cuGraphReleaseUserObject (CUgraph graph, CUUserObject object, unsigned int count)

Release a user object reference from a graph.

Parameters

graph

- The graph that will release the reference

object

- The user object to release a reference for

count

- The number of references to release, typically 1. Must be nonzero and not larger than INT_MAX.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Releases user object references owned by a graph.

See CUDA User Objects in the CUDA C++ Programming Guide for more information on user objects.

See also:

[cuUserObjectCreate](#), [cuUserObjectRetain](#), [cuUserObjectRelease](#), [cuGraphRetainUserObject](#), [cuGraphCreate](#)

CUresult cuGraphRemoveDependencies (CUgraph hGraph, const CUgraphNode *from, const CUgraphNode *to, size_t numDependencies)

Removes dependency edges from a graph.

Parameters**hGraph**

- Graph from which to remove dependencies

from

- Array of nodes that provide the dependencies

to

- Array of dependent nodes

numDependencies

- Number of dependencies to be removed

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

The number of dependencies to be removed is defined by `numDependencies`. Elements in `from` and `to` at corresponding indices define a dependency. Each node in `from` and `to` must belong to `hGraph`.

If `numDependencies` is 0, elements in `from` and `to` will be ignored. Specifying a non-existing dependency will return an error.



Note:

- ▶ Graph objects are not threadsafe. [More here.](#)
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphAddDependencies](#), [cuGraphGetEdges](#), [cuGraphNodeGetDependencies](#),
[cuGraphNodeGetDependentNodes](#)

CUresult cuGraphRetainUserObject (CUgraph graph, CUUserObject object, unsigned int count, unsigned int flags)

Retain a reference to a user object from a graph.

Parameters

graph

- The graph to associate the reference with

object

- The user object to retain a reference for

count

- The number of references to add to the graph, typically 1. Must be nonzero and not larger than INT_MAX.

flags

- The optional flag [CU_GRAPH_USER_OBJECT_MOVE](#) transfers references from the calling thread, rather than create new references. Pass 0 to create new references.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Creates or moves user object references that will be owned by a CUDA graph.

See CUDA User Objects in the CUDA C++ Programming Guide for more information on user objects.

See also:

[cuUserObjectCreate](#), [cuUserObjectRetain](#), [cuUserObjectRelease](#), [cuGraphReleaseUserObject](#), [cuGraphCreate](#)

CUresult cuGraphUpload (CUgraphExec hGraphExec, CUstream hStream)

Uploads an executable graph in a stream.

Parameters

hGraphExec

- Executable graph to upload

hStream

- Stream in which to upload the graph

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Uploads `hGraphExec` to the device in `hStream` without executing it. Uploads of the same `hGraphExec` will be serialized. Each upload is ordered behind both any previous work in `hStream` and any previous launches of `hGraphExec`.



Note:

- ▶ Graph objects are not threadsafe. [More here](#).
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphInstantiate](#), [cuGraphLaunch](#), [cuGraphExecDestroy](#)

CUresult cuUserObjectCreate (CUUserObject *object_out, void *ptr, CUhostFn destroy, unsigned int initialRefCount, unsigned int flags)

Create a user object.

Parameters

object_out

- Location to return the user object handle

ptr

- The pointer to pass to the destroy function

destroy

- Callback to free the user object when it is no longer in use

initialRefCount

- The initial refcount to create the object with, typically 1. The initial references are owned by the calling thread.

flags

- Currently it is required to pass [CU_USER_OBJECT_NO_DESTRUCTOR_SYNC](#), which is the only defined flag. This indicates that the destroy callback cannot be waited on by any CUDA API. Users requiring synchronization of the callback should signal its completion manually.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Create a user object with the specified destructor callback and initial reference count. The initial references are owned by the caller.

Destructor callbacks cannot make CUDA API calls and should avoid blocking behavior, as they are executed by a shared internal thread. Another thread may be signaled to perform such actions, if it does not block forward progress of tasks scheduled through CUDA.

See CUDA User Objects in the CUDA C++ Programming Guide for more information on user objects.

See also:

[cuUserObjectRetain](#), [cuUserObjectRelease](#), [cuGraphRetainUserObject](#), [cuGraphReleaseUserObject](#), [cuGraphCreate](#)

CUresult cuUserObjectRelease (CUUserObject object, unsigned int count)

Release a reference to a user object.

Parameters**object**

- The object to release

count

- The number of references to release, typically 1. Must be nonzero and not larger than INT_MAX.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Releases user object references owned by the caller. The object's destructor is invoked if the reference count reaches zero.

It is undefined behavior to release references not owned by the caller, or to use a user object handle after all references are released.

See CUDA User Objects in the CUDA C++ Programming Guide for more information on user objects.

See also:

[cuUserObjectCreate](#), [cuUserObjectRetain](#), [cuGraphRetainUserObject](#), [cuGraphReleaseUserObject](#), [cuGraphCreate](#)

CUresult cuUserObjectRetain (CUUserObject object, unsigned int count)

Retain a reference to a user object.

Parameters

object

- The object to retain

count

- The number of references to retain, typically 1. Must be nonzero and not larger than INT_MAX.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Retains new references to a user object. The new references are owned by the caller.

See CUDA User Objects in the CUDA C++ Programming Guide for more information on user objects.

See also:

[cuUserObjectCreate](#), [cuUserObjectRelease](#), [cuGraphRetainUserObject](#), [cuGraphReleaseUserObject](#), [cuGraphCreate](#)

6.22. Occupancy

This section describes the occupancy calculation functions of the low-level CUDA driver application programming interface.

CUresult

`cuOccupancyAvailableDynamicSMemPerBlock (size_t *dynamicSmemSize, CUfunction func, int numBlocks, int blockSize)`

Returns dynamic shared memory available per block when launching `numBlocks` blocks on SM.

Parameters

dynamicSmemSize

- Returned maximum dynamic shared memory

func

- Kernel function for which occupancy is calculated

numBlocks

- Number of blocks to fit on SM

blockSize

- Size of the blocks

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_UNKNOWN](#)

Description

Returns in `*dynamicSmemSize` the maximum size of dynamic shared memory to allow `numBlocks` blocks per SM.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

CUresult

`cuOccupancyMaxActiveBlocksPerMultiprocessor (int *numBlocks, CUfunction func, int blockSize, size_t dynamicSMemSize)`

Returns occupancy of a function.

Parameters

numBlocks

- Returned occupancy

func

- Kernel for which occupancy is calculated

blockSize

- Block size the kernel is intended to be launched with

dynamicSMemSize

- Per-block dynamic shared memory usage intended, in bytes

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_UNKNOWN](#)

Description

Returns in `*numBlocks` the number of the maximum active blocks per streaming multiprocessor.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cudaOccupancyMaxActiveBlocksPerMultiprocessor](#)

CUresult

`cuOccupancyMaxActiveBlocksPerMultiprocessorWithFlags`
 (int *numBlocks, CUfunction func, int blockSize, size_t
 dynamicSMemSize, unsigned int flags)

Returns occupancy of a function.

Parameters

numBlocks

- Returned occupancy

func

- Kernel for which occupancy is calculated

blockSize

- Block size the kernel is intended to be launched with

dynamicSMemSize

- Per-block dynamic shared memory usage intended, in bytes

flags

- Requested behavior for the occupancy calculator

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_UNKNOWN](#)

Description

Returns in *numBlocks the number of the maximum active blocks per streaming multiprocessor.

The Flags parameter controls how special cases are handled. The valid flags are:

- ▶ [CU_OCCUPANCY_DEFAULT](#), which maintains the default behavior as `cuOccupancyMaxActiveBlocksPerMultiprocessor`;
- ▶ [CU_OCCUPANCY_DISABLE_CACHING_OVERRIDE](#), which suppresses the default behavior on platform where global caching affects occupancy. On such platforms, if caching is enabled, but per-block SM resource usage would result in zero occupancy, the occupancy calculator will calculate the occupancy as if caching is disabled. Setting [CU_OCCUPANCY_DISABLE_CACHING_OVERRIDE](#) makes the occupancy calculator to return 0 in such cases. More information can be found about this feature in the "Unified L1/Texture Cache" section of the Maxwell tuning guide.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cudaOccupancyMaxActiveBlocksPerMultiprocessorWithFlags](#)

CUresult cuOccupancyMaxPotentialBlockSize (int *minGridSize, int *blockSize, CUfunction func, CUoccupancyB2DSize blockSizeToDynamicSMemSize, size_t dynamicSMemSize, int blockSizeLimit)

Suggest a launch configuration with reasonable occupancy.

Parameters**minGridSize**

- Returned minimum grid size needed to achieve the maximum occupancy

blockSize

- Returned maximum block size that can achieve the maximum occupancy

func

- Kernel for which launch configuration is calculated

blockSizeToDynamicSMemSize

- A function that calculates how much per-block dynamic shared memory `func` uses based on the block size

dynamicSMemSize

- Dynamic shared memory usage intended, in bytes

blockSizeLimit

- The maximum block size `func` is designed to handle

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_UNKNOWN](#)

Description

Returns in `*blockSize` a reasonable block size that can achieve the maximum occupancy (or, the maximum number of active warps with the fewest blocks per multiprocessor), and in `*minGridSize` the minimum grid size to achieve the maximum occupancy.

If `blockSizeLimit` is 0, the configurator will use the maximum block size permitted by the device / function instead.

If per-block dynamic shared memory allocation is not needed, the user should leave both `blockSizeToDynamicSMemSize` and `dynamicSMemSize` as 0.

If per-block dynamic shared memory allocation is needed, then if the dynamic shared memory size is constant regardless of block size, the size should be passed through `dynamicSMemSize`, and `blockSizeToDynamicSMemSize` should be NULL.

Otherwise, if the per-block dynamic shared memory size varies with different block sizes, the user needs to provide a unary function through `blockSizeToDynamicSMemSize` that computes the dynamic shared memory needed by `func` for any given block size. `dynamicSMemSize` is ignored. An example signature is:

```
↑ // Take block size, returns dynamic shared memory needed
   size_t blockSizeToSmem(int blockSize);
```



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cudaOccupancyMaxPotentialBlockSize](#)

CUresult

```
cuOccupancyMaxPotentialBlockSizeWithFlags
(int *minGridSize, int *blockSize, CUfunction func,
CUoccupancyB2DSize blockSizeToDynamicSMemSize,
size_t dynamicSMemSize, int blockSizeLimit,
unsigned int flags)
```

Suggest a launch configuration with reasonable occupancy.

Parameters

minGridSize

- Returned minimum grid size needed to achieve the maximum occupancy

blockSize

- Returned maximum block size that can achieve the maximum occupancy

func

- Kernel for which launch configuration is calculated

blockSizeToDynamicSMemSize

- A function that calculates how much per-block dynamic shared memory `func` uses based on the block size

dynamicSMemSize

- Dynamic shared memory usage intended, in bytes

blockSizeLimit

- The maximum block size `func` is designed to handle

flags

- Options

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_UNKNOWN](#)

Description

An extended version of [cuOccupancyMaxPotentialBlockSize](#). In addition to arguments passed to [cuOccupancyMaxPotentialBlockSize](#), [cuOccupancyMaxPotentialBlockSizeWithFlags](#) also takes a `Flags` parameter.

The `Flags` parameter controls how special cases are handled. The valid flags are:

- ▶ [CU_OCCUPANCY_DEFAULT](#), which maintains the default behavior as [cuOccupancyMaxPotentialBlockSize](#);
- ▶ [CU_OCCUPANCY_DISABLE_CACHING_OVERRIDE](#), which suppresses the default behavior on platform where global caching affects occupancy. On such platforms, the launch configurations that produces maximal occupancy might not support global caching. Setting [CU_OCCUPANCY_DISABLE_CACHING_OVERRIDE](#) guarantees that the the produced launch configuration is global caching compatible at a potential cost of occupancy. More information can be found about this feature in the "Unified L1/Texture Cache" section of the Maxwell tuning guide.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cudaOccupancyMaxPotentialBlockSizeWithFlags](#)

6.23. Texture Reference Management [DEPRECATED]

This section describes the deprecated texture reference management functions of the low-level CUDA driver application programming interface.

CUresult cuTexRefCreate (CUtexref *pTexRef)

Creates a texture reference.

Parameters

pTexRef

- Returned texture reference

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

[Deprecated](#)

Creates a texture reference and returns its handle in *pTexRef. Once created, the application must call [cuTexRefSetArray\(\)](#) or [cuTexRefSetAddress\(\)](#) to associate the reference with allocated memory. Other texture reference functions are used to specify the format and interpretation (addressing, filtering, etc.) to be used when the memory is read through this texture reference.

See also:

[cuTexRefDestroy](#)

CUresult cuTexRefDestroy (CUtexref hTexRef)

Destroys a texture reference.

Parameters

hTexRef

- Texture reference to destroy

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

[Deprecated](#)

Destroys the texture reference specified by `hTexRef`.

See also:

[cuTexRefCreate](#)

CUresult cuTexRefGetAddress (CUdeviceptr *pdptr, CUtexref hTexRef)

Gets the address associated with a texture reference.

Parameters

pdptr

- Returned device address

hTexRef

- Texture reference

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

[Deprecated](#)

Returns in `*pdptr` the base address bound to the texture reference `hTexRef`, or returns [CUDA_ERROR_INVALID_VALUE](#) if the texture reference is not bound to any device memory range.

See also:

[cuTexRefSetAddress](#), [cuTexRefSetAddress2D](#), [cuTexRefSetAddressMode](#), [cuTexRefSetArray](#), [cuTexRefSetFilterMode](#), [cuTexRefSetFlags](#), [cuTexRefSetFormat](#), [cuTexRefGetAddressMode](#), [cuTexRefGetArray](#), [cuTexRefGetFilterMode](#), [cuTexRefGetFlags](#), [cuTexRefGetFormat](#)

CUresult cuTexRefGetAddressMode (CUaddress_mode *pam, CUtexref hTexRef, int dim)

Gets the addressing mode used by a texture reference.

Parameters

pam

- Returned addressing mode

hTexRef

- Texture reference

dim

- Dimension

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Deprecated

Returns in *pam the addressing mode corresponding to the dimension dim of the texture reference hTexRef. Currently, the only valid value for dim are 0 and 1.

See also:

[cuTexRefSetAddress](#), [cuTexRefSetAddress2D](#), [cuTexRefSetAddressMode](#), [cuTexRefSetArray](#),
[cuTexRefSetFilterMode](#), [cuTexRefSetFlags](#), [cuTexRefSetFormat](#), [cuTexRefGetAddress](#),
[cuTexRefGetArray](#), [cuTexRefGetFilterMode](#), [cuTexRefGetFlags](#), [cuTexRefGetFormat](#)

CUresult cuTexRefGetArray (CUarray *phArray, CUtexref hTexRef)

Gets the array bound to a texture reference.

Parameters

phArray

- Returned array

hTexRef

- Texture reference

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

[Deprecated](#)

Returns in `*pArray` the CUDA array bound to the texture reference `hTexRef`, or returns [CUDA_ERROR_INVALID_VALUE](#) if the texture reference is not bound to any CUDA array.

See also:

[cuTexRefSetAddress](#), [cuTexRefSetAddress2D](#), [cuTexRefSetAddressMode](#), [cuTexRefSetArray](#), [cuTexRefSetFilterMode](#), [cuTexRefSetFlags](#), [cuTexRefSetFormat](#), [cuTexRefGetAddress](#), [cuTexRefGetAddressMode](#), [cuTexRefGetFilterMode](#), [cuTexRefGetFlags](#), [cuTexRefGetFormat](#)

CUresult cuTexRefGetBorderColor (float *pBorderColor, CUtexref hTexRef)

Gets the border color used by a texture reference.

Parameters

pBorderColor

- Returned Type and Value of RGBA color

hTexRef

- Texture reference

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

[Deprecated](#)

Returns in `pBorderColor`, values of the RGBA color used by the texture reference `hTexRef`. The color value is of type float and holds color components in the following sequence: `pBorderColor[0]` holds 'R' component `pBorderColor[1]` holds 'G' component `pBorderColor[2]` holds 'B' component `pBorderColor[3]` holds 'A' component

See also:

[cuTexRefSetAddressMode](#), [cuTexRefSetAddressMode](#), [cuTexRefSetBorderColor](#)

CUresult cuTexRefGetFilterMode (CUfilter_mode *pfm, CUtexref hTexRef)

Gets the filter-mode used by a texture reference.

Parameters

pfm

- Returned filtering mode

hTexRef

- Texture reference

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

[Deprecated](#)

Returns in *pfm the filtering mode of the texture reference hTexRef.

See also:

[cuTexRefSetAddress](#), [cuTexRefSetAddress2D](#), [cuTexRefSetAddressMode](#), [cuTexRefSetArray](#), [cuTexRefSetFilterMode](#), [cuTexRefSetFlags](#), [cuTexRefSetFormat](#), [cuTexRefGetAddress](#), [cuTexRefGetAddressMode](#), [cuTexRefGetArray](#), [cuTexRefGetFlags](#), [cuTexRefGetFormat](#)

CUresult cuTexRefGetFlags (unsigned int *pFlags, CUtexref hTexRef)

Gets the flags used by a texture reference.

Parameters

pFlags

- Returned flags

hTexRef

- Texture reference

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Deprecated

Returns in `*pFlags` the flags of the texture reference `hTexRef`.

See also:

[cuTexRefSetAddress](#), [cuTexRefSetAddress2D](#), [cuTexRefSetAddressMode](#), [cuTexRefSetArray](#), [cuTexRefSetFilterMode](#), [cuTexRefSetFlags](#), [cuTexRefSetFormat](#), [cuTexRefGetAddress](#), [cuTexRefGetAddressMode](#), [cuTexRefGetArray](#), [cuTexRefGetFilterMode](#), [cuTexRefGetFormat](#)

CUresult cuTexRefGetFormat (CUarray_format *pFormat, int *pNumChannels, CUtexref hTexRef)

Gets the format used by a texture reference.

Parameters

pFormat

- Returned format

pNumChannels

- Returned number of components

hTexRef

- Texture reference

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Deprecated

Returns in `*pFormat` and `*pNumChannels` the format and number of components of the CUDA array bound to the texture reference `hTexRef`. If `pFormat` or `pNumChannels` is NULL, it will be ignored.

See also:

[cuTexRefSetAddress](#), [cuTexRefSetAddress2D](#), [cuTexRefSetAddressMode](#), [cuTexRefSetArray](#), [cuTexRefSetFilterMode](#), [cuTexRefSetFlags](#), [cuTexRefSetFormat](#), [cuTexRefGetAddress](#), [cuTexRefGetAddressMode](#), [cuTexRefGetArray](#), [cuTexRefGetFilterMode](#), [cuTexRefGetFlags](#)

CUresult cuTexRefGetMaxAnisotropy (int *pmaxAniso, CUtexref hTexRef)

Gets the maximum anisotropy for a texture reference.

Parameters

pmaxAniso

- Returned maximum anisotropy

hTexRef

- Texture reference

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

[Deprecated](#)

Returns the maximum anisotropy in `pmaxAniso` that's used when reading memory through the texture reference `hTexRef`.

See also:

[cuTexRefSetAddress](#), [cuTexRefSetAddress2D](#), [cuTexRefSetAddressMode](#), [cuTexRefSetArray](#), [cuTexRefSetFlags](#), [cuTexRefSetFormat](#), [cuTexRefGetAddress](#), [cuTexRefGetAddressMode](#), [cuTexRefGetArray](#), [cuTexRefGetFilterMode](#), [cuTexRefGetFlags](#), [cuTexRefGetFormat](#)

CUresult cuTexRefGetMipmapFilterMode (CUfilter_mode *pfm, CUtexref hTexRef)

Gets the mipmap filtering mode for a texture reference.

Parameters

pfm

- Returned mipmap filtering mode

hTexRef

- Texture reference

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Deprecated

Returns the mipmap filtering mode in `pfm` that's used when reading memory through the texture reference `hTexRef`.

See also:

[cuTexRefSetAddress](#), [cuTexRefSetAddress2D](#), [cuTexRefSetAddressMode](#), [cuTexRefSetArray](#), [cuTexRefSetFlags](#), [cuTexRefSetFormat](#), [cuTexRefGetAddress](#), [cuTexRefGetAddressMode](#), [cuTexRefGetArray](#), [cuTexRefGetFilterMode](#), [cuTexRefGetFlags](#), [cuTexRefGetFormat](#)

CUresult cuTexRefGetMipmapLevelBias (float *pbias, CUtexref hTexRef)

Gets the mipmap level bias for a texture reference.

Parameters

pbias

- Returned mipmap level bias

hTexRef

- Texture reference

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Deprecated

Returns the mipmap level bias in `pBias` that's added to the specified mipmap level when reading memory through the texture reference `hTexRef`.

See also:

[cuTexRefSetAddress](#), [cuTexRefSetAddress2D](#), [cuTexRefSetAddressMode](#), [cuTexRefSetArray](#), [cuTexRefSetFlags](#), [cuTexRefSetFormat](#), [cuTexRefGetAddress](#), [cuTexRefGetAddressMode](#), [cuTexRefGetArray](#), [cuTexRefGetFilterMode](#), [cuTexRefGetFlags](#), [cuTexRefGetFormat](#)

CUresult cuTexRefGetMipmapLevelClamp (float *pminMipmapLevelClamp, float *pmaxMipmapLevelClamp, CUtexref hTexRef)

Gets the min/max mipmap level clamps for a texture reference.

Parameters

pminMipmapLevelClamp

- Returned mipmap min level clamp

pmaxMipmapLevelClamp

- Returned mipmap max level clamp

hTexRef

- Texture reference

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Deprecated

Returns the min/max mipmap level clamps in `pminMipmapLevelClamp` and `pmaxMipmapLevelClamp` that's used when reading memory through the texture reference `hTexRef`.

See also:

[cuTexRefSetAddress](#), [cuTexRefSetAddress2D](#), [cuTexRefSetAddressMode](#), [cuTexRefSetArray](#),
[cuTexRefSetFlags](#), [cuTexRefSetFormat](#), [cuTexRefGetAddress](#), [cuTexRefGetAddressMode](#),
[cuTexRefGetArray](#), [cuTexRefGetFilterMode](#), [cuTexRefGetFlags](#), [cuTexRefGetFormat](#)

CUresult cuTexRefGetMipmappedArray (CUmipmappedArray *phMipmappedArray, CUtexref hTexRef)

Gets the mipmapped array bound to a texture reference.

Parameters

phMipmappedArray

- Returned mipmapped array

hTexRef

- Texture reference

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

[Deprecated](#)

Returns in `*pMipmappedArray` the CUDA mipmapped array bound to the texture reference `hTexRef`, or returns [CUDA_ERROR_INVALID_VALUE](#) if the texture reference is not bound to any CUDA mipmapped array.

See also:

[cuTexRefSetAddress](#), [cuTexRefSetAddress2D](#), [cuTexRefSetAddressMode](#), [cuTexRefSetArray](#),
[cuTexRefSetFilterMode](#), [cuTexRefSetFlags](#), [cuTexRefSetFormat](#), [cuTexRefGetAddress](#),
[cuTexRefGetAddressMode](#), [cuTexRefGetFilterMode](#), [cuTexRefGetFlags](#), [cuTexRefGetFormat](#)

CUresult cuTexRefSetAddress (size_t *ByteOffset, CUtexref hTexRef, CUdeviceptr dptr, size_t bytes)

Binds an address as a texture reference.

Parameters**ByteOffset**

- Returned byte offset

hTexRef

- Texture reference to bind

dptr

- Device pointer to bind

bytes

- Size of memory to bind in bytes

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

[Deprecated](#)

Binds a linear address range to the texture reference `hTexRef`. Any previous address or CUDA array state associated with the texture reference is superseded by this function. Any memory previously bound to `hTexRef` is unbound.

Since the hardware enforces an alignment requirement on texture base addresses, [cuTexRefSetAddress\(\)](#) passes back a byte offset in `*ByteOffset` that must be applied to texture fetches in order to read from the desired memory. This offset must be divided by the texel size and passed to kernels that read from the texture so they can be applied to the `tex1Dfetch()` function.

If the device memory pointer was returned from [cuMemAlloc\(\)](#), the offset is guaranteed to be 0 and NULL may be passed as the `ByteOffset` parameter.

The total number of elements (or texels) in the linear address range cannot exceed [CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE1D_LINEAR_WIDTH](#). The number of elements is computed as $(\text{bytes} / \text{bytesPerElement})$, where `bytesPerElement` is determined from the data format and number of components set using [cuTexRefSetFormat\(\)](#).

See also:

[cuTexRefSetAddress2D](#), [cuTexRefSetAddressMode](#), [cuTexRefSetArray](#), [cuTexRefSetFilterMode](#), [cuTexRefSetFlags](#), [cuTexRefSetFormat](#), [cuTexRefGetAddress](#), [cuTexRefGetAddressMode](#), [cuTexRefGetArray](#), [cuTexRefGetFilterMode](#), [cuTexRefGetFlags](#), [cuTexRefGetFormat](#), [cudaBindTexture](#)

CUresult cuTexRefSetAddress2D (CUtexref hTexRef, const CUDA_ARRAY_DESCRIPTOR *desc, CUdeviceptr dptr, size_t Pitch)

Binds an address as a 2D texture reference.

Parameters

hTexRef

- Texture reference to bind

desc

- Descriptor of CUDA array

dptr

- Device pointer to bind

Pitch

- Line pitch in bytes

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Deprecated

Binds a linear address range to the texture reference `hTexRef`. Any previous address or CUDA array state associated with the texture reference is superseded by this function. Any memory previously bound to `hTexRef` is unbound.

Using a `tex2D()` function inside a kernel requires a call to either [cuTexRefSetArray\(\)](#) to bind the corresponding texture reference to an array, or [cuTexRefSetAddress2D\(\)](#) to bind the texture reference to linear memory.

Function calls to [cuTexRefSetFormat\(\)](#) cannot follow calls to [cuTexRefSetAddress2D\(\)](#) for the same texture reference.

It is required that `dptr` be aligned to the appropriate hardware-specific texture alignment. You can query this value using the device attribute [CU_DEVICE_ATTRIBUTE_TEXTURE_ALIGNMENT](#). If an unaligned `dptr` is supplied, [CUDA_ERROR_INVALID_VALUE](#) is returned.

`Pitch` has to be aligned to the hardware-specific texture pitch alignment. This value can be queried using the device attribute [CU_DEVICE_ATTRIBUTE_TEXTURE_PITCH_ALIGNMENT](#). If an unaligned `Pitch` is supplied, [CUDA_ERROR_INVALID_VALUE](#) is returned.

Width and Height, which are specified in elements (or texels), cannot exceed [CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_LINEAR_WIDTH](#) and [CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_LINEAR_HEIGHT](#) respectively. `Pitch`, which is specified in bytes, cannot exceed [CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_LINEAR_PITCH](#).

See also:

[cuTexRefSetAddress](#), [cuTexRefSetAddressMode](#), [cuTexRefSetArray](#), [cuTexRefSetFilterMode](#), [cuTexRefSetFlags](#), [cuTexRefSetFormat](#), [cuTexRefGetAddress](#), [cuTexRefGetAddressMode](#), [cuTexRefGetArray](#), [cuTexRefGetFilterMode](#), [cuTexRefGetFlags](#), [cuTexRefGetFormat](#), [cudaBindTexture2D](#)

CUresult cuTexRefSetAddressMode (CUtexref hTexRef, int dim, CUaddress_mode am)

Sets the addressing mode for a texture reference.

Parameters

hTexRef

- Texture reference

dim

- Dimension

am

- Addressing mode to set

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

[Deprecated](#)

Specifies the addressing mode `am` for the given dimension `dim` of the texture reference `hTexRef`. If `dim` is zero, the addressing mode is applied to the first parameter of the functions used to fetch from the texture; if `dim` is 1, the second, and so on. [CUaddress_mode](#) is defined as:

```
↑ typedef enum CUaddress_mode_enum {
    CU_TR_ADDRESS_MODE_WRAP = 0,
    CU_TR_ADDRESS_MODE_CLAMP = 1,
    CU_TR_ADDRESS_MODE_MIRROR = 2,
    CU_TR_ADDRESS_MODE_BORDER = 3
} CUaddress_mode;
```

Note that this call has no effect if `hTexRef` is bound to linear memory. Also, if the flag, [CU_TRSF_NORMALIZED_COORDINATES](#), is not set, the only supported address mode is [CU_TR_ADDRESS_MODE_CLAMP](#).

See also:

[cuTexRefSetAddress](#), [cuTexRefSetAddress2D](#), [cuTexRefSetArray](#),
[cuTexRefSetFilterMode](#), [cuTexRefSetFlags](#), [cuTexRefSetFormat](#), [cuTexRefGetAddress](#),
[cuTexRefGetAddressMode](#), [cuTexRefGetArray](#), [cuTexRefGetFilterMode](#), [cuTexRefGetFlags](#),
[cuTexRefGetFormat](#), [cudaBindTexture](#), [cudaBindTexture2D](#), [cudaBindTextureToArray](#),
[cudaBindTextureToMipmappedArray](#)

CUresult cuTexRefSetArray (CUtexref hTexRef, CUarray hArray, unsigned int Flags)

Binds an array as a texture reference.

Parameters**hTexRef**

- Texture reference to bind

hArray

- Array to bind

Flags

- Options (must be [CU_TRSA_OVERRIDE_FORMAT](#))

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

[Deprecated](#)

Binds the CUDA array `hArray` to the texture reference `hTexRef`. Any previous address or CUDA array state associated with the texture reference is superseded by this function. `Flags` must be set to [CU_TRSA_OVERRIDE_FORMAT](#). Any CUDA array previously bound to `hTexRef` is unbound.

See also:

[cuTexRefSetAddress](#), [cuTexRefSetAddress2D](#), [cuTexRefSetAddressMode](#), [cuTexRefSetFilterMode](#), [cuTexRefSetFlags](#), [cuTexRefSetFormat](#), [cuTexRefGetAddress](#), [cuTexRefGetAddressMode](#), [cuTexRefGetArray](#), [cuTexRefGetFilterMode](#), [cuTexRefGetFlags](#), [cuTexRefGetFormat](#), [cudaBindTextureToArray](#)

CUresult cuTexRefSetBorderColor (CUtexref hTexRef, float *pBorderColor)

Sets the border color for a texture reference.

Parameters

hTexRef

- Texture reference

pBorderColor

- RGBA color

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

[Deprecated](#)

Specifies the value of the RGBA color via the `pBorderColor` to the texture reference `hTexRef`. The color value supports only float type and holds color components in the following sequence: `pBorderColor[0]` holds 'R' component `pBorderColor[1]` holds 'G' component `pBorderColor[2]` holds 'B' component `pBorderColor[3]` holds 'A' component

Note that the color values can be set only when the Address mode is set to `CU_TR_ADDRESS_MODE_BORDER` using `cuTexRefSetAddressMode`. Applications using integer border color values have to "reinterpret_cast" their values to float.

See also:

[cuTexRefSetAddressMode](#), [cuTexRefGetAddressMode](#), [cuTexRefGetBorderColor](#), [cudaBindTexture](#), [cudaBindTexture2D](#), [cudaBindTextureToArray](#), [cudaBindTextureToMipmappedArray](#)

CUresult cuTexRefSetFilterMode (CUtexref hTexRef, CUfilter_mode fm)

Sets the filtering mode for a texture reference.

Parameters

hTexRef

- Texture reference

fm

- Filtering mode to set

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Deprecated

Specifies the filtering mode `fm` to be used when reading memory through the texture reference `hTexRef`. `CUfilter_mode_enum` is defined as:

```
↑ typedef enum CUfilter_mode_enum {
    CU_TR_FILTER_MODE_POINT = 0,
    CU_TR_FILTER_MODE_LINEAR = 1
} CUfilter_mode;
```

Note that this call has no effect if `hTexRef` is bound to linear memory.

See also:

[cuTexRefSetAddress](#), [cuTexRefSetAddress2D](#), [cuTexRefSetAddressMode](#), [cuTexRefSetArray](#), [cuTexRefSetFlags](#), [cuTexRefSetFormat](#), [cuTexRefGetAddress](#), [cuTexRefGetAddressMode](#), [cuTexRefGetArray](#), [cuTexRefGetFilterMode](#), [cuTexRefGetFlags](#), [cuTexRefGetFormat](#), [cudaBindTextureToArray](#)

CUresult cuTexRefSetFlags (CUtexref hTexRef, unsigned int Flags)

Sets the flags for a texture reference.

Parameters

hTexRef

- Texture reference

Flags

- Optional flags to set

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Deprecated

Specifies optional flags via `Flags` to specify the behavior of data returned through the texture reference `hTexRef`. The valid flags are:

- ▶ [CU_TRSF_READ_AS_INTEGER](#), which suppresses the default behavior of having the texture promote integer data to floating point data in the range [0, 1]. Note that texture with 32-bit integer format would not be promoted, regardless of whether or not this flag is specified;
- ▶ [CU_TRSF_NORMALIZED_COORDINATES](#), which suppresses the default behavior of having the texture coordinates range from [0, Dim) where Dim is the width or height of the CUDA array. Instead, the texture coordinates [0, 1.0) reference the entire breadth of the array dimension;
- ▶ [CU_TRSF_DISABLE_TRILINEAR_OPTIMIZATION](#), which disables any trilinear filtering optimizations. Trilinear optimizations improve texture filtering performance by allowing bilinear filtering on textures in scenarios where it can closely approximate the expected results.

See also:

[cuTexRefSetAddress](#), [cuTexRefSetAddress2D](#), [cuTexRefSetAddressMode](#), [cuTexRefSetArray](#), [cuTexRefSetFilterMode](#), [cuTexRefSetFormat](#), [cuTexRefGetAddress](#), [cuTexRefGetAddressMode](#), [cuTexRefGetArray](#), [cuTexRefGetFilterMode](#), [cuTexRefGetFlags](#), [cuTexRefGetFormat](#), [cudaBindTexture](#), [cudaBindTexture2D](#), [cudaBindTextureToArray](#), [cudaBindTextureToMipmappedArray](#)

CUresult cuTexRefSetFormat (CUtexref hTexRef, CUarray_format fmt, int NumPackedComponents)

Sets the format for a texture reference.

Parameters

hTexRef

- Texture reference

fmt

- Format to set

NumPackedComponents

- Number of components per array element

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Deprecated

Specifies the format of the data to be read by the texture reference `hTexRef`. `fmt` and `NumPackedComponents` are exactly analogous to the `Format` and `NumChannels` members of the `CUDA_ARRAY_DESCRIPTOR` structure: They specify the format of each component and the number of components per array element.

See also:

[cuTexRefSetAddress](#), [cuTexRefSetAddress2D](#), [cuTexRefSetAddressMode](#), [cuTexRefSetArray](#), [cuTexRefSetFilterMode](#), [cuTexRefSetFlags](#), [cuTexRefGetAddress](#), [cuTexRefGetAddressMode](#), [cuTexRefGetArray](#), [cuTexRefGetFilterMode](#), [cuTexRefGetFlags](#), [cuTexRefGetFormat](#), [cudaCreateChannelDesc](#), [cudaBindTexture](#), [cudaBindTexture2D](#), [cudaBindTextureToArray](#), [cudaBindTextureToMipmappedArray](#)

CUresult cuTexRefSetMaxAnisotropy (CUtexref hTexRef, unsigned int maxAniso)

Sets the maximum anisotropy for a texture reference.

Parameters

hTexRef

- Texture reference

maxAniso

- Maximum anisotropy

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

[Deprecated](#)

Specifies the maximum anisotropy `maxAniso` to be used when reading memory through the texture reference `hTexRef`.

Note that this call has no effect if `hTexRef` is bound to linear memory.

See also:

[cuTexRefSetAddress](#), [cuTexRefSetAddress2D](#), [cuTexRefSetAddressMode](#), [cuTexRefSetArray](#),
[cuTexRefSetFlags](#), [cuTexRefSetFormat](#), [cuTexRefGetAddress](#), [cuTexRefGetAddressMode](#),
[cuTexRefGetArray](#), [cuTexRefGetFilterMode](#), [cuTexRefGetFlags](#), [cuTexRefGetFormat](#),
[cudaBindTextureToArray](#), [cudaBindTextureToMipmappedArray](#)

CUresult cuTexRefSetMipmapFilterMode (CUtexref hTexRef, CUfilter_mode fm)

Sets the mipmap filtering mode for a texture reference.

Parameters**hTexRef**

- Texture reference

fm

- Filtering mode to set

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

[Deprecated](#)

Specifies the mipmap filtering mode `fm` to be used when reading memory through the texture reference `hTexRef`. `CUfilter_mode_enum` is defined as:

```
↑ typedef enum CUfilter_mode_enum {
    CU_TR_FILTER_MODE_POINT = 0,
    CU_TR_FILTER_MODE_LINEAR = 1
```

```
} CUfilter_mode;
```

Note that this call has no effect if `hTexRef` is not bound to a mipmapped array.

See also:

[cuTexRefSetAddress](#), [cuTexRefSetAddress2D](#), [cuTexRefSetAddressMode](#), [cuTexRefSetArray](#), [cuTexRefSetFlags](#), [cuTexRefSetFormat](#), [cuTexRefGetAddress](#), [cuTexRefGetAddressMode](#), [cuTexRefGetArray](#), [cuTexRefGetFilterMode](#), [cuTexRefGetFlags](#), [cuTexRefGetFormat](#), [cudaBindTextureToMipmappedArray](#)

CUresult cuTexRefSetMipmapLevelBias (CUtexref hTexRef, float bias)

Sets the mipmap level bias for a texture reference.

Parameters

hTexRef

- Texture reference

bias

- Mipmap level bias

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Deprecated

Specifies the mipmap level bias `bias` to be added to the specified mipmap level when reading memory through the texture reference `hTexRef`.

Note that this call has no effect if `hTexRef` is not bound to a mipmapped array.

See also:

[cuTexRefSetAddress](#), [cuTexRefSetAddress2D](#), [cuTexRefSetAddressMode](#), [cuTexRefSetArray](#), [cuTexRefSetFlags](#), [cuTexRefSetFormat](#), [cuTexRefGetAddress](#), [cuTexRefGetAddressMode](#), [cuTexRefGetArray](#), [cuTexRefGetFilterMode](#), [cuTexRefGetFlags](#), [cuTexRefGetFormat](#), [cudaBindTextureToMipmappedArray](#)

CUresult cuTexRefSetMipmapLevelClamp (CUtexref hTexRef, float minMipmapLevelClamp, float maxMipmapLevelClamp)

Sets the mipmap min/max mipmap level clamps for a texture reference.

Parameters

hTexRef

- Texture reference

minMipmapLevelClamp

- Mipmap min level clamp

maxMipmapLevelClamp

- Mipmap max level clamp

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Deprecated

Specifies the min/max mipmap level clamps, `minMipmapLevelClamp` and `maxMipmapLevelClamp` respectively, to be used when reading memory through the texture reference `hTexRef`.

Note that this call has no effect if `hTexRef` is not bound to a mipmapped array.

See also:

[cuTexRefSetAddress](#), [cuTexRefSetAddress2D](#), [cuTexRefSetAddressMode](#), [cuTexRefSetArray](#), [cuTexRefSetFlags](#), [cuTexRefSetFormat](#), [cuTexRefGetAddress](#), [cuTexRefGetAddressMode](#), [cuTexRefGetArray](#), [cuTexRefGetFilterMode](#), [cuTexRefGetFlags](#), [cuTexRefGetFormat](#), [cudaBindTextureToMipmappedArray](#)

CUresult cuTexRefSetMipmappedArray (CUtexref hTexRef, CUmipmappedArray hMipmappedArray, unsigned int Flags)

Binds a mipmapped array to a texture reference.

Parameters

hTexRef

- Texture reference to bind

hMipmappedArray

- Mipmapped array to bind

Flags

- Options (must be [CU_TRSA_OVERRIDE_FORMAT](#))

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Deprecated

Binds the CUDA mipmapped array `hMipmappedArray` to the texture reference `hTexRef`. Any previous address or CUDA array state associated with the texture reference is superseded by this function. `Flags` must be set to [CU_TRSA_OVERRIDE_FORMAT](#). Any CUDA array previously bound to `hTexRef` is unbound.

See also:

[cuTexRefSetAddress](#), [cuTexRefSetAddress2D](#), [cuTexRefSetAddressMode](#), [cuTexRefSetFilterMode](#), [cuTexRefSetFlags](#), [cuTexRefSetFormat](#), [cuTexRefGetAddress](#), [cuTexRefGetAddressMode](#), [cuTexRefGetArray](#), [cuTexRefGetFilterMode](#), [cuTexRefGetFlags](#), [cuTexRefGetFormat](#), [cudaBindTextureToMipmappedArray](#)

6.24. Surface Reference Management [DEPRECATED]

This section describes the surface reference management functions of the low-level CUDA driver application programming interface.

CUresult cuSurfRefGetArray (CUarray *phArray, CUsurfref hSurfRef)

Passes back the CUDA array bound to a surface reference.

Parameters

phArray

- Surface reference handle

hSurfRef

- Surface reference handle

Returns

CUDA_SUCCESS, CUDA_ERROR_DEINITIALIZED, CUDA_ERROR_NOT_INITIALIZED, CUDA_ERROR_INVALID_CONTEXT, CUDA_ERROR_INVALID_VALUE

Description

Deprecated

Returns in *phArray the CUDA array bound to the surface reference hSurfRef, or returns CUDA_ERROR_INVALID_VALUE if the surface reference is not bound to any CUDA array.

See also:

cuModuleGetSurfRef, cuSurfRefSetArray

CUresult cuSurfRefSetArray (CUsurfref hSurfRef, CUarray hArray, unsigned int Flags)

Sets the CUDA array for a surface reference.

Parameters

hSurfRef

- Surface reference handle

hArray

- CUDA array handle

Flags

- set to 0

Returns

CUDA_SUCCESS, CUDA_ERROR_DEINITIALIZED, CUDA_ERROR_NOT_INITIALIZED, CUDA_ERROR_INVALID_CONTEXT, CUDA_ERROR_INVALID_VALUE

Description

Deprecated

Sets the CUDA array `hArray` to be read and written by the surface reference `hSurfRef`. Any previous CUDA array state associated with the surface reference is superseded by this function. `Flags` must be set to 0. The `CUDA_ARRAY3D_SURFACE_LDST` flag must have been set for the CUDA array. Any CUDA array previously bound to `hSurfRef` is unbound.

See also:

[cuModuleGetSurfRef](#), [cuSurfRefGetArray](#), [cudaBindSurfaceToArray](#)

6.25. Texture Object Management

This section describes the texture object management functions of the low-level CUDA driver application programming interface. The texture object API is only supported on devices of compute capability 3.0 or higher.

```
CUresult cuTexObjectCreate (CUtexObject
*pTexObject, const CUDA_RESOURCE_DESC
*pResDesc, const CUDA_TEXTURE_DESC
*pTexDesc, const CUDA_RESOURCE_VIEW_DESC
*pResViewDesc)
```

Creates a texture object.

Parameters

pTexObject

- Texture object to create

pResDesc

- Resource descriptor

pTexDesc

- Texture descriptor

pResViewDesc

- Resource view descriptor

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Creates a texture object and returns it in `pTexObject`. `pResDesc` describes the data to texture from. `pTexDesc` describes how the data should be sampled. `pResViewDesc` is an optional argument that specifies an alternate format for the data described by `pResDesc`, and also describes the subresource region to restrict access to when texturing. `pResViewDesc` can only be specified if the type of resource is a CUDA array or a CUDA mipmapped array.

Texture objects are only supported on devices of compute capability 3.0 or higher. Additionally, a texture object is an opaque value, and, as such, should only be accessed through CUDA API calls.

The `CUDA_RESOURCE_DESC` structure is defined as:

```
↑
    typedef struct CUDA_RESOURCE_DESC_st
    {
        CUresourcetype resType;

        union {
            struct {
                CUarray hArray;
            } array;
            struct {
                CUmipmappedArray hMipmappedArray;
            } mipmap;
            struct {
                CUdeviceptr devPtr;
                CUarray_format format;
                unsigned int numChannels;
                size_t sizeInBytes;
            } linear;
            struct {
                CUdeviceptr devPtr;
                CUarray_format format;
                unsigned int numChannels;
                size_t width;
                size_t height;
                size_t pitchInBytes;
            } pitch2D;
        } res;

        unsigned int flags;
    } CUDA_RESOURCE_DESC;
```

where:

- ▶ `CUDA_RESOURCE_DESC::resType` specifies the type of resource to texture from. `CUresourcetype` is defined as:

```
↑
    typedef enum CUresourcetype_enum {
        CU_RESOURCE_TYPE_ARRAY = 0x00,
        CU_RESOURCE_TYPE_MIPMAPPED_ARRAY = 0x01,
        CU_RESOURCE_TYPE_LINEAR = 0x02,
        CU_RESOURCE_TYPE_PITCH2D = 0x03
    } CUresourcetype;
```

If `CUDA_RESOURCE_DESC::resType` is set to `CU_RESOURCE_TYPE_ARRAY`, `CUDA_RESOURCE_DESC::res::array::hArray` must be set to a valid CUDA array handle.

If `CUDA_RESOURCE_DESC::resType` is set to `CU_RESOURCE_TYPE_MIPMAPPED_ARRAY`, `CUDA_RESOURCE_DESC::res::mipmap::hMipmappedArray` must be set to a valid CUDA mipmapped array handle.

If `CUDA_RESOURCE_DESC::resType` is set to `CU_RESOURCE_TYPE_LINEAR`, `CUDA_RESOURCE_DESC::res::linear::devPtr` must be set to a valid device pointer, that is aligned to `CU_DEVICE_ATTRIBUTE_TEXTURE_ALIGNMENT`. `CUDA_RESOURCE_DESC::res::linear::format` and `CUDA_RESOURCE_DESC::res::linear::numChannels` describe the format of each component and the number of components per array element. `CUDA_RESOURCE_DESC::res::linear::sizeInBytes` specifies the size of the array in bytes. The total number of elements in the linear address range cannot exceed `CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE1D_LINEAR_WIDTH`. The number of elements is computed as $(\text{sizeInBytes} / (\text{sizeof}(\text{format}) * \text{numChannels}))$.

If `CUDA_RESOURCE_DESC::resType` is set to `CU_RESOURCE_TYPE_PITCH2D`, `CUDA_RESOURCE_DESC::res::pitch2D::devPtr` must be set to a valid device pointer, that is aligned to `CU_DEVICE_ATTRIBUTE_TEXTURE_ALIGNMENT`. `CUDA_RESOURCE_DESC::res::pitch2D::format` and `CUDA_RESOURCE_DESC::res::pitch2D::numChannels` describe the format of each component and the number of components per array element. `CUDA_RESOURCE_DESC::res::pitch2D::width` and `CUDA_RESOURCE_DESC::res::pitch2D::height` specify the width and height of the array in elements, and cannot exceed `CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_LINEAR_WIDTH` and `CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_LINEAR_HEIGHT` respectively. `CUDA_RESOURCE_DESC::res::pitch2D::pitchInBytes` specifies the pitch between two rows in bytes and has to be aligned to `CU_DEVICE_ATTRIBUTE_TEXTURE_PITCH_ALIGNMENT`. Pitch cannot exceed `CU_DEVICE_ATTRIBUTE_MAXIMUM_TEXTURE2D_LINEAR_PITCH`.

- flags must be set to zero.

The `CUDA_TEXTURE_DESC` struct is defined as

```
↑
    typedef struct CUDA_TEXTURE_DESC_st {
        CUaddress_mode addressMode[3];
        CUfilter_mode filterMode;
        unsigned int flags;
        unsigned int maxAnisotropy;
        CUfilter_mode mipmapFilterMode;
        float mipmapLevelBias;
        float minMipmapLevelClamp;
        float maxMipmapLevelClamp;
    } CUDA_TEXTURE_DESC;
```

where

- `CUDA_TEXTURE_DESC::addressMode` specifies the addressing mode for each dimension of the texture data. `CUaddress_mode` is defined as:

```
↑
    typedef enum CUaddress_mode_enum {
        CU_TR_ADDRESS_MODE_WRAP = 0,
        CU_TR_ADDRESS_MODE_CLAMP = 1,
```

```

        CU_TR_ADDRESS_MODE_MIRROR = 2,
        CU_TR_ADDRESS_MODE_BORDER = 3
    } CUaddress_mode;

```

This is ignored if `CUDA_RESOURCE_DESC::resType` is `CU_RESOURCE_TYPE_LINEAR`. Also, if the flag, `CU_TRSF_NORMALIZED_COORDINATES` is not set, the only supported address mode is `CU_TR_ADDRESS_MODE_CLAMP`.

- ▶ `CUDA_TEXTURE_DESC::filterMode` specifies the filtering mode to be used when fetching from the texture. `CUfilter_mode` is defined as:

```

↑ typedef enum CUfilter_mode_enum {
    CU_TR_FILTER_MODE_POINT = 0,
    CU_TR_FILTER_MODE_LINEAR = 1
} CUfilter_mode;

```

This is ignored if `CUDA_RESOURCE_DESC::resType` is `CU_RESOURCE_TYPE_LINEAR`.

- ▶ `CUDA_TEXTURE_DESC::flags` can be any combination of the following:
 - ▶ `CU_TRSF_READ_AS_INTEGER`, which suppresses the default behavior of having the texture promote integer data to floating point data in the range [0, 1]. Note that texture with 32-bit integer format would not be promoted, regardless of whether or not this flag is specified.
 - ▶ `CU_TRSF_NORMALIZED_COORDINATES`, which suppresses the default behavior of having the texture coordinates range from [0, Dim] where Dim is the width or height of the CUDA array. Instead, the texture coordinates [0, 1.0] reference the entire breadth of the array dimension; Note that for CUDA mipmapped arrays, this flag has to be set.
 - ▶ `CU_TRSF_DISABLE_TRILINEAR_OPTIMIZATION`, which disables any trilinear filtering optimizations. Trilinear optimizations improve texture filtering performance by allowing bilinear filtering on textures in scenarios where it can closely approximate the expected results.
- ▶ `CUDA_TEXTURE_DESC::maxAnisotropy` specifies the maximum anisotropy ratio to be used when doing anisotropic filtering. This value will be clamped to the range [1,16].
- ▶ `CUDA_TEXTURE_DESC::mipmapFilterMode` specifies the filter mode when the calculated mipmap level lies between two defined mipmap levels.
- ▶ `CUDA_TEXTURE_DESC::mipmapLevelBias` specifies the offset to be applied to the calculated mipmap level.
- ▶ `CUDA_TEXTURE_DESC::minMipmapLevelClamp` specifies the lower end of the mipmap level range to clamp access to.
- ▶ `CUDA_TEXTURE_DESC::maxMipmapLevelClamp` specifies the upper end of the mipmap level range to clamp access to.

The `CUDA_RESOURCE_VIEW_DESC` struct is defined as

```

↑ typedef struct CUDA_RESOURCE_VIEW_DESC_st
    {
        CUresourceViewFormat format;
        size_t width;
        size_t height;
        size_t depth;
    };

```

```

        unsigned int firstMipmapLevel;
        unsigned int lastMipmapLevel;
        unsigned int firstLayer;
        unsigned int lastLayer;
    } CUDA_RESOURCE_VIEW_DESC;

```

where:

- ▶ [CUDA_RESOURCE_VIEW_DESC::format](#) specifies how the data contained in the CUDA array or CUDA mipmapped array should be interpreted. Note that this can incur a change in size of the texture data. If the resource view format is a block compressed format, then the underlying CUDA array or CUDA mipmapped array has to have a base of format [CU_AD_FORMAT_UNSIGNED_INT32](#) with 2 or 4 channels, depending on the block compressed format. For ex., BC1 and BC4 require the underlying CUDA array to have a format of [CU_AD_FORMAT_UNSIGNED_INT32](#) with 2 channels. The other BC formats require the underlying resource to have the same base format but with 4 channels.
- ▶ [CUDA_RESOURCE_VIEW_DESC::width](#) specifies the new width of the texture data. If the resource view format is a block compressed format, this value has to be 4 times the original width of the resource. For non block compressed formats, this value has to be equal to that of the original resource.
- ▶ [CUDA_RESOURCE_VIEW_DESC::height](#) specifies the new height of the texture data. If the resource view format is a block compressed format, this value has to be 4 times the original height of the resource. For non block compressed formats, this value has to be equal to that of the original resource.
- ▶ [CUDA_RESOURCE_VIEW_DESC::depth](#) specifies the new depth of the texture data. This value has to be equal to that of the original resource.
- ▶ [CUDA_RESOURCE_VIEW_DESC::firstMipmapLevel](#) specifies the most detailed mipmap level. This will be the new mipmap level zero. For non-mipmapped resources, this value has to be zero. [CUDA_TEXTURE_DESC::minMipmapLevelClamp](#) and [CUDA_TEXTURE_DESC::maxMipmapLevelClamp](#) will be relative to this value. For ex., if the firstMipmapLevel is set to 2, and a minMipmapLevelClamp of 1.2 is specified, then the actual minimum mipmap level clamp will be 3.2.
- ▶ [CUDA_RESOURCE_VIEW_DESC::lastMipmapLevel](#) specifies the least detailed mipmap level. For non-mipmapped resources, this value has to be zero.
- ▶ [CUDA_RESOURCE_VIEW_DESC::firstLayer](#) specifies the first layer index for layered textures. This will be the new layer zero. For non-layered resources, this value has to be zero.
- ▶ [CUDA_RESOURCE_VIEW_DESC::lastLayer](#) specifies the last layer index for layered textures. For non-layered resources, this value has to be zero.

See also:

[cuTexObjectDestroy](#), [cudaCreateTextureObject](#)

CUresult cuTexObjectDestroy (CUtexObject texObject)

Destroys a texture object.

Parameters

texObject

- Texture object to destroy

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Destroys the texture object specified by `texObject`.

See also:

[cuTexObjectCreate](#), [cudaDestroyTextureObject](#)

CUresult cuTexObjectGetResourceDesc (CUDA_RESOURCE_DESC *pResDesc, CUtexObject texObject)

Returns a texture object's resource descriptor.

Parameters

pResDesc

- Resource descriptor

texObject

- Texture object

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Returns the resource descriptor for the texture object specified by `texObject`.

See also:

[cuTexObjectCreate](#), [cudaGetTextureObjectResourceDesc](#),

CUresult cuTexObjectGetResourceViewDesc (CUDA_RESOURCE_VIEW_DESC *pResViewDesc, CUtexObject texObject)

Returns a texture object's resource view descriptor.

Parameters

pResViewDesc

- Resource view descriptor

texObject

- Texture object

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Returns the resource view descriptor for the texture object specified by `texObject`. If no resource view was set for `texObject`, the [CUDA_ERROR_INVALID_VALUE](#) is returned.

See also:

[cuTexObjectCreate](#), [cudaGetTextureObjectResourceViewDesc](#)

CUresult cuTexObjectGetTextureDesc (CUDA_TEXTURE_DESC *pTexDesc, CUtexObject texObject)

Returns a texture object's texture descriptor.

Parameters

pTexDesc

- Texture descriptor

texObject

- Texture object

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Returns the texture descriptor for the texture object specified by `texObject`.

See also:

[cuTexObjectCreate](#), [cudaGetTextureObjectTextureDesc](#)

6.26. Surface Object Management

This section describes the surface object management functions of the low-level CUDA driver application programming interface. The surface object API is only supported on devices of compute capability 3.0 or higher.

```
CUresult cuSurfObjectCreate (CUsurfObject
*pSurfObject, const CUDA_RESOURCE_DESC
*pResDesc)
```

Creates a surface object.

Parameters

pSurfObject

- Surface object to create

pResDesc

- Resource descriptor

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Creates a surface object and returns it in `pSurfObject`. `pResDesc` describes the data to perform surface load/stores on. [CUDA_RESOURCE_DESC::resType](#) must be [CU_RESOURCE_TYPE_ARRAY](#) and [CUDA_RESOURCE_DESC::res::array::hArray](#) must be set to a valid CUDA array handle. [CUDA_RESOURCE_DESC::flags](#) must be set to zero.

Surface objects are only supported on devices of compute capability 3.0 or higher. Additionally, a surface object is an opaque value, and, as such, should only be accessed through CUDA API calls.

See also:

[cuSurfObjectDestroy](#), [cudaCreateSurfaceObject](#)

CUresult cuSurfObjectDestroy (CUsurfObject surfObject)

Destroys a surface object.

Parameters

surfObject

- Surface object to destroy

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Destroys the surface object specified by `surfObject`.

See also:

[cuSurfObjectCreate](#), [cudaDestroySurfaceObject](#)

CUresult cuSurfObjectGetResourceDesc (CUDA_RESOURCE_DESC *pResDesc, CUsurfObject surfObject)

Returns a surface object's resource descriptor.

Parameters

pResDesc

- Resource descriptor

surfObject

- Surface object

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Returns the resource descriptor for the surface object specified by `surfObject`.

See also:

[cuSurfObjectCreate](#), [cudaGetSurfaceObjectResourceDesc](#)

6.27. Peer Context Memory Access

This section describes the direct peer context memory access functions of the low-level CUDA driver application programming interface.

CUresult cuCtxDisablePeerAccess (CUcontext peerContext)

Disables direct access to memory allocations in a peer context and unregisters any registered allocations.

Parameters

peerContext

- Peer context to disable direct access to

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_PEER_ACCESS_NOT_ENABLED](#), [CUDA_ERROR_INVALID_CONTEXT](#),

Description

Returns [CUDA_ERROR_PEER_ACCESS_NOT_ENABLED](#) if direct peer access has not yet been enabled from `peerContext` to the current context.

Returns [CUDA_ERROR_INVALID_CONTEXT](#) if there is no current context, or if `peerContext` is not a valid context.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuDeviceCanAccessPeer](#), [cuCtxEnablePeerAccess](#), [cudaDeviceDisablePeerAccess](#)

CUresult cuCtxEnablePeerAccess (CUcontext peerContext, unsigned int Flags)

Enables direct access to memory allocations in a peer context.

Parameters

peerContext

- Peer context to enable direct access to from the current context

Flags

- Reserved for future use and must be set to 0

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_PEER_ACCESS_ALREADY_ENABLED](#), [CUDA_ERROR_TOO_MANY_PEERS](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_PEER_ACCESS_UNSUPPORTED](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

If both the current context and `peerContext` are on devices which support unified addressing (as may be queried using [CU_DEVICE_ATTRIBUTE_UNIFIED_ADDRESSING](#)) and same major compute capability, then on success all allocations from `peerContext` will immediately be accessible by the current context. See [Unified Addressing](#) for additional details.

Note that access granted by this call is unidirectional and that in order to access memory from the current context in `peerContext`, a separate symmetric call to [cuCtxEnablePeerAccess\(\)](#) is required.

Note that there are both device-wide and system-wide limitations per system configuration, as noted in the CUDA Programming Guide under the section "Peer-to-Peer Memory Access".

Returns [CUDA_ERROR_PEER_ACCESS_UNSUPPORTED](#) if [cuDeviceCanAccessPeer\(\)](#) indicates that the [CUdevice](#) of the current context cannot directly access memory from the [CUdevice](#) of `peerContext`.

Returns [CUDA_ERROR_PEER_ACCESS_ALREADY_ENABLED](#) if direct access of `peerContext` from the current context has already been enabled.

Returns [CUDA_ERROR_TOO_MANY_PEERS](#) if direct peer access is not possible because hardware resources required for peer access have been exhausted.

Returns [CUDA_ERROR_INVALID_CONTEXT](#) if there is no current context, `peerContext` is not a valid context, or if the current context is `peerContext`.

Returns [CUDA_ERROR_INVALID_VALUE](#) if `Flags` is not 0.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuDeviceCanAccessPeer](#), [cuCtxDisablePeerAccess](#), [cudaDeviceEnablePeerAccess](#)

CUresult cuDeviceCanAccessPeer (int *canAccessPeer, CUdevice dev, CUdevice peerDev)

Queries if a device may directly access a peer device's memory.

Parameters

canAccessPeer

- Returned access capability

dev

- Device from which allocations on `peerDev` are to be directly accessed.

peerDev

- Device on which the allocations to be directly accessed by `dev` reside.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_DEVICE](#)

Description

Returns in `*canAccessPeer` a value of 1 if contexts on `dev` are capable of directly accessing memory from contexts on `peerDev` and 0 otherwise. If direct access of `peerDev` from `dev` is possible, then access may be enabled on two specific contexts by calling [cuCtxEnablePeerAccess\(\)](#).

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuCtxEnablePeerAccess](#), [cuCtxDisablePeerAccess](#), [cudaDeviceCanAccessPeer](#)

CUresult cuDeviceGetP2PAttribute (int *value, CUdevice_P2PAttribute attrib, CUdevice srcDevice, CUdevice dstDevice)

Queries attributes of the link between two devices.

Parameters

value

- Returned value of the requested attribute

attrib

- The requested attribute of the link between `srcDevice` and `dstDevice`.

srcDevice

- The source device of the target link.

dstDevice

- The destination device of the target link.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_DEVICE](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Returns in `*value` the value of the requested attribute `attrib` of the link between `srcDevice` and `dstDevice`. The supported attributes are:

- ▶ [CU_DEVICE_P2P_ATTRIBUTE_PERFORMANCE_RANK](#): A relative value indicating the performance of the link between two devices.
- ▶ [CU_DEVICE_P2P_ATTRIBUTE_ACCESS_SUPPORTED](#) P2P: 1 if P2P Access is enable.
- ▶ [CU_DEVICE_P2P_ATTRIBUTE_NATIVE_ATOMIC_SUPPORTED](#): 1 if Atomic operations over the link are supported.
- ▶ [CU_DEVICE_P2P_ATTRIBUTE_CUDA_ARRAY_ACCESS_SUPPORTED](#): 1 if `cudaArray` can be accessed over the link.

Returns [CUDA_ERROR_INVALID_DEVICE](#) if `srcDevice` or `dstDevice` are not valid or if they represent the same device.

Returns [CUDA_ERROR_INVALID_VALUE](#) if `attrib` is not valid or if `value` is a null pointer.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuCtxEnablePeerAccess](#), [cuCtxDisablePeerAccess](#), [cuDeviceCanAccessPeer](#),
[cudaDeviceGetP2PAttribute](#)

6.28. Graphics Interoperability

This section describes the graphics interoperability functions of the low-level CUDA driver application programming interface.

CUresult cuGraphicsMapResources (unsigned int count, CUgraphicsResource *resources, CUstream hStream)

Map graphics resources for access by CUDA.

Parameters

count

- Number of resources to map

resources

- Resources to map for CUDA usage

hStream

- Stream with which to synchronize

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_HANDLE](#),
[CUDA_ERROR_ALREADY_MAPPED](#), [CUDA_ERROR_UNKNOWN](#)

Description

Maps the `count` graphics resources in `resources` for access by CUDA.

The resources in `resources` may be accessed by CUDA until they are unmapped. The graphics API from which `resources` were registered should not access any resources while they are mapped by CUDA. If an application does so, the results are undefined.

This function provides the synchronization guarantee that any graphics calls issued before [cuGraphicsMapResources\(\)](#) will complete before any subsequent CUDA work issued in `stream` begins.

If `resources` includes any duplicate entries then [CUDA_ERROR_INVALID_HANDLE](#) is returned. If any of `resources` are presently mapped for access by CUDA then [CUDA_ERROR_ALREADY_MAPPED](#) is returned.

**Note:**

- ▶ This function uses standard [default stream](#) semantics.
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphicsResourceGetMappedPointer](#), [cuGraphicsSubResourceGetMappedArray](#),
[cuGraphicsUnmapResources](#), [cudaGraphicsMapResources](#)

CUresult

cuGraphicsResourceGetMappedMipmappedArray (CUmipmappedArray *pMipmappedArray, CUgraphicsResource resource)

Get a mipmapped array through which to access a mapped graphics resource.

Parameters

pMipmappedArray

- Returned mipmapped array through which `resource` may be accessed

resource

- Mapped resource to access

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_NOT_MAPPED](#),
[CUDA_ERROR_NOT_MAPPED_AS_ARRAY](#)

Description

Returns in `*pMipmappedArray` a mipmapped array through which the mapped graphics resource `resource`. The value set in `*pMipmappedArray` may change every time that `resource` is mapped.

If `resource` is not a texture then it cannot be accessed via a mipmapped array and [CUDA_ERROR_NOT_MAPPED_AS_ARRAY](#) is returned. If `resource` is not mapped then [CUDA_ERROR_NOT_MAPPED](#) is returned.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphicsResourceGetMappedPointer](#), [cudaGraphicsResourceGetMappedMipmappedArray](#)

CUresult cuGraphicsResourceGetMappedPointer (CUdeviceptr *pDevPtr, size_t *pSize, CUgraphicsResource resource)

Get a device pointer through which to access a mapped graphics resource.

Parameters

pDevPtr

- Returned pointer through which `resource` may be accessed

pSize

- Returned size of the buffer accessible starting at `*pPointer`

resource

- Mapped resource to access

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_NOT_MAPPED](#),
[CUDA_ERROR_NOT_MAPPED_AS_POINTER](#)

Description

Returns in `*pDevPtr` a pointer through which the mapped graphics resource `resource` may be accessed. Returns in `pSize` the size of the memory in bytes which may be accessed from that pointer. The value set in `pPointer` may change every time that `resource` is mapped.

If `resource` is not a buffer then it cannot be accessed via a pointer and [CUDA_ERROR_NOT_MAPPED_AS_POINTER](#) is returned. If `resource` is not mapped then [CUDA_ERROR_NOT_MAPPED](#) is returned. *



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphicsMapResources](#), [cuGraphicsSubResourceGetMappedArray](#),
[cudaGraphicsResourceGetMappedPointer](#)

CUresult cuGraphicsResourceSetMapFlags (CUgraphicsResource resource, unsigned int flags)

Set usage flags for mapping a graphics resource.

Parameters

resource

- Registered resource to set flags for

flags

- Parameters for resource mapping

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_ALREADY_MAPPED](#)

Description

Set `flags` for mapping the graphics resource `resource`.

Changes to `flags` will take effect the next time `resource` is mapped. The `flags` argument may be any of the following:

- ▶ `CU_GRAPHICS_MAP_RESOURCE_FLAGS_NONE`: Specifies no hints about how this resource will be used. It is therefore assumed that this resource will be read from and written to by CUDA kernels. This is the default value.
- ▶ `CU_GRAPHICS_MAP_RESOURCE_FLAGS_READONLY`: Specifies that CUDA kernels which access this resource will not write to this resource.
- ▶ `CU_GRAPHICS_MAP_RESOURCE_FLAGS_WRITEDISCARD`: Specifies that CUDA kernels which access this resource will not read from this resource and will write over the entire contents of the resource, so none of the data previously stored in the resource will be preserved.

If `resource` is presently mapped for access by CUDA then [CUDA_ERROR_ALREADY_MAPPED](#) is returned. If `flags` is not one of the above values then [CUDA_ERROR_INVALID_VALUE](#) is returned.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphicsMapResources](#), [cudaGraphicsResourceSetMapFlags](#)

CUresult cuGraphicsSubResourceGetMappedArray (CUarray *pArray, CUgraphicsResource resource, unsigned int arrayIndex, unsigned int mipLevel)

Get an array through which to access a subresource of a mapped graphics resource.

Parameters

pArray

- Returned array through which a subresource of `resource` may be accessed

resource

- Mapped resource to access

arrayIndex

- Array index for array textures or cubemap face index as defined by [CUarray_cubemap_face](#) for cubemap textures for the subresource to access

mipLevel

- Mipmap level for the subresource to access

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_NOT_MAPPED](#),
[CUDA_ERROR_NOT_MAPPED_AS_ARRAY](#)

Description

Returns in `*pArray` an array through which the subresource of the mapped graphics resource `resource` which corresponds to array index `arrayIndex` and mipmap level `mipLevel` may be accessed. The value set in `*pArray` may change every time that `resource` is mapped.

If `resource` is not a texture then it cannot be accessed via an array and [CUDA_ERROR_NOT_MAPPED_AS_ARRAY](#) is returned. If `arrayIndex` is not a valid array index for `resource` then [CUDA_ERROR_INVALID_VALUE](#) is returned. If `mipLevel` is not a valid mipmap level for `resource` then [CUDA_ERROR_INVALID_VALUE](#) is returned. If `resource` is not mapped then [CUDA_ERROR_NOT_MAPPED](#) is returned.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphicsResourceGetMappedPointer](#), [cudaGraphicsSubResourceGetMappedArray](#)

CUresult cuGraphicsUnmapResources (unsigned int count, CUgraphicsResource *resources, CUstream hStream)

Unmap graphics resources.

Parameters

count

- Number of resources to unmap

resources

- Resources to unmap

hStream

- Stream with which to synchronize

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_NOT_MAPPED](#), [CUDA_ERROR_UNKNOWN](#)

Description

Unmaps the `count` graphics resources in `resources`.

Once unmapped, the resources in `resources` may not be accessed by CUDA until they are mapped again.

This function provides the synchronization guarantee that any CUDA work issued in `stream` before [cuGraphicsUnmapResources\(\)](#) will complete before any subsequently issued graphics work begins.

If `resources` includes any duplicate entries then [CUDA_ERROR_INVALID_HANDLE](#) is returned. If any of `resources` are not presently mapped for access by CUDA then [CUDA_ERROR_NOT_MAPPED](#) is returned.



Note:

- ▶ This function uses standard [default stream](#) semantics.
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphicsMapResources](#), [cudaGraphicsUnmapResources](#)

CUresult cuGraphicsUnregisterResource (CUgraphicsResource resource)

Unregisters a graphics resource for access by CUDA.

Parameters

resource

- Resource to unregister

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_HANDLE](#),
[CUDA_ERROR_UNKNOWN](#)

Description

Unregisters the graphics resource `resource` so it is not accessible by CUDA unless registered again.

If `resource` is invalid then [CUDA_ERROR_INVALID_HANDLE](#) is returned.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphicsD3D9RegisterResource](#), [cuGraphicsD3D10RegisterResource](#),
[cuGraphicsD3D11RegisterResource](#), [cuGraphicsGLRegisterBuffer](#),
[cuGraphicsGLRegisterImage](#), [cudaGraphicsUnregisterResource](#)

6.29. Driver Entry Point Access

This section describes the driver entry point access functions of the low-level CUDA driver application programming interface.

CUresult cuGetProcAddress (const char *symbol, void **pfn, int cudaVersion, cuuint64_t flags)

Returns the requested driver API function pointer.

Parameters

symbol

- The base name of the driver API function to look for. As an example, for the driver API `cuMemAlloc_v2`, `symbol` would be `cuMemAlloc` and `cudaVersion` would be the ABI compatible CUDA version for the `_v2` variant.

pfn

- Location to return the function pointer to the requested driver function

cudaVersion

- The CUDA version to look for the requested driver symbol

flags

- Flags to specify search options.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_NOT_SUPPORTED](#), [CUDA_ERROR_NOT_FOUND](#)

Description

Returns in `**pfn` the address of the CUDA driver function for the requested CUDA version and flags.

The CUDA version is specified as $(1000 * \text{major} + 10 * \text{minor})$, so CUDA 11.2 should be specified as 11020. For a requested driver symbol, if the specified CUDA version is greater than or equal to the CUDA version in which the driver symbol was introduced, this API will return the function pointer to the corresponding versioned function.

The pointer returned by the API should be cast to a function pointer matching the requested driver function's definition in the API header file. The function pointer typedef can be picked up from the corresponding typedefs header file. For example, `cudaTypedefs.h` consists of function pointer typedefs for driver APIs defined in `cuda.h`.

The API will return [CUDA_ERROR_NOT_FOUND](#) if the requested driver function is not supported on the platform, no ABI compatible driver function exists for the specified `cudaVersion` or if the driver symbol is invalid.

The requested flags can be:

- ▶ [CU_GET_PROC_ADDRESS_DEFAULT](#): This is the default mode. This is equivalent to [CU_GET_PROC_ADDRESS_PER_THREAD_DEFAULT_STREAM](#) if the code is compiled with `--default-stream per-thread` compilation flag

or the macro `CUDA_API_PER_THREAD_DEFAULT_STREAM` is defined;
[CU_GET_PROC_ADDRESS_LEGACY_STREAM](#) otherwise.

- ▶ [CU_GET_PROC_ADDRESS_LEGACY_STREAM](#): This will enable the search for all driver symbols that match the requested driver symbol name except the corresponding per-thread versions.
- ▶ [CU_GET_PROC_ADDRESS_PER_THREAD_DEFAULT_STREAM](#): This will enable the search for all driver symbols that match the requested driver symbol name including the per-thread versions. If a per-thread version is not found, the API will return the legacy version of the driver function.



Note:

Version mixing among CUDA-defined types and driver API versions is strongly discouraged and doing so can result in an undefined behavior. [More here](#).

See also:

[cudaGetDriverEntryPoint](#)

6.30. Profiler Control [DEPRECATED]

This section describes the profiler control functions of the low-level CUDA driver application programming interface.

CUresult cuProfilerInitialize (const char *configFile, const char *outputFile, CUoutput_mode outputMode)

Initialize the profiling.

Parameters

configFile

- Name of the config file that lists the counters/options for profiling.

outputFile

- Name of the outputFile where the profiling results will be stored.

outputMode

- outputMode, can be `CU_OUT_KEY_VALUE_PAIR` or `CU_OUT_CSV`.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_PROFILER_DISABLED](#)

Description

Deprecated

Using this API user can initialize the CUDA profiler by specifying the configuration file, output file and output file format. This API is generally used to profile different set of counters by looping the kernel launch. The `configFile` parameter can be used to select profiling options including profiler counters. Refer to the "Compute Command Line Profiler User Guide" for supported profiler options and counters.

Limitation: The CUDA profiler cannot be initialized with this API if another profiling tool is already active, as indicated by the `CUDA_ERROR_PROFILER_DISABLED` return code.

Typical usage of the profiling APIs is as follows:

```
for each set of counters/options { cuProfilerInitialize\(\); //Initialize profiling, set the counters
or options in the config file ... cuProfilerStart\(\); // code to be profiled cuProfilerStop\(\); ...
cuProfilerStart\(\); // code to be profiled cuProfilerStop\(\); ... }
```



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuProfilerStart](#), [cuProfilerStop](#), [cudaProfilerInitialize](#)

6.31. Profiler Control

This section describes the profiler control functions of the low-level CUDA driver application programming interface.

CUresult [cuProfilerStart](#) (void)

Enable profiling.

Returns

`CUDA_SUCCESS`, [CUDA_ERROR_INVALID_CONTEXT](#)

Description

Enables profile collection by the active profiling tool for the current context. If profiling is already enabled, then [cuProfilerStart\(\)](#) has no effect.

`cuProfilerStart` and `cuProfilerStop` APIs are used to programmatically control the profiling granularity by allowing profiling to be done only on selective pieces of code.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuProfilerInitialize](#), [cuProfilerStop](#), [cudaProfilerStart](#)

CUresult cuProfilerStop (void)

Disable profiling.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_CONTEXT](#)

Description

Disables profile collection by the active profiling tool for the current context. If profiling is already disabled, then [cuProfilerStop\(\)](#) has no effect.

[cuProfilerStart](#) and [cuProfilerStop](#) APIs are used to programmatically control the profiling granularity by allowing profiling to be done only on selective pieces of code.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuProfilerInitialize](#), [cuProfilerStart](#), [cudaProfilerStop](#)

6.32. OpenGL Interoperability

This section describes the OpenGL interoperability functions of the low-level CUDA driver application programming interface. Note that mapping of OpenGL resources is performed with the graphics API agnostic, resource mapping interface described in [Graphics Interoperability](#).

OpenGL Interoperability [DEPRECATED]

enum CUGLDeviceList

CUDA devices corresponding to an OpenGL device

Values

CU_GL_DEVICE_LIST_ALL = 0x01

The CUDA devices for all GPUs used by the current OpenGL context

CU_GL_DEVICE_LIST_CURRENT_FRAME = 0x02

The CUDA devices for the GPUs used by the current OpenGL context in its currently rendering frame

CU_GL_DEVICE_LIST_NEXT_FRAME = 0x03

The CUDA devices for the GPUs to be used by the current OpenGL context in the next frame

CUresult cuGLGetDevices (unsigned int *pCudaDeviceCount, CUdevice *pCudaDevices, unsigned int cudaDeviceCount, CUGLDeviceList deviceList)

Gets the CUDA devices associated with the current OpenGL context.

Parameters

pCudaDeviceCount

- Returned number of CUDA devices.

pCudaDevices

- Returned CUDA devices.

cudaDeviceCount

- The size of the output device array pCudaDevices.

deviceList

- The set of devices to return.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_NO_DEVICE](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_GRAPHICS_CONTEXT](#)

Description

Returns in *pCudaDeviceCount the number of CUDA-compatible devices corresponding to the current OpenGL context. Also returns in *pCudaDevices at most cudaDeviceCount of the CUDA-compatible devices corresponding to the current OpenGL context. If any of the GPUs being used by the current OpenGL context are not CUDA capable then the call will return [CUDA_ERROR_NO_DEVICE](#).

The deviceList argument may be any of the following:

- ▶ [CU_GL_DEVICE_LIST_ALL](#): Query all devices used by the current OpenGL context.

- ▶ [CU_GL_DEVICE_LIST_CURRENT_FRAME](#): Query the devices used by the current OpenGL context to render the current frame (in SLI).
- ▶ [CU_GL_DEVICE_LIST_NEXT_FRAME](#): Query the devices used by the current OpenGL context to render the next frame (in SLI). Note that this is a prediction, it can't be guaranteed that this is correct in all cases.

**Note:**

- ▶ This function is not supported on Mac OS X.
- ▶ Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuWGLGetDevice](#), [cudaGLGetDevices](#)

CUresult cuGraphicsGLRegisterBuffer (CUgraphicsResource *pCudaResource, GLuint buffer, unsigned int Flags)

Registers an OpenGL buffer object.

Parameters

pCudaResource

- Pointer to the returned object handle

buffer

- name of buffer object to be registered

Flags

- Register flags

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_ALREADY_MAPPED](#),
[CUDA_ERROR_INVALID_CONTEXT](#),

Description

Registers the buffer object specified by `buffer` for access by CUDA. A handle to the registered object is returned as `pCudaResource`. The register flags `Flags` specify the intended usage, as follows:

- ▶ [CU_GRAPHICS_REGISTER_FLAGS_NONE](#): Specifies no hints about how this resource will be used. It is therefore assumed that this resource will be read from and written to by CUDA. This is the default value.

- ▶ `CU_GRAPHICS_REGISTER_FLAGS_READ_ONLY`: Specifies that CUDA will not write to this resource.
- ▶ `CU_GRAPHICS_REGISTER_FLAGS_WRITE_DISCARD`: Specifies that CUDA will not read from this resource and will write over the entire contents of the resource, so none of the data previously stored in the resource will be preserved.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphicsUnregisterResource](#), [cuGraphicsMapResources](#),
[cuGraphicsResourceGetMappedPointer](#), [cudaGraphicsGLRegisterBuffer](#)

CUresult cuGraphicsGLRegisterImage (CUgraphicsResource *pCudaResource, GLuint image, GLenum target, unsigned int Flags)

Register an OpenGL texture or renderbuffer object.

Parameters

pCudaResource

- Pointer to the returned object handle

image

- name of texture or renderbuffer object to be registered

target

- Identifies the type of object specified by `image`

Flags

- Register flags

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_ALREADY_MAPPED](#),
[CUDA_ERROR_INVALID_CONTEXT](#),

Description

Registers the texture or renderbuffer object specified by `image` for access by CUDA. A handle to the registered object is returned as `pCudaResource`.

`target` must match the type of the object, and must be one of `GL_TEXTURE_2D`, `GL_TEXTURE_RECTANGLE`, `GL_TEXTURE_CUBE_MAP`, `GL_TEXTURE_3D`, `GL_TEXTURE_2D_ARRAY`, or `GL_RENDERBUFFER`.

The register flags `Flags` specify the intended usage, as follows:

- ▶ `CU_GRAPHICS_REGISTER_FLAGS_NONE`: Specifies no hints about how this resource will be used. It is therefore assumed that this resource will be read from and written to by CUDA. This is the default value.
- ▶ `CU_GRAPHICS_REGISTER_FLAGS_READ_ONLY`: Specifies that CUDA will not write to this resource.
- ▶ `CU_GRAPHICS_REGISTER_FLAGS_WRITE_DISCARD`: Specifies that CUDA will not read from this resource and will write over the entire contents of the resource, so none of the data previously stored in the resource will be preserved.
- ▶ `CU_GRAPHICS_REGISTER_FLAGS_SURFACE_LDST`: Specifies that CUDA will bind this resource to a surface reference.
- ▶ `CU_GRAPHICS_REGISTER_FLAGS_TEXTURE_GATHER`: Specifies that CUDA will perform texture gather operations on this resource.

The following image formats are supported. For brevity's sake, the list is abbreviated. For ex., `{GL_R, GL_RG} X {8, 16}` would expand to the following 4 formats `{GL_R8, GL_R16, GL_RG8, GL_RG16}` :

- ▶ `GL_RED, GL_RG, GL_RGBA, GL_LUMINANCE, GL_ALPHA, GL_LUMINANCE_ALPHA, GL_INTENSITY`
- ▶ `{GL_R, GL_RG, GL_RGBA} X {8, 16, 16F, 32F, 8UI, 16UI, 32UI, 8I, 16I, 32I}`
- ▶ `{GL_LUMINANCE, GL_ALPHA, GL_LUMINANCE_ALPHA, GL_INTENSITY} X {8, 16, 16F_ARB, 32F_ARB, 8UI_EXT, 16UI_EXT, 32UI_EXT, 8I_EXT, 16I_EXT, 32I_EXT}`

The following image classes are currently disallowed:

- ▶ Textures with borders
- ▶ Multisampled renderbuffers



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphicsUnregisterResource](#), [cuGraphicsMapResources](#), [cuGraphicsSubResourceGetMappedArray](#), [cudaGraphicsGLRegisterImage](#)

CUresult cuWGLGetDevice (CUdevice *pDevice, HGPUNV hGpu)

Gets the CUDA device associated with hGpu.

Parameters

pDevice

- Device associated with hGpu

hGpu

- Handle to a GPU, as queried via WGL_NV_gpu_affinity()

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Returns in *pDevice the CUDA device associated with a hGpu, if applicable.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGLMapBufferObject](#), [cuGLRegisterBufferObject](#), [cuGLUnmapBufferObject](#), [cuGLUnregisterBufferObject](#), [cuGLUnmapBufferObjectAsync](#), [cuGLSetBufferObjectMapFlags](#), [cudaWGLGetDevice](#)

6.32.1. OpenGL Interoperability [DEPRECATED]

OpenGL Interoperability

This section describes deprecated OpenGL interoperability functionality.

enum CUGLmap_flags

Flags to map or unmap a resource

Values

CU_GL_MAP_RESOURCE_FLAGS_NONE = 0x00

CU_GL_MAP_RESOURCE_FLAGS_READ_ONLY = 0x01

CU_GL_MAP_RESOURCE_FLAGS_WRITE_DISCARD = 0x02

CUresult cuGLCtxCreate (CUcontext *pCtx, unsigned int Flags, CUdevice device)

Create a CUDA context for interoperability with OpenGL.

Parameters

pCtx

- Returned CUDA context

Flags

- Options for CUDA context creation

device

- Device on which to create the context

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_OUT_OF_MEMORY](#)

Description

Deprecated This function is deprecated as of Cuda 5.0.

This function is deprecated and should no longer be used. It is no longer necessary to associate a CUDA context with an OpenGL context in order to achieve maximum interoperability performance.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuCtxCreate](#), [cuGLInit](#), [cuGLMapBufferObject](#), [cuGLRegisterBufferObject](#), [cuGLUnmapBufferObject](#), [cuGLUnregisterBufferObject](#), [cuGLMapBufferObjectAsync](#), [cuGLUnmapBufferObjectAsync](#), [cuGLSetBufferObjectMapFlags](#), [cuWGLGetDevice](#)

CUresult cuGLInit (void)

Initializes OpenGL interoperability.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_UNKNOWN](#)

Description

Deprecated This function is deprecated as of Cuda 3.0.

Initializes OpenGL interoperability. This function is deprecated and calling it is no longer required. It may fail if the needed OpenGL driver facilities are not available.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGLMapBufferObject](#), [cuGLRegisterBufferObject](#), [cuGLUnmapBufferObject](#), [cuGLUnregisterBufferObject](#), [cuGLMapBufferObjectAsync](#), [cuGLUnmapBufferObjectAsync](#), [cuGLSetBufferObjectMapFlags](#), [cuWGLGetDevice](#)

CUresult cuGLMapBufferObject (CUdeviceptr *dptr, size_t *size, GLuint buffer)

Maps an OpenGL buffer object.

Parameters

dptr

- Returned mapped base pointer

size

- Returned size of mapping

buffer

- The name of the buffer object to map

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_MAP_FAILED](#)

Description

Deprecated This function is deprecated as of Cuda 3.0.

Maps the buffer object specified by `buffer` into the address space of the current CUDA context and returns in `*dptr` and `*size` the base pointer and size of the resulting mapping.

There must be a valid OpenGL context bound to the current thread when this function is called. This must be the same context, or a member of the same shareGroup, as the context that was bound when the buffer was registered.

All streams in the current CUDA context are synchronized with the current GL context.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphicsMapResources](#)

CUresult cuGLMapBufferObjectAsync (CUdeviceptr *dptr, size_t *size, GLuint buffer, CUstream hStream)

Maps an OpenGL buffer object.

Parameters

dptr

- Returned mapped base pointer

size

- Returned size of mapping

buffer

- The name of the buffer object to map

hStream

- Stream to synchronize

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_MAP_FAILED](#)

Description

Deprecated This function is deprecated as of Cuda 3.0.

Maps the buffer object specified by `buffer` into the address space of the current CUDA context and returns in `*dptr` and `*size` the base pointer and size of the resulting mapping.

There must be a valid OpenGL context bound to the current thread when this function is called. This must be the same context, or a member of the same `shareGroup`, as the context that was bound when the buffer was registered.

Stream `hStream` in the current CUDA context is synchronized with the current GL context.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphicsMapResources](#)

CUresult cuGLRegisterBufferObject (GLuint buffer)

Registers an OpenGL buffer object.

Parameters

buffer

- The name of the buffer object to register.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_ALREADY_MAPPED](#)

Description

[Deprecated](#) This function is deprecated as of Cuda 3.0.

Registers the buffer object specified by `buffer` for access by CUDA. This function must be called before CUDA can map the buffer object. There must be a valid OpenGL context bound to the current thread when this function is called, and the buffer name is resolved by that context.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphicsGLRegisterBuffer](#)

CUresult cuGLSetBufferObjectMapFlags (GLuint buffer, unsigned int Flags)

Set the map flags for an OpenGL buffer object.

Parameters

buffer

- Buffer object to unmap

Flags

- Map flags

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_ALREADY_MAPPED](#), [CUDA_ERROR_INVALID_CONTEXT](#),

Description

[Deprecated](#) This function is deprecated as of Cuda 3.0.

Sets the map flags for the buffer object specified by `buffer`.

Changes to `Flags` will take effect the next time `buffer` is mapped. The `Flags` argument may be any of the following:

- ▶ `CU_GL_MAP_RESOURCE_FLAGS_NONE`: Specifies no hints about how this resource will be used. It is therefore assumed that this resource will be read from and written to by CUDA kernels. This is the default value.
- ▶ `CU_GL_MAP_RESOURCE_FLAGS_READ_ONLY`: Specifies that CUDA kernels which access this resource will not write to this resource.
- ▶ `CU_GL_MAP_RESOURCE_FLAGS_WRITE_DISCARD`: Specifies that CUDA kernels which access this resource will not read from this resource and will write over the entire contents of the resource, so none of the data previously stored in the resource will be preserved.

If `buffer` has not been registered for use with CUDA, then [CUDA_ERROR_INVALID_HANDLE](#) is returned. If `buffer` is presently mapped for access by CUDA, then [CUDA_ERROR_ALREADY_MAPPED](#) is returned.

There must be a valid OpenGL context bound to the current thread when this function is called. This must be the same context, or a member of the same shareGroup, as the context that was bound when the buffer was registered.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphicsResourceSetMapFlags](#)

CUresult cuGLUnmapBufferObject (GLuint buffer)

Unmaps an OpenGL buffer object.

Parameters

buffer

- Buffer object to unmap

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

[Deprecated](#) This function is deprecated as of Cuda 3.0.

Unmaps the buffer object specified by `buffer` for access by CUDA.

There must be a valid OpenGL context bound to the current thread when this function is called. This must be the same context, or a member of the same `shareGroup`, as the context that was bound when the buffer was registered.

All streams in the current CUDA context are synchronized with the current GL context.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphicsUnmapResources](#)

CUresult cuGLUnmapBufferObjectAsync (GLuint buffer, CUstream hStream)

Unmaps an OpenGL buffer object.

Parameters

buffer

- Name of the buffer object to unmap

hStream

- Stream to synchronize

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

[Deprecated](#) This function is deprecated as of Cuda 3.0.

Unmaps the buffer object specified by `buffer` for access by CUDA.

There must be a valid OpenGL context bound to the current thread when this function is called. This must be the same context, or a member of the same shareGroup, as the context that was bound when the buffer was registered.

Stream `hStream` in the current CUDA context is synchronized with the current GL context.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphicsUnmapResources](#)

CUresult cuGLUnregisterBufferObject (GLuint buffer)

Unregister an OpenGL buffer object.

Parameters

buffer

- Name of the buffer object to unregister

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Deprecated This function is deprecated as of Cuda 3.0.

Unregisters the buffer object specified by `buffer`. This releases any resources associated with the registered buffer. After this call, the buffer may no longer be mapped for access by CUDA.

There must be a valid OpenGL context bound to the current thread when this function is called. This must be the same context, or a member of the same shareGroup, as the context that was bound when the buffer was registered.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuGraphicsUnregisterResource](#)

6.33. VDPAU Interoperability

This section describes the VDPAU interoperability functions of the low-level CUDA driver application programming interface.

CUresult cuGraphicsVDPAURegisterOutputSurface
(CUgraphicsResource *pCudaResource,
VdpOutputSurface vdpSurface, unsigned int flags)

Registers a VDPAU VdpOutputSurface object.

Parameters

pCudaResource

- Pointer to the returned object handle

vdpSurface

- The VdpOutputSurface to be registered

flags

- Map flags

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_ALREADY_MAPPED](#), [CUDA_ERROR_INVALID_CONTEXT](#),

Description

Registers the VdpOutputSurface specified by `vdpSurface` for access by CUDA. A handle to the registered object is returned as `pCudaResource`. The surface's intended usage is specified using `flags`, as follows:

- ▶ `CU_GRAPHICS_MAP_RESOURCE_FLAGS_NONE`: Specifies no hints about how this resource will be used. It is therefore assumed that this resource will be read from and written to by CUDA. This is the default value.
- ▶ `CU_GRAPHICS_MAP_RESOURCE_FLAGS_READ_ONLY`: Specifies that CUDA will not write to this resource.
- ▶ `CU_GRAPHICS_MAP_RESOURCE_FLAGS_WRITE_DISCARD`: Specifies that CUDA will not read from this resource and will write over the entire contents of the resource, so none of the data previously stored in the resource will be preserved.

The VdpOutputSurface is presented as an array of subresources that may be accessed using pointers returned by [cuGraphicsSubResourceGetMappedArray](#). The exact number of valid `arrayIndex` values depends on the VDPAU surface format. The mapping is shown in the table below. `mipLevel` must be 0.

**Note:**

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuCtxCreate](#), [cuVDPAUCtxCreate](#), [cuGraphicsVDPAURegisterVideoSurface](#),
[cuGraphicsUnregisterResource](#), [cuGraphicsResourceSetMapFlags](#),
[cuGraphicsMapResources](#), [cuGraphicsUnmapResources](#),
[cuGraphicsSubResourceGetMappedArray](#), [cuVDPAUGetDevice](#),
[cudaGraphicsVDPAURegisterOutputSurface](#)

CUresult cuGraphicsVDPAURegisterVideoSurface (CUgraphicsResource *pCudaResource, VdpVideoSurface vdpSurface, unsigned int flags)

Registers a VDPAU VdpVideoSurface object.

Parameters**pCudaResource**

- Pointer to the returned object handle

vdpSurface

- The VdpVideoSurface to be registered

flags

- Map flags

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_ALREADY_MAPPED](#),
[CUDA_ERROR_INVALID_CONTEXT](#),


Description

Registers the VdpVideoSurface specified by `vdpSurface` for access by CUDA. A handle to the registered object is returned as `pCudaResource`. The surface's intended usage is specified using `flags`, as follows:

- ▶ `CU_GRAPHICS_MAP_RESOURCE_FLAGS_NONE`: Specifies no hints about how this resource will be used. It is therefore assumed that this resource will be read from and written to by CUDA. This is the default value.
- ▶ `CU_GRAPHICS_MAP_RESOURCE_FLAGS_READ_ONLY`: Specifies that CUDA will not write to this resource.

- ▶ `CU_GRAPHICS_MAP_RESOURCE_FLAGS_WRITE_DISCARD`: Specifies that CUDA will not read from this resource and will write over the entire contents of the resource, so none of the data previously stored in the resource will be preserved.

The `VdpVideoSurface` is presented as an array of subresources that may be accessed using pointers returned by [cuGraphicsSubResourceGetMappedArray](#). The exact number of valid `arrayIndex` values depends on the VDPAU surface format. The mapping is shown in the table below. `mipLevel` must be 0.

 **Note:**
Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuCtxCreate](#), [cuVDPAUCtxCreate](#), [cuGraphicsVDPAURegisterOutputSurface](#),
[cuGraphicsUnregisterResource](#), [cuGraphicsResourceSetMapFlags](#),
[cuGraphicsMapResources](#), [cuGraphicsUnmapResources](#),
[cuGraphicsSubResourceGetMappedArray](#), [cuVDPAUGetDevice](#),
[cudaGraphicsVDPAURegisterVideoSurface](#)

CUresult cuVDPAUCtxCreate (CUcontext *pCtx, unsigned int flags, CUdevice device, VdpDevice vdpDevice, VdpGetProcAddress *vdpGetProcAddress)

Create a CUDA context for interoperability with VDPAU.

Parameters

pCtx

- Returned CUDA context

flags

- Options for CUDA context creation

device

- Device on which to create the context

vdpDevice

- The `VdpDevice` to interop with

vdpGetProcAddress

- VDPAU's `VdpGetProcAddress` function pointer

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_OUT_OF_MEMORY](#)

Description

Creates a new CUDA context, initializes VDPAU interoperability, and associates the CUDA context with the calling thread. It must be called before performing any other VDPAU interoperability operations. It may fail if the needed VDPAU driver facilities are not available. For usage of the `flags` parameter, see [cuCtxCreate\(\)](#).



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuCtxCreate](#), [cuGraphicsVDPAURegisterVideoSurface](#),
[cuGraphicsVDPAURegisterOutputSurface](#), [cuGraphicsUnregisterResource](#),
[cuGraphicsResourceSetMapFlags](#), [cuGraphicsMapResources](#), [cuGraphicsUnmapResources](#),
[cuGraphicsSubResourceGetMappedArray](#), [cuVDPAUGetDevice](#)

CUresult cuVDPAUGetDevice (CUdevice *pDevice, VdpDevice vdpDevice, VdpGetProcAddress *vdpGetProcAddress)

Gets the CUDA device associated with a VDPAU device.

Parameters

pDevice

- Device associated with vdpDevice

vdpDevice

- A VdpDevice handle

vdpGetProcAddress

- VDPAU's VdpGetProcAddress function pointer

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#)

Description

Returns in `*pDevice` the CUDA device associated with a `vdpDevice`, if applicable.



Note:

Note that this function may also return error codes from previous, asynchronous launches.

See also:

[cuCtxCreate](#), [cuVDPACtxCreate](#), [cuGraphicsVDPAURegisterVideoSurface](#), [cuGraphicsVDPAURegisterOutputSurface](#), [cuGraphicsUnregisterResource](#), [cuGraphicsResourceSetMapFlags](#), [cuGraphicsMapResources](#), [cuGraphicsUnmapResources](#), [cuGraphicsSubResourceGetMappedArray](#), [cudaVDPAUGetDevice](#)

6.34. EGL Interoperability

This section describes the EGL interoperability functions of the low-level CUDA driver application programming interface.

CUresult cuEGLStreamConsumerAcquireFrame (CUeglStreamConnection *conn, CUgraphicsResource *pCudaResource, CUstream *pStream, unsigned int timeout)

Acquire an image frame from the EGLStream with CUDA as a consumer.

Parameters

conn

- Connection on which to acquire

pCudaResource

- CUDA resource on which the stream frame will be mapped for use.

pStream

- CUDA stream for synchronization and any data migrations implied by [CUeglResourceLocationFlags](#).

timeout

- Desired timeout in usec for a new frame to be acquired. If set as [CUDA_EGL_INFINITE_TIMEOUT](#), acquire waits infinitely. After timeout occurs CUDA consumer tries to acquire an old frame if available and `EGL_SUPPORT_REUSE_NV` flag is set.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_LAUNCH_TIMEOUT](#),

Description

Acquire an image frame from EGLStreamKHR. This API can also acquire an old frame presented by the producer unless explicitly disabled by setting EGL_SUPPORT_REUSE_NV flag to EGL_FALSE during stream initialization. By default, EGLStream is created with this flag set to EGL_TRUE. [cuGraphicsResourceGetMappedEglFrame](#) can be called on `pCudaResource` to get CUeglFrame.

See also:

[cuEGLStreamConsumerConnect](#), [cuEGLStreamConsumerDisconnect](#),
[cuEGLStreamConsumerAcquireFrame](#), [cuEGLStreamConsumerReleaseFrame](#),
[cudaEGLStreamConsumerAcquireFrame](#)

CUresult cuEGLStreamConsumerConnect (CUeglStreamConnection *conn, EGLStreamKHR stream)

Connect CUDA to EGLStream as a consumer.

Parameters

conn

- Pointer to the returned connection handle

stream

- EGLStreamKHR handle

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_INVALID_CONTEXT](#),

Description

Connect CUDA as a consumer to EGLStreamKHR specified by `stream`.

The EGLStreamKHR is an EGL object that transfers a sequence of image frames from one API to another.

See also:

[cuEGLStreamConsumerConnect](#), [cuEGLStreamConsumerDisconnect](#),
[cuEGLStreamConsumerAcquireFrame](#), [cuEGLStreamConsumerReleaseFrame](#),
[cudaEGLStreamConsumerConnect](#)

CUresult cuEGLStreamConsumerConnectWithFlags (CUeglStreamConnection *conn, EGLStreamKHR stream, unsigned int flags)

Connect CUDA to EGLStream as a consumer with given flags.

Parameters

conn

- Pointer to the returned connection handle

stream

- EGLStreamKHR handle

flags

- Flags denote intended location - system or video.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_INVALID_CONTEXT](#),

Description

Connect CUDA as a consumer to EGLStreamKHR specified by `stream` with specified `flags` defined by `CUeglResourceLocationFlags`.

The flags specify whether the consumer wants to access frames from system memory or video memory. Default is [CU_EGL_RESOURCE_LOCATION_VIDMEM](#).

See also:

[cuEGLStreamConsumerConnect](#), [cuEGLStreamConsumerDisconnect](#),
[cuEGLStreamConsumerAcquireFrame](#), [cuEGLStreamConsumerReleaseFrame](#),
[cudaEGLStreamConsumerConnectWithFlags](#)

CUresult cuEGLStreamConsumerDisconnect (CUeglStreamConnection *conn)

Disconnect CUDA as a consumer to EGLStream .

Parameters

conn

- Connection to disconnect.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_INVALID_CONTEXT](#),

Description

Disconnect CUDA as a consumer to EGLStreamKHR.

See also:

[cuEGLStreamConsumerConnect](#), [cuEGLStreamConsumerDisconnect](#),
[cuEGLStreamConsumerAcquireFrame](#), [cuEGLStreamConsumerReleaseFrame](#),
[cudaEGLStreamConsumerDisconnect](#)

CUresult cuEGLStreamConsumerReleaseFrame (CUeglStreamConnection *conn, CUgraphicsResource pCudaResource, CUstream *pStream)

Releases the last frame acquired from the EGLStream.

Parameters

conn

- Connection on which to release

pCudaResource

- CUDA resource whose corresponding frame is to be released

pStream

- CUDA stream on which release will be done.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_HANDLE](#),

Description

Release the acquired image frame specified by pCudaResource to EGLStreamKHR. If EGL_SUPPORT_REUSE_NV flag is set to EGL_TRUE, at the time of EGL creation this API doesn't release the last frame acquired on the EGLStream. By default, EGLStream is created with this flag set to EGL_TRUE.

See also:

[cuEGLStreamConsumerConnect](#), [cuEGLStreamConsumerDisconnect](#),
[cuEGLStreamConsumerAcquireFrame](#), [cuEGLStreamConsumerReleaseFrame](#),
[cudaEGLStreamConsumerReleaseFrame](#)

CUresult cuEGLStreamProducerConnect (CUeglStreamConnection *conn, EGLStreamKHR stream, EGLint width, EGLint height)

Connect CUDA to EGLStream as a producer.

Parameters

conn

- Pointer to the returned connection handle

stream

- EGLStreamKHR handle

width

- width of the image to be submitted to the stream

height

- height of the image to be submitted to the stream

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_INVALID_CONTEXT](#),

Description

Connect CUDA as a producer to EGLStreamKHR specified by `stream`.

The EGLStreamKHR is an EGL object that transfers a sequence of image frames from one API to another.

See also:

[cuEGLStreamProducerConnect](#), [cuEGLStreamProducerDisconnect](#),
[cuEGLStreamProducerPresentFrame](#), [cudaEGLStreamProducerConnect](#)

CUresult cuEGLStreamProducerDisconnect (CUeglStreamConnection *conn)

Disconnect CUDA as a producer to EGLStream .

Parameters

conn

- Connection to disconnect.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_INVALID_CONTEXT](#),

Description

Disconnect CUDA as a producer to EGLStreamKHR.

See also:

[cuEGLStreamProducerConnect](#), [cuEGLStreamProducerDisconnect](#),
[cuEGLStreamProducerPresentFrame](#), [cudaEGLStreamProducerDisconnect](#)

CUresult cuEGLStreamProducerPresentFrame (CUeglStreamConnection *conn, CUeglFrame eglframe, CUstream *pStream)

Present a CUDA eglFrame to the EGLStream with CUDA as a producer.

Parameters

conn

- Connection on which to present the CUDA array

eglframe

- CUDA Eglstream Proucer Frame handle to be sent to the consumer over EglStream.

pStream

- CUDA stream on which to present the frame.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_HANDLE](#),

Description

When a frame is presented by the producer, it gets associated with the EGLStream and thus it is illegal to free the frame before the producer is disconnected. If a frame is freed and reused it may lead to undefined behavior.

If producer and consumer are on different GPUs (iGPU and dGPU) then frametype [CU_EGL_FRAME_TYPE_ARRAY](#) is not supported. [CU_EGL_FRAME_TYPE_PITCH](#) can be used for such cross-device applications.

The CUeglFrame is defined as:

```
↑ typedef struct CUeglFrame_st {
    union {
        CUarray pArray[MAX_PLANES];
        void* pPitch[MAX_PLANES];
    } frame;
    unsigned int width;
    unsigned int height;
    unsigned int depth;
    unsigned int pitch;
    unsigned int planeCount;
    unsigned int numChannels;
};
```

```

    CUeglFrameType frameType;
    CUeglColorFormat eglColorFormat;
    CUarray_format cuFormat;
} CUeglFrame;

```

For CUeglFrame of type `CU_EGL_FRAME_TYPE_PITCH`, the application may present sub-region of a memory allocation. In that case, the pitched pointer will specify the start address of the sub-region in the allocation and corresponding CUeglFrame fields will specify the dimensions of the sub-region.

See also:

[cuEGLStreamProducerConnect](#), [cuEGLStreamProducerDisconnect](#),
[cuEGLStreamProducerReturnFrame](#), [cudaEGLStreamProducerPresentFrame](#)

CUresult cuEGLStreamProducerReturnFrame (CUeglStreamConnection *conn, CUeglFrame *eglframe, CUstream *pStream)

Return the CUDA eglFrame to the EGLStream released by the consumer.

Parameters

conn

- Connection on which to return

eglframe

- CUDA Eglstream Proucer Frame handle returned from the consumer over EglStream.

pStream

- CUDA stream on which to return the frame.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_LAUNCH_TIMEOUT](#)

Description

This API can potentially return `CUDA_ERROR_LAUNCH_TIMEOUT` if the consumer has not returned a frame to EGL stream. If timeout is returned the application can retry.

See also:

[cuEGLStreamProducerConnect](#), [cuEGLStreamProducerDisconnect](#),
[cuEGLStreamProducerPresentFrame](#), [cudaEGLStreamProducerReturnFrame](#)

CUresult cuEventCreateFromEGLSync (CUevent *phEvent, EGLSyncKHR eglSync, unsigned int flags)

Creates an event from EGLSync object.

Parameters

phEvent

- Returns newly created event

eglSync

- Opaque handle to EGLSync object

flags

- Event creation flags

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#), [CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#), [CUDA_ERROR_OUT_OF_MEMORY](#)

Description

Creates an event *phEvent from an EGLSyncKHR eglSync with the flags specified via flags. Valid flags include:

- ▶ [CU_EVENT_DEFAULT](#): Default event creation flag.
- ▶ [CU_EVENT_BLOCKING_SYNC](#): Specifies that the created event should use blocking synchronization. A CPU thread that uses [cuEventSynchronize\(\)](#) to wait on an event created with this flag will block until the event has actually been completed.

Once the eglSync gets destroyed, [cuEventDestroy](#) is the only API that can be invoked on the event.

[cuEventRecord](#) and TimingData are not supported for events created from EGLSync.

The EGLSyncKHR is an opaque handle to an EGL sync object. typedef void* EGLSyncKHR

See also:

[cuEventQuery](#), [cuEventSynchronize](#), [cuEventDestroy](#)

CUresult cuGraphicsEGLRegisterImage (CUgraphicsResource *pCudaResource, EGLImageKHR image, unsigned int flags)

Registers an EGL image.

Parameters

pCudaResource

- Pointer to the returned object handle

image

- An EGLImageKHR image which can be used to create target resource.

flags

- Map flags

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_ALREADY_MAPPED](#),
[CUDA_ERROR_INVALID_CONTEXT](#),

Description

Registers the EGLImageKHR specified by `image` for access by CUDA. A handle to the registered object is returned as `pCudaResource`. Additional Mapping/Unmapping is not required for the registered resource and [cuGraphicsResourceGetMappedEglFrame](#) can be directly called on the `pCudaResource`.

The application will be responsible for synchronizing access to shared objects. The application must ensure that any pending operation which access the objects have completed before passing control to CUDA. This may be accomplished by issuing and waiting for `glFinish` command on all GLcontexts (for OpenGL and likewise for other APIs). The application will be also responsible for ensuring that any pending operation on the registered CUDA resource has completed prior to executing subsequent commands in other APIs accessing the same memory objects. This can be accomplished by calling `cuCtxSynchronize` or `cuEventSynchronize` (preferably).

The surface's intended usage is specified using `flags`, as follows:

- ▶ `CUDA_GRAPHICS_MAP_RESOURCE_FLAGS_NONE`: Specifies no hints about how this resource will be used. It is therefore assumed that this resource will be read from and written to by CUDA. This is the default value.
- ▶ `CUDA_GRAPHICS_MAP_RESOURCE_FLAGS_READ_ONLY`: Specifies that CUDA will not write to this resource.
- ▶ `CUDA_GRAPHICS_MAP_RESOURCE_FLAGS_WRITE_DISCARD`: Specifies that CUDA will not read from this resource and will write over the entire contents of the resource, so none of

the data previously stored in the resource will be preserved. These flags currently have no effect and are reserved for future use.

The EGLImageKHR is an object which can be used to create EGLImage target resource. It is defined as a void pointer. `typedef void* EGLImageKHR`

See also:

[cuGraphicsEGLRegisterImage](#), [cuGraphicsUnregisterResource](#),
[cuGraphicsResourceSetMapFlags](#), [cuGraphicsMapResources](#), [cuGraphicsUnmapResources](#),
[cudaGraphicsEGLRegisterImage](#)

CUresult cuGraphicsResourceGetMappedEglFrame (CUeglFrame *eglFrame, CUgraphicsResource resource, unsigned int index, unsigned int mipLevel)

Get an eglFrame through which to access a registered EGL graphics resource.

Parameters

eglFrame

- Returned eglFrame.

resource

- Registered resource to access.

index

- Index for cubemap surfaces.

mipLevel

- Mipmap level for the subresource to access.

Returns

[CUDA_SUCCESS](#), [CUDA_ERROR_DEINITIALIZED](#), [CUDA_ERROR_NOT_INITIALIZED](#),
[CUDA_ERROR_INVALID_CONTEXT](#), [CUDA_ERROR_INVALID_VALUE](#),
[CUDA_ERROR_INVALID_HANDLE](#), [CUDA_ERROR_NOT_MAPPED](#)

Description

Returns in *eglFrame an eglFrame pointer through which the registered graphics resource resource may be accessed. This API can only be called for registered EGL graphics resources.

The CUeglFrame is defined as:

```
↑ typedef struct CUeglFrame_st {
    union {
        CUarray pArray[MAX_PLANES];
        void* pPitch[MAX_PLANES];
    } frame;
    unsigned int width;
    unsigned int height;
```

```
    unsigned int depth;  
    unsigned int pitch;  
    unsigned int planeCount;  
    unsigned int numChannels;  
    CUeglFrameType frameType;  
    CUeglColorFormat eglColorFormat;  
    CUarray\_format cuFormat;  
} CUeglFrame;
```

If resource is not registered then [CUDA_ERROR_NOT_MAPPED](#) is returned. *

See also:

[cuGraphicsMapResources](#), [cuGraphicsSubResourceGetMappedArray](#),
[cuGraphicsResourceGetMappedPointer](#), [cudaGraphicsResourceGetMappedEglFrame](#)

Chapter 7. Data Structures

Here are the data structures with brief descriptions:

[**CUaccessPolicyWindow_v1**](#)

[**CUarrayMapInfo_v1**](#)

[**CUDA_ARRAY3D_DESCRIPTOR_v2**](#)

[**CUDA_ARRAY_DESCRIPTOR_v2**](#)

[**CUDA_ARRAY_SPARSE_PROPERTIES_v1**](#)

[**CUDA_EXT_SEM_SIGNAL_NODE_PARAMS_v1**](#)

[**CUDA_EXT_SEM_WAIT_NODE_PARAMS_v1**](#)

[**CUDA_EXTERNAL_MEMORY_BUFFER_DESC_v1**](#)

[**CUDA_EXTERNAL_MEMORY_HANDLE_DESC_v1**](#)

[**CUDA_EXTERNAL_MEMORY_MIPMAPPED_ARRAY_DESC_v1**](#)

[**CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC_v1**](#)

[**CUDA_EXTERNAL_SEMAPHORE_SIGNAL_PARAMS_v1**](#)

[**CUDA_EXTERNAL_SEMAPHORE_WAIT_PARAMS_v1**](#)

[**CUDA_HOST_NODE_PARAMS_v1**](#)

[**CUDA_KERNEL_NODE_PARAMS_v1**](#)

[**CUDA_LAUNCH_PARAMS_v1**](#)

[**CUDA_MEMCPY2D_v2**](#)

[**CUDA_MEMCPY3D_PEER_v1**](#)

[**CUDA_MEMCPY3D_v2**](#)

[**CUDA_MEMSET_NODE_PARAMS_v1**](#)

[**CUDA_POINTER_ATTRIBUTE_P2P_TOKENS_v1**](#)

[**CUDA_RESOURCE_DESC_v1**](#)

[**CUDA_RESOURCE_VIEW_DESC_v1**](#)

[**CUDA_TEXTURE_DESC_v1**](#)

[**CUdevprop_v1**](#)

[**CUeglFrame_v1**](#)

[**CUipcEventHandle_v1**](#)

[**CUipcMemHandle_v1**](#)

[**CUkernelNodeAttrValue_v1**](#)

[**CUmемAccessDesc_v1**](#)

[**CUmемAllocationProp_v1**](#)

[**CUmемLocation_v1**](#)

[CUmemPoolProps_v1](#)[CUmemPoolPtrExportData_v1](#)[CUstreamAttrValue_v1](#)[CUstreamBatchMemOpParams_v1](#)

7.1. CUaccessPolicyWindow_v1 Struct Reference

Specifies an access policy for a window, a contiguous extent of memory beginning at `base_ptr` and ending at `base_ptr + num_bytes`. `num_bytes` is limited by `CU_DEVICE_ATTRIBUTE_MAX_ACCESS_POLICY_WINDOW_SIZE`. Partition into many segments and assign segments such that: `sum of "hit segments" / window == approx. ratio`. `sum of "miss segments" / window == approx 1-ratio`. Segments and ratio specifications are fitted to the capabilities of the architecture. Accesses in a hit segment apply the `hitProp` access policy. Accesses in a miss segment apply the `missProp` access policy.

`void *CUaccessPolicyWindow_v1::base_ptr`

Starting address of the access policy window. CUDA driver may align it.

`CUaccessProperty`

`CUaccessPolicyWindow_v1::hitProp`

[CUaccessProperty](#) set for hit.

`float CUaccessPolicyWindow_v1::hitRatio`

`hitRatio` specifies percentage of lines assigned `hitProp`, rest are assigned `missProp`.

`CUaccessProperty`

`CUaccessPolicyWindow_v1::missProp`

[CUaccessProperty](#) set for miss. Must be either `NORMAL` or `STREAMING`

`size_t CUaccessPolicyWindow_v1::num_bytes`

Size in bytes of the window policy. CUDA driver may restrict the maximum size and alignment.

7.2. CUarrayMapInfo_v1 Struct Reference

Specifies the CUDA array or CUDA mipmapped array memory mapping information

unsigned int CUarrayMapInfo_v1::deviceBitMask

Device ordinal bit mask

unsigned int CUarrayMapInfo_v1::extentDepth

Depth in elements

unsigned int CUarrayMapInfo_v1::extentHeight

Height in elements

unsigned int CUarrayMapInfo_v1::extentWidth

Width in elements

unsigned int CUarrayMapInfo_v1::flags

flags for future use, must be zero now.

unsigned int CUarrayMapInfo_v1::layer

For CUDA layered arrays must be a valid layer index. Otherwise, must be zero

unsigned int CUarrayMapInfo_v1::level

For CUDA mipmapped arrays must a valid mipmap level. For CUDA arrays must be zero

CUmemHandleType

CUarrayMapInfo_v1::memHandleType

Memory handle type

CUmemOperationType

CUarrayMapInfo_v1::memOperationType

Memory operation type

`unsigned long long CUarrayMapInfo_v1::offset`

Offset within mip tail

Offset within the memory

`unsigned int CUarrayMapInfo_v1::offsetX`

Starting X offset in elements

`unsigned int CUarrayMapInfo_v1::offsetY`

Starting Y offset in elements

`unsigned int CUarrayMapInfo_v1::offsetZ`

Starting Z offset in elements

`unsigned int CUarrayMapInfo_v1::reserved`

Reserved for future use, must be zero now.

`CUresourcetype CUarrayMapInfo_v1::resourceType`

Resource type

`unsigned long long CUarrayMapInfo_v1::size`

Extent in bytes

`CUarraySparseSubresourceType`

`CUarrayMapInfo_v1::subresourceType`

Sparse subresource type

7.3. `CUDA_ARRAY3D_DESCRIPTOR_v2` Struct Reference

3D array descriptor

`size_t CUDA_ARRAY3D_DESCRIPTOR_v2::Depth`

Depth of 3D array

`unsigned int`

`CUDA_ARRAY3D_DESCRIPTOR_v2::Flags`

Flags

`CUarray_format`

`CUDA_ARRAY3D_DESCRIPTOR_v2::Format`

Array format

`size_t CUDA_ARRAY3D_DESCRIPTOR_v2::Height`

Height of 3D array

`unsigned int`

`CUDA_ARRAY3D_DESCRIPTOR_v2::NumChannels`

Channels per array element

`size_t CUDA_ARRAY3D_DESCRIPTOR_v2::Width`

Width of 3D array

7.4. `CUDA_ARRAY_DESCRIPTOR_v2` Struct Reference

Array descriptor

`CUarray_format`

`CUDA_ARRAY_DESCRIPTOR_v2::Format`

Array format

`size_t CUDA_ARRAY_DESCRIPTOR_v2::Height`

Height of array

`unsigned int`

`CUDA_ARRAY_DESCRIPTOR_v2::NumChannels`

Channels per array element

`size_t CUDA_ARRAY_DESCRIPTOR_v2::Width`

Width of array

7.5. `CUDA_ARRAY_SPARSE_PROPERTIES_v1` Struct Reference

CUDA array sparse properties

`unsigned int`

`CUDA_ARRAY_SPARSE_PROPERTIES_v1::depth`

Depth of sparse tile in elements

`unsigned int`

`CUDA_ARRAY_SPARSE_PROPERTIES_v1::flags`

Flags will either be zero or `CUDA_ARRAY_SPARSE_PROPERTIES_SINGLE_MIPTAIL`

`unsigned int`

`CUDA_ARRAY_SPARSE_PROPERTIES_v1::height`

Height of sparse tile in elements

`unsigned int`

`CUDA_ARRAY_SPARSE_PROPERTIES_v1::mipTailFirstLevel`

First mip level at which the mip tail begins.

unsigned long long
 CUDA_ARRAY_SPARSE_PROPERTIES_v1::miptailSize

Total size of the mip tail.

unsigned int
 CUDA_ARRAY_SPARSE_PROPERTIES_v1::width

Width of sparse tile in elements

7.6. CUDA_EXT_SEM_SIGNAL_NODE_PARAMS_v1 Struct Reference

Semaphore signal node parameters

CUexternalSemaphore
 *CUDA_EXT_SEM_SIGNAL_NODE_PARAMS_v1::extSemArray

Array of external semaphore handles.

unsigned int
 CUDA_EXT_SEM_SIGNAL_NODE_PARAMS_v1::numExtSems

Number of handles and parameters supplied in extSemArray and paramsArray.

const
 CUDA_EXTERNAL_SEMAPHORE_SIGNAL_PARAMS
 *CUDA_EXT_SEM_SIGNAL_NODE_PARAMS_v1::paramsArray

Array of external semaphore signal parameters.

7.7. CUDA_EXT_SEM_WAIT_NODE_PARAMS_v1 Struct Reference

Semaphore wait node parameters

`CUexternalSemaphore`

`*CUDA_EXT_SEM_WAIT_NODE_PARAMS_v1::extSemArray`

Array of external semaphore handles.

`unsigned int`

`CUDA_EXT_SEM_WAIT_NODE_PARAMS_v1::numExtSems`

Number of handles and parameters supplied in `extSemArray` and `paramsArray`.

`const`

`CUDA_EXTERNAL_SEMAPHORE_WAIT_PARAMS`

`*CUDA_EXT_SEM_WAIT_NODE_PARAMS_v1::paramsArray`

Array of external semaphore wait parameters.

7.8. `CUDA_EXTERNAL_MEMORY_BUFFER_DESC` Struct Reference

External memory buffer descriptor

`unsigned int`

`CUDA_EXTERNAL_MEMORY_BUFFER_DESC_v1::flags`

Flags reserved for future use. Must be zero.

`unsigned long long`

`CUDA_EXTERNAL_MEMORY_BUFFER_DESC_v1::offset`

Offset into the memory object where the buffer's base is

`unsigned long long`

`CUDA_EXTERNAL_MEMORY_BUFFER_DESC_v1::size`

Size of the buffer

7.9. CUDA_EXTERNAL_MEMORY_HANDLE_DESC Struct Reference

External memory handle descriptor

int

CUDA_EXTERNAL_MEMORY_HANDLE_DESC_v1::fd

File descriptor referencing the memory object. Valid when type is [CU_EXTERNAL_MEMORY_HANDLE_TYPE_OPAQUE_FD](#)

unsigned int

CUDA_EXTERNAL_MEMORY_HANDLE_DESC_v1::flags

Flags must either be zero or [CUDA_EXTERNAL_MEMORY_DEDICATED](#)

void

***CUDA_EXTERNAL_MEMORY_HANDLE_DESC_v1::handle**

Valid NT handle. Must be NULL if 'name' is non-NULL

const void

***CUDA_EXTERNAL_MEMORY_HANDLE_DESC_v1::name**

Name of a valid memory object. Must be NULL if 'handle' is non-NULL.

const void

***CUDA_EXTERNAL_MEMORY_HANDLE_DESC_v1::nvSciBufObj**

A handle representing an NvSciBuf Object. Valid when type is [CU_EXTERNAL_MEMORY_HANDLE_TYPE_NVSCIBUF](#)

unsigned long long

CUDA_EXTERNAL_MEMORY_HANDLE_DESC_v1::size

Size of the memory allocation

`CUexternalMemoryHandleType`
`CUDA_EXTERNAL_MEMORY_HANDLE_DESC_v1::type`

Type of the handle

`CUDA_EXTERNAL_MEMORY_HANDLE_DESC_v1::@11::@12`
`CUDA_EXTERNAL_MEMORY_HANDLE_DESC_v1::win32`

Win32 handle referencing the semaphore object. Valid when type is one of the following:

- ▶ [`CU_EXTERNAL_MEMORY_HANDLE_TYPE_OPAQUE_WIN32`](#)
 - ▶ [`CU_EXTERNAL_MEMORY_HANDLE_TYPE_OPAQUE_WIN32_KMT`](#)
 - ▶ [`CU_EXTERNAL_MEMORY_HANDLE_TYPE_D3D12_HEAP`](#)
 - ▶ [`CU_EXTERNAL_MEMORY_HANDLE_TYPE_D3D12_RESOURCE`](#)
 - ▶ [`CU_EXTERNAL_MEMORY_HANDLE_TYPE_D3D11_RESOURCE`](#)
 - ▶ [`CU_EXTERNAL_MEMORY_HANDLE_TYPE_D3D11_RESOURCE_KMT`](#)
- Exactly one of 'handle' and 'name' must be non-NULL. If type is one of the following: [`CU_EXTERNAL_MEMORY_HANDLE_TYPE_OPAQUE_WIN32_KMT`](#) [`CU_EXTERNAL_MEMORY_HANDLE_TYPE_D3D11_RESOURCE_KMT`](#) then 'name' must be NULL.

7.10. `CUDA_EXTERNAL_MEMORY_MIPMAPPED_ARRAY_DESCRIPTOR` Struct Reference

External memory mipmap descriptor

`struct CUDA_ARRAY3D_DESCRIPTOR`
`CUDA_EXTERNAL_MEMORY_MIPMAPPED_ARRAY_DESC_v1::array_desc`

Format, dimension and type of base level of the mipmap chain

`unsigned int`
`CUDA_EXTERNAL_MEMORY_MIPMAPPED_ARRAY_DESC_v1::num_levels`

Total number of levels in the mipmap chain

unsigned long long

CUDA_EXTERNAL_MEMORY_MIPMAPPED_ARRAY_DESC_v1::c

Offset into the memory object where the base level of the mipmap chain is.

7.11. CUDA_EXTERNAL_SEMAPHORE_HANDLE_D Struct Reference

External semaphore handle descriptor

int

CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC_v1::fd

File descriptor referencing the semaphore object. Valid when type is one of the following:

- ▶ [CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_OPAQUE_FD](#)
- ▶ [CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_TIMELINE_SEMAPHORE_FD](#)

unsigned int

CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC_v1::flags

Flags reserved for the future. Must be zero.

void

*CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC_v1::handle

Valid NT handle. Must be NULL if 'name' is non-NULL

const void

*CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC_v1::name

Name of a valid synchronization primitive. Must be NULL if 'handle' is non-NULL.

const void

*CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC_v1::nvSciSy

Valid NvSciSyncObj. Must be non NULL

CUexternalSemaphoreHandleType

CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC_v1::type

Type of the handle

CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC_v1::@13::@14

CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC_v1::win32

Win32 handle referencing the semaphore object. Valid when type is one of the following:

- ▶ [CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_OPAQUE_WIN32](#)
- ▶ [CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_OPAQUE_WIN32_KMT](#)
- ▶ [CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_D3D12_FENCE](#)
- ▶ [CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_D3D11_FENCE](#)
- ▶ [CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_D3D11_KEYED_MUTEX](#)
- ▶ [CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_TIMELINE_SEMAPHORE_WIN32](#) Exactly one of 'handle' and 'name' must be non-NULL. If type is one of the following:
 - ▶ [CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_OPAQUE_WIN32_KMT](#)
 - ▶ [CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_D3D11_KEYED_MUTEX_KMT](#) then 'name' must be NULL.

7.12. CUDA_EXTERNAL_SEMAPHORE_SIGNAL_PARAMS

Struct Reference

External semaphore signal parameters

void

*[CUDA_EXTERNAL_SEMAPHORE_SIGNAL_PARAMS_v1::fence](#)

Pointer to NvSciSyncFence. Valid if [CUexternalSemaphoreHandleType](#) is of type [CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_NVSCISYNC](#).

CUDA_EXTERNAL_SEMAPHORE_SIGNAL_PARAMS_v1::@15::@16

CUDA_EXTERNAL_SEMAPHORE_SIGNAL_PARAMS_v1::fence

Parameters for fence objects

unsigned int

`CUDA_EXTERNAL_SEMAPHORE_SIGNAL_PARAMS_v1::flags`

Only when `CUDA_EXTERNAL_SEMAPHORE_SIGNAL_PARAMS` is used to signal a `CUexternalSemaphore` of type `CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_NVSCISYNC`, the valid flag is `CUDA_EXTERNAL_SEMAPHORE_SIGNAL_SKIP_NVSCIBUF_MEMSYNC` which indicates that while signaling the `CUexternalSemaphore`, no memory synchronization operations should be performed for any external memory object imported as `CU_EXTERNAL_MEMORY_HANDLE_TYPE_NVSCIBUF`. For all other types of `CUexternalSemaphore`, flags must be zero.

unsigned long long

`CUDA_EXTERNAL_SEMAPHORE_SIGNAL_PARAMS_v1::key`

Value of key to release the mutex with

`CUDA_EXTERNAL_SEMAPHORE_SIGNAL_PARAMS_v1::@15::@`
`CUDA_EXTERNAL_SEMAPHORE_SIGNAL_PARAMS_v1::keyedM`

Parameters for keyed mutex objects

unsigned long long

`CUDA_EXTERNAL_SEMAPHORE_SIGNAL_PARAMS_v1::value`

Value of fence to be signaled

7.13. `CUDA_EXTERNAL_SEMAPHORE_WAIT_PARAMS` Struct Reference

External semaphore wait parameters

`CUDA_EXTERNAL_SEMAPHORE_WAIT_PARAMS_v1::@19::@20`
`CUDA_EXTERNAL_SEMAPHORE_WAIT_PARAMS_v1::fence`

Parameters for fence objects

unsigned int

`CUDA_EXTERNAL_SEMAPHORE_WAIT_PARAMS_v1::flags`

Only when `CUDA_EXTERNAL_SEMAPHORE_WAIT_PARAMS` is used to wait on a `CUexternalSemaphore` of type `CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_NVSCISYNC`, the valid flag is `CUDA_EXTERNAL_SEMAPHORE_WAIT_SKIP_NVSCIBUF_MEMSYNC` which indicates that while waiting for the `CUexternalSemaphore`, no memory synchronization operations should be performed for any external memory object imported as `CU_EXTERNAL_MEMORY_HANDLE_TYPE_NVSCIBUF`. For all other types of `CUexternalSemaphore`, flags must be zero.

unsigned long long

`CUDA_EXTERNAL_SEMAPHORE_WAIT_PARAMS_v1::key`

Value of key to acquire the mutex with

`CUDA_EXTERNAL_SEMAPHORE_WAIT_PARAMS_v1::@19::@22`

`CUDA_EXTERNAL_SEMAPHORE_WAIT_PARAMS_v1::keyedMut`

Parameters for keyed mutex objects

`CUDA_EXTERNAL_SEMAPHORE_WAIT_PARAMS_v1::@19::@21`

`CUDA_EXTERNAL_SEMAPHORE_WAIT_PARAMS_v1::nvSciSyn`

Pointer to `NvSciSyncFence`. Valid if `CUexternalSemaphoreHandleType` is of type `CU_EXTERNAL_SEMAPHORE_HANDLE_TYPE_NVSCISYNC`.

unsigned int

`CUDA_EXTERNAL_SEMAPHORE_WAIT_PARAMS_v1::timeoutM`

Timeout in milliseconds to wait to acquire the mutex

unsigned long long

`CUDA_EXTERNAL_SEMAPHORE_WAIT_PARAMS_v1::value`

Value of fence to be waited on

7.14. CUDA_HOST_NODE_PARAMS_v1 Struct Reference

Host node parameters

`CUhostFn CUDA_HOST_NODE_PARAMS_v1::fn`

The function to call when the node executes

`void *CUDA_HOST_NODE_PARAMS_v1::userData`

Argument to pass to the function

7.15. CUDA_KERNEL_NODE_PARAMS_v1 Struct Reference

GPU kernel node parameters

`unsigned int`

`CUDA_KERNEL_NODE_PARAMS_v1::blockDimX`

X dimension of each thread block

`unsigned int`

`CUDA_KERNEL_NODE_PARAMS_v1::blockDimY`

Y dimension of each thread block

`unsigned int`

`CUDA_KERNEL_NODE_PARAMS_v1::blockDimZ`

Z dimension of each thread block

`**CUDA_KERNEL_NODE_PARAMS_v1::extra`

Extra options

`CUfunction CUDA_KERNEL_NODE_PARAMS_v1::func`

Kernel to launch

`unsigned int`

`CUDA_KERNEL_NODE_PARAMS_v1::gridDimX`

Width of grid in blocks

`unsigned int`

`CUDA_KERNEL_NODE_PARAMS_v1::gridDimY`

Height of grid in blocks

`unsigned int`

`CUDA_KERNEL_NODE_PARAMS_v1::gridDimZ`

Depth of grid in blocks

`**CUDA_KERNEL_NODE_PARAMS_v1::kernelParams`

Array of pointers to kernel parameters

`unsigned int`

`CUDA_KERNEL_NODE_PARAMS_v1::sharedMemBytes`

Dynamic shared-memory size per thread block in bytes

7.16. CUDA_LAUNCH_PARAMS_v1 Struct Reference

Kernel launch parameters

`unsigned int`

`CUDA_LAUNCH_PARAMS_v1::blockDimX`

X dimension of each thread block

`unsigned int CUDA_LAUNCH_PARAMS_v1::blockDimY`

Y dimension of each thread block

`unsigned int
CUDA_LAUNCH_PARAMS_v1::blockDimZ`

Z dimension of each thread block

`CUfunction CUDA_LAUNCH_PARAMS_v1::function`

Kernel to launch

`unsigned int CUDA_LAUNCH_PARAMS_v1::gridDimX`

Width of grid in blocks

`unsigned int CUDA_LAUNCH_PARAMS_v1::gridDimY`

Height of grid in blocks

`unsigned int CUDA_LAUNCH_PARAMS_v1::gridDimZ`

Depth of grid in blocks

`CUstream CUDA_LAUNCH_PARAMS_v1::hStream`

Stream identifier

`**CUDA_LAUNCH_PARAMS_v1::kernelParams`

Array of pointers to kernel parameters

`unsigned int
CUDA_LAUNCH_PARAMS_v1::sharedMemBytes`

Dynamic shared-memory size per thread block in bytes

7.17. CUDA_MEMCPY2D_v2 Struct Reference

2D memory copy parameters

`CUarray` `CUDA_MEMCPY2D_v2::dstArray`

Destination array reference

`CUdeviceptr` `CUDA_MEMCPY2D_v2::dstDevice`

Destination device pointer

`void *``CUDA_MEMCPY2D_v2::dstHost`

Destination host pointer

`CUmemorytype`

`CUDA_MEMCPY2D_v2::dstMemoryType`

Destination memory type (host, device, array)

`size_t` `CUDA_MEMCPY2D_v2::dstPitch`

Destination pitch (ignored when dst is array)

`size_t` `CUDA_MEMCPY2D_v2::dstXInBytes`

Destination X in bytes

`size_t` `CUDA_MEMCPY2D_v2::dstY`

Destination Y

`size_t` `CUDA_MEMCPY2D_v2::Height`

Height of 2D memory copy

`CUarray` `CUDA_MEMCPY2D_v2::srcArray`

Source array reference

`CUdeviceptr CUDA_MEMCPY2D_v2::srcDevice`

Source device pointer

`const void *CUDA_MEMCPY2D_v2::srcHost`

Source host pointer

`CUmemorytype`

`CUDA_MEMCPY2D_v2::srcMemoryType`

Source memory type (host, device, array)

`size_t CUDA_MEMCPY2D_v2::srcPitch`

Source pitch (ignored when src is array)

`size_t CUDA_MEMCPY2D_v2::srcXInBytes`

Source X in bytes

`size_t CUDA_MEMCPY2D_v2::srcY`

Source Y

`size_t CUDA_MEMCPY2D_v2::WidthInBytes`

Width of 2D memory copy in bytes

7.18. `CUDA_MEMCPY3D_PEER_v1` Struct Reference

3D memory cross-context copy parameters

`size_t CUDA_MEMCPY3D_PEER_v1::Depth`

Depth of 3D memory copy

`CUarray CUDA_MEMCPY3D_PEER_v1::dstArray`

Destination array reference

CUcontext CUDA_MEMCPY3D_PEER_v1::dstContext

Destination context (ignored with dstMemoryType is [CU_MEMORYTYPE_ARRAY](#))

CUdeviceptr CUDA_MEMCPY3D_PEER_v1::dstDevice

Destination device pointer

size_t CUDA_MEMCPY3D_PEER_v1::dstHeight

Destination height (ignored when dst is array; may be 0 if Depth==1)

void *CUDA_MEMCPY3D_PEER_v1::dstHost

Destination host pointer

size_t CUDA_MEMCPY3D_PEER_v1::dstLOD

Destination LOD

CUmemorytype

CUDA_MEMCPY3D_PEER_v1::dstMemoryType

Destination memory type (host, device, array)

size_t CUDA_MEMCPY3D_PEER_v1::dstPitch

Destination pitch (ignored when dst is array)

size_t CUDA_MEMCPY3D_PEER_v1::dstXInBytes

Destination X in bytes

size_t CUDA_MEMCPY3D_PEER_v1::dstY

Destination Y

size_t CUDA_MEMCPY3D_PEER_v1::dstZ

Destination Z

`size_t CUDA_MEMCPY3D_PEER_v1::Height`

Height of 3D memory copy

`CUarray CUDA_MEMCPY3D_PEER_v1::srcArray`

Source array reference

`CUcontext CUDA_MEMCPY3D_PEER_v1::srcContext`

Source context (ignored with `srcMemoryType` is `CU_MEMORYTYPE_ARRAY`)

`CUdeviceptr CUDA_MEMCPY3D_PEER_v1::srcDevice`

Source device pointer

`size_t CUDA_MEMCPY3D_PEER_v1::srcHeight`

Source height (ignored when `src` is array; may be 0 if `Depth==1`)

`const void *CUDA_MEMCPY3D_PEER_v1::srcHost`

Source host pointer

`size_t CUDA_MEMCPY3D_PEER_v1::srcLOD`

Source LOD

`CUmemorytype`

`CUDA_MEMCPY3D_PEER_v1::srcMemoryType`

Source memory type (host, device, array)

`size_t CUDA_MEMCPY3D_PEER_v1::srcPitch`

Source pitch (ignored when `src` is array)

`size_t CUDA_MEMCPY3D_PEER_v1::srcXInBytes`

Source X in bytes

`size_t CUDA_MEMCPY3D_PEER_v1::srcY`

Source Y

`size_t CUDA_MEMCPY3D_PEER_v1::srcZ`

Source Z

`size_t CUDA_MEMCPY3D_PEER_v1::WidthInBytes`

Width of 3D memory copy in bytes

7.19. CUDA_MEMCPY3D_v2 Struct Reference

3D memory copy parameters

`size_t CUDA_MEMCPY3D_v2::Depth`

Depth of 3D memory copy

`CUarray CUDA_MEMCPY3D_v2::dstArray`

Destination array reference

`CUdeviceptr CUDA_MEMCPY3D_v2::dstDevice`

Destination device pointer

`size_t CUDA_MEMCPY3D_v2::dstHeight`

Destination height (ignored when dst is array; may be 0 if Depth==1)

`void *CUDA_MEMCPY3D_v2::dstHost`

Destination host pointer

`size_t CUDA_MEMCPY3D_v2::dstLOD`

Destination LOD

`CUmemorytype`

`CUDA_MEMCPY3D_v2::dstMemoryType`

Destination memory type (host, device, array)

`size_t CUDA_MEMCPY3D_v2::dstPitch`

Destination pitch (ignored when dst is array)

`size_t CUDA_MEMCPY3D_v2::dstXInBytes`

Destination X in bytes

`size_t CUDA_MEMCPY3D_v2::dstY`

Destination Y

`size_t CUDA_MEMCPY3D_v2::dstZ`

Destination Z

`size_t CUDA_MEMCPY3D_v2::Height`

Height of 3D memory copy

`void *CUDA_MEMCPY3D_v2::reserved0`

Must be NULL

`void *CUDA_MEMCPY3D_v2::reserved1`

Must be NULL

`CUarray CUDA_MEMCPY3D_v2::srcArray`

Source array reference

`CUdeviceptr CUDA_MEMCPY3D_v2::srcDevice`

Source device pointer

`size_t CUDA_MEMCPY3D_v2::srcHeight`

Source height (ignored when src is array; may be 0 if Depth==1)

`const void *CUDA_MEMCPY3D_v2::srcHost`

Source host pointer

`size_t CUDA_MEMCPY3D_v2::srcLOD`

Source LOD

`CUmemorytype`

`CUDA_MEMCPY3D_v2::srcMemoryType`

Source memory type (host, device, array)

`size_t CUDA_MEMCPY3D_v2::srcPitch`

Source pitch (ignored when src is array)

`size_t CUDA_MEMCPY3D_v2::srcXInBytes`

Source X in bytes

`size_t CUDA_MEMCPY3D_v2::srcY`

Source Y

`size_t CUDA_MEMCPY3D_v2::srcZ`

Source Z

`size_t CUDA_MEMCPY3D_v2::WidthInBytes`

Width of 3D memory copy in bytes

7.20. `CUDA_MEMSET_NODE_PARAMS_v1` Struct Reference

Memset node parameters

`CUdeviceptr CUDA_MEMSET_NODE_PARAMS_v1::dst`

Destination device pointer

`unsigned int`

`CUDA_MEMSET_NODE_PARAMS_v1::elementSize`

Size of each element in bytes. Must be 1, 2, or 4.

`size_t CUDA_MEMSET_NODE_PARAMS_v1::height`

Number of rows

`size_t CUDA_MEMSET_NODE_PARAMS_v1::pitch`

Pitch of destination device pointer. Unused if height is 1

`unsigned int`

`CUDA_MEMSET_NODE_PARAMS_v1::value`

Value to be set

`size_t CUDA_MEMSET_NODE_PARAMS_v1::width`

Width of the row in elements

7.21. `CUDA_POINTER_ATTRIBUTE_P2P_TOKENS` Struct Reference

GPU Direct v3 tokens

7.22. `CUDA_RESOURCE_DESC_v1` Struct Reference

CUDA Resource descriptor

`CUdeviceptr CUDA_RESOURCE_DESC_v1::devPtr`

Device pointer

`unsigned int CUDA_RESOURCE_DESC_v1::flags`

Flags (must be zero)

`CUarray_format CUDA_RESOURCE_DESC_v1::format`

Array format

`CUarray CUDA_RESOURCE_DESC_v1::hArray`

CUDA array

`size_t CUDA_RESOURCE_DESC_v1::height`

Height of the array in elements

`CUmipmappedArray`

`CUDA_RESOURCE_DESC_v1::hMipmappedArray`

CUDA mipmapped array

`unsigned int`

`CUDA_RESOURCE_DESC_v1::numChannels`

Channels per array element

`size_t CUDA_RESOURCE_DESC_v1::pitchInBytes`

Pitch between two rows in bytes

`CUresourcetype`

`CUDA_RESOURCE_DESC_v1::resType`

Resource type

`size_t CUDA_RESOURCE_DESC_v1::sizeInBytes`

Size in bytes

`size_t CUDA_RESOURCE_DESC_v1::width`

Width of the array in elements

7.23. `CUDA_RESOURCE_VIEW_DESC_v1` Struct Reference

Resource view descriptor

`size_t CUDA_RESOURCE_VIEW_DESC_v1::depth`

Depth of the resource view

`unsigned int`

`CUDA_RESOURCE_VIEW_DESC_v1::firstLayer`

First layer index

`unsigned int`

`CUDA_RESOURCE_VIEW_DESC_v1::firstMipmapLevel`

First defined mipmap level

`CUresourceViewFormat`

`CUDA_RESOURCE_VIEW_DESC_v1::format`

Resource view format

`size_t CUDA_RESOURCE_VIEW_DESC_v1::height`

Height of the resource view

`unsigned int`

`CUDA_RESOURCE_VIEW_DESC_v1::lastLayer`

Last layer index

unsigned int

CUDA_RESOURCE_VIEW_DESC_v1::lastMipmapLevel

Last defined mipmap level

size_t CUDA_RESOURCE_VIEW_DESC_v1::width

Width of the resource view

7.24. CUDA_TEXTURE_DESC_v1 Struct Reference

Texture descriptor

CUaddress_mode

CUDA_TEXTURE_DESC_v1::addressMode

Address modes

float CUDA_TEXTURE_DESC_v1::borderColor

Border Color

CUfilter_mode CUDA_TEXTURE_DESC_v1::filterMode

Filter mode

unsigned int CUDA_TEXTURE_DESC_v1::flags

Flags

unsigned int

CUDA_TEXTURE_DESC_v1::maxAnisotropy

Maximum anisotropy ratio

float

CUDA_TEXTURE_DESC_v1::maxMipmapLevelClamp

Mipmap maximum level clamp

float

CUDA_TEXTURE_DESC_v1::minMipmapLevelClamp

Mipmap minimum level clamp

CUfilter_mode

CUDA_TEXTURE_DESC_v1::mipmapFilterMode

Mipmap filter mode

float CUDA_TEXTURE_DESC_v1::mipmapLevelBias

Mipmap level bias

7.25. CUdevprop_v1 Struct Reference

Legacy device properties

int CUdevprop_v1::clockRate

Clock frequency in kilohertz

int CUdevprop_v1::maxGridSize

Maximum size of each dimension of a grid

int CUdevprop_v1::maxThreadsDim

Maximum size of each dimension of a block

int CUdevprop_v1::maxThreadsPerBlock

Maximum number of threads per block

int CUdevprop_v1::memPitch

Maximum pitch in bytes allowed by memory copies

int CUdevprop_v1::regsPerBlock

32-bit registers available per block

int CUdevprop_v1::sharedMemPerBlock

Shared memory available per block in bytes

int CUdevprop_v1::SIMDWidth

Warp size in threads

int CUdevprop_v1::textureAlign

Alignment requirement for textures

int CUdevprop_v1::totalConstantMemory

Constant memory available on device in bytes

7.26. CUeglFrame_v1 Struct Reference

CUDA EGLFrame structure Descriptor - structure defining one frame of EGL.

Each frame may contain one or more planes depending on whether the surface * is Multiplanar or not.

CUarray_format CUeglFrame_v1::cuFormat

CUDA Array Format

unsigned int CUeglFrame_v1::depth

Depth of first plane

CUeglColorFormat CUeglFrame_v1::eglColorFormat

CUDA EGL Color Format

CUeglFrameType CUeglFrame_v1::frameType

Array or Pitch

unsigned int CUeglFrame_v1::height

Height of first plane

unsigned int CUeglFrame_v1::numChannels

Number of channels for the plane

CUarray CUeglFrame_v1::pArray

Array of CUarray corresponding to each plane

unsigned int CUeglFrame_v1::pitch

Pitch of first plane

unsigned int CUeglFrame_v1::planeCount

Number of planes

void *CUeglFrame_v1::pPitch

Array of Pointers corresponding to each plane

unsigned int CUeglFrame_v1::width

Width of first plane

7.27. CUipcEventHandle_v1 Struct Reference

CUDA IPC event handle

7.28. CUipcMemHandle_v1 Struct Reference

CUDA IPC mem handle

7.29. CUkernelNodeAttrValue_v1 Union Reference

Graph kernel node attributes union, used with `cuKernelNodeSetAttribute/`
`cuKernelNodeGetAttribute`

```
struct CUaccessPolicyWindow
CUkernelNodeAttrValue_v1::accessPolicyWindow
```

Attribute CUaccessPolicyWindow.

```
int CUkernelNodeAttrValue_v1::cooperative
```

Nonzero indicates a cooperative kernel (see [cuLaunchCooperativeKernel](#)).

7.30. CUmемAccessDesc_v1 Struct Reference

Memory access descriptor

```
CUmемAccess_flags CUmемAccessDesc_v1::flags
```

CUmемProt accessibility flags to set on the request

```
struct CUmемLocation
CUmемAccessDesc_v1::location
```

Location on which the request is to change it's accessibility

7.31. CUmemAllocationProp_v1 Struct Reference

Specifies the allocation properties for a allocation.

unsigned char

CUmemAllocationProp_v1::compressionType

Allocation hint for requesting compressible memory. On devices that support Compute Data Compression, compressible memory can be used to accelerate accesses to data with unstructured sparsity and other compressible data patterns. Applications are expected to query allocation property of the handle obtained with [cuMemCreate](#) using [cuMemGetAllocationPropertiesFromHandle](#) to validate if the obtained allocation is compressible or not. Note that compressed memory may not be mappable on all devices.

struct CUmemLocation

CUmemAllocationProp_v1::location

Location of allocation

CUmemAllocationHandleType

CUmemAllocationProp_v1::requestedHandleTypes

requested [CUmemAllocationHandleType](#)

CUmemAllocationType

CUmemAllocationProp_v1::type

Allocation type

unsigned short CUmemAllocationProp_v1::usage

Bitmask indicating intended usage for this allocation

void

*CUmemAllocationProp_v1::win32HandleMetaData

Windows-specific POBJECT_ATTRIBUTES required when [CU_MEM_HANDLE_TYPE_WIN32](#) is specified. This object attributes structure includes security attributes that define the scope of which exported allocations may be transferred to other processes. In all other cases, this field is required to be zero.

7.32. CUmemLocation_v1 Struct Reference

Specifies a memory location.

int CUmemLocation_v1::id

identifier for a given this location's [CUmemLocationType](#).

CUmemLocationType CUmemLocation_v1::type

Specifies the location type, which modifies the meaning of id.

7.33. CUmemPoolProps_v1 Struct Reference

Specifies the properties of allocations made from the pool.

CUmemAllocationType

CUmemPoolProps_v1::allocType

Allocation type. Currently must be specified as [CU_MEM_ALLOCATION_TYPE_PINNED](#)

CUmemAllocationHandleType

CUmemPoolProps_v1::handleTypes

Handle types that will be supported by allocations from the pool.

```
struct CUmemLocation
CUmemPoolProps_v1::location
```

Location where allocations should reside.

```
unsigned char CUmemPoolProps_v1::reserved
```

reserved for future use, must be 0

```
void *CUmemPoolProps_v1::win32SecurityAttributes
```

Windows-specific LPSECURITY_ATTRIBUTES required when [CU_MEM_HANDLE_TYPE_WIN32](#) is specified. This security attribute defines the scope of which exported allocations may be transferred to other processes. In all other cases, this field is required to be zero.

7.34. CUmemPoolPtrExportData_v1 Struct Reference

Opaque data for exporting a pool allocation

7.35. CUstreamAttrValue_v1 Union Reference

Stream attributes union, used with [cuStreamSetAttribute/cuStreamGetAttribute](#)

```
struct CUaccessPolicyWindow
CUstreamAttrValue_v1::accessPolicyWindow
```

Attribute CUaccessPolicyWindow.

```
CUsynchronizationPolicy
CUstreamAttrValue_v1::syncPolicy
```

Value for [CU_STREAM_ATTRIBUTE_SYNCHRONIZATION_POLICY](#).

7.36. CUstreamBatchMemOpParams_v1 Union Reference

Per-operation parameters for [cuStreamBatchMemOp](#)

Chapter 8. Data Fields

Here is a list of all documented struct and union fields with links to the struct/union documentation for each field:

A

accessPolicyWindow

[CUkernelNodeAttrValue_v1](#)

[CUstreamAttrValue_v1](#)

addressMode

[CUDA_TEXTURE_DESC_v1](#)

allocType

[CUmemPoolProps_v1](#)

arrayDesc

[CUDA_EXTERNAL_MEMORY_MIPMAPPED_ARRAY_DESC_v1](#)

B

base_ptr

[CUaccessPolicyWindow_v1](#)

blockDimX

[CUDA_KERNEL_NODE_PARAMS_v1](#)

[CUDA_LAUNCH_PARAMS_v1](#)

blockDimY

[CUDA_KERNEL_NODE_PARAMS_v1](#)

[CUDA_LAUNCH_PARAMS_v1](#)

blockDimZ

[CUDA_KERNEL_NODE_PARAMS_v1](#)

[CUDA_LAUNCH_PARAMS_v1](#)

borderColor

[CUDA_TEXTURE_DESC_v1](#)

C

clockRate

[CUdevprop_v1](#)

compressionType[CUmemAllocationProp_v1](#)**cooperative**[CUkernelNodeAttrValue_v1](#)**cuFormat**[CUeglFrame_v1](#)**D****depth**[CUDA_ARRAY_SPARSE_PROPERTIES_v1](#)[CUDA_RESOURCE_VIEW_DESC_v1](#)**Depth**[CUDA_MEMCPY3D_v2](#)[CUDA_MEMCPY3D_PEER_v1](#)**depth**[CUeglFrame_v1](#)**Depth**[CUDA_ARRAY3D_DESCRIPTOR_v2](#)**deviceBitMask**[CUarrayMapInfo_v1](#)**devPtr**[CUDA_RESOURCE_DESC_v1](#)**dst**[CUDA_MEMSET_NODE_PARAMS_v1](#)**dstArray**[CUDA_MEMCPY2D_v2](#)[CUDA_MEMCPY3D_v2](#)[CUDA_MEMCPY3D_PEER_v1](#)**dstContext**[CUDA_MEMCPY3D_PEER_v1](#)**dstDevice**[CUDA_MEMCPY3D_PEER_v1](#)[CUDA_MEMCPY2D_v2](#)[CUDA_MEMCPY3D_v2](#)**dstHeight**[CUDA_MEMCPY3D_v2](#)[CUDA_MEMCPY3D_PEER_v1](#)**dstHost**[CUDA_MEMCPY2D_v2](#)[CUDA_MEMCPY3D_v2](#)[CUDA_MEMCPY3D_PEER_v1](#)**dstLOD**[CUDA_MEMCPY3D_v2](#)

[CUDA_MEMCPY3D_PEER_v1](#)

dstMemoryType

[CUDA_MEMCPY2D_v2](#)

[CUDA_MEMCPY3D_v2](#)

[CUDA_MEMCPY3D_PEER_v1](#)

dstPitch

[CUDA_MEMCPY3D_PEER_v1](#)

[CUDA_MEMCPY2D_v2](#)

[CUDA_MEMCPY3D_v2](#)

dstXInBytes

[CUDA_MEMCPY3D_PEER_v1](#)

[CUDA_MEMCPY3D_v2](#)

[CUDA_MEMCPY2D_v2](#)

dstY

[CUDA_MEMCPY3D_PEER_v1](#)

[CUDA_MEMCPY2D_v2](#)

[CUDA_MEMCPY3D_v2](#)

dstZ

[CUDA_MEMCPY3D_PEER_v1](#)

[CUDA_MEMCPY3D_v2](#)

E

eglColorFormat

[CUeglFrame_v1](#)

elementSize

[CUDA_MEMSET_NODE_PARAMS_v1](#)

extentDepth

[CUarrayMapInfo_v1](#)

extentHeight

[CUarrayMapInfo_v1](#)

extentWidth

[CUarrayMapInfo_v1](#)

extra

[CUDA_KERNEL_NODE_PARAMS_v1](#)

extSemArray

[CUDA_EXT_SEM_WAIT_NODE_PARAMS_v1](#)

[CUDA_EXT_SEM_SIGNAL_NODE_PARAMS_v1](#)

F

fd

[CUDA_EXTERNAL_MEMORY_HANDLE_DESC_v1](#)

[CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC_v1](#)

fence[CUDA_EXTERNAL_SEMAPHORE_SIGNAL_PARAMS_v1](#)[CUDA_EXTERNAL_SEMAPHORE_WAIT_PARAMS_v1](#)[CUDA_EXTERNAL_SEMAPHORE_SIGNAL_PARAMS_v1](#)**filterMode**[CUDA_TEXTURE_DESC_v1](#)**firstLayer**[CUDA_RESOURCE_VIEW_DESC_v1](#)**firstMipmapLevel**[CUDA_RESOURCE_VIEW_DESC_v1](#)**flags**[CUDA_EXTERNAL_SEMAPHORE_WAIT_PARAMS_v1](#)**Flags**[CUDA_ARRAY3D_DESCRIPTOR_v2](#)**flags**[CUarrayMapInfo_v1](#)[CUDA_ARRAY_SPARSE_PROPERTIES_v1](#)[CUmemAccessDesc_v1](#)[CUDA_EXTERNAL_SEMAPHORE_SIGNAL_PARAMS_v1](#)[CUDA_RESOURCE_DESC_v1](#)[CUDA_TEXTURE_DESC_v1](#)[CUDA_EXTERNAL_MEMORY_HANDLE_DESC_v1](#)[CUDA_EXTERNAL_MEMORY_BUFFER_DESC_v1](#)[CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC_v1](#)**fn**[CUDA_HOST_NODE_PARAMS_v1](#)**format**[CUDA_RESOURCE_DESC_v1](#)[CUDA_RESOURCE_VIEW_DESC_v1](#)**Format**[CUDA_ARRAY3D_DESCRIPTOR_v2](#)[CUDA_ARRAY_DESCRIPTOR_v2](#)**frameType**[CUeglFrame_v1](#)**func**[CUDA_KERNEL_NODE_PARAMS_v1](#)**function**[CUDA_LAUNCH_PARAMS_v1](#)**G****gridDimX**[CUDA_KERNEL_NODE_PARAMS_v1](#)[CUDA_LAUNCH_PARAMS_v1](#)

gridDimY

[CUDA_LAUNCH_PARAMS_v1](#)
[CUDA_KERNEL_NODE_PARAMS_v1](#)

gridDimZ

[CUDA_LAUNCH_PARAMS_v1](#)
[CUDA_KERNEL_NODE_PARAMS_v1](#)

H**handle**

[CUDA_EXTERNAL_MEMORY_HANDLE_DESC_v1](#)
[CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC_v1](#)

handleTypes

[CUmemPoolProps_v1](#)

hArray

[CUDA_RESOURCE_DESC_v1](#)

height

[CUDA_RESOURCE_VIEW_DESC_v1](#)

Height

[CUDA_ARRAY3D_DESCRIPTOR_v2](#)
[CUDA_ARRAY_DESCRIPTOR_v2](#)

height

[CUeglFrame_v1](#)

Height

[CUDA_MEMCPY3D_v2](#)

height

[CUDA_MEMSET_NODE_PARAMS_v1](#)

Height

[CUDA_MEMCPY2D_v2](#)

height

[CUDA_ARRAY_SPARSE_PROPERTIES_v1](#)
[CUDA_RESOURCE_DESC_v1](#)

Height

[CUDA_MEMCPY3D_PEER_v1](#)

hitProp

[CUaccessPolicyWindow_v1](#)

hitRatio

[CUaccessPolicyWindow_v1](#)

hMipmappedArray

[CUDA_RESOURCE_DESC_v1](#)

hStream

[CUDA_LAUNCH_PARAMS_v1](#)

I

id[CUmemLocation_v1](#)

K

kernelParams[CUDA_KERNEL_NODE_PARAMS_v1](#)[CUDA_LAUNCH_PARAMS_v1](#)**key**[CUDA_EXTERNAL_SEMAPHORE_WAIT_PARAMS_v1](#)[CUDA_EXTERNAL_SEMAPHORE_SIGNAL_PARAMS_v1](#)**keyedMutex**[CUDA_EXTERNAL_SEMAPHORE_WAIT_PARAMS_v1](#)[CUDA_EXTERNAL_SEMAPHORE_SIGNAL_PARAMS_v1](#)

L

lastLayer[CUDA_RESOURCE_VIEW_DESC_v1](#)**lastMipmapLevel**[CUDA_RESOURCE_VIEW_DESC_v1](#)**layer**[CUarrayMapInfo_v1](#)**level**[CUarrayMapInfo_v1](#)**location**[CUmemPoolProps_v1](#)[CUmemAccessDesc_v1](#)[CUmemAllocationProp_v1](#)

M

maxAnisotropy[CUDA_TEXTURE_DESC_v1](#)**maxGridSize**[CUdevprop_v1](#)**maxMipmapLevelClamp**[CUDA_TEXTURE_DESC_v1](#)**maxThreadsDim**[CUdevprop_v1](#)**maxThreadsPerBlock**[CUdevprop_v1](#)**memHandleType**[CUarrayMapInfo_v1](#)

memOperationType[CUarrayMapInfo_v1](#)**memPitch**[CUdevprop_v1](#)**minMipmapLevelClamp**[CUDA_TEXTURE_DESC_v1](#)**mipmapFilterMode**[CUDA_TEXTURE_DESC_v1](#)**mipmapLevelBias**[CUDA_TEXTURE_DESC_v1](#)**miptailFirstLevel**[CUDA_ARRAY_SPARSE_PROPERTIES_v1](#)**miptailSize**[CUDA_ARRAY_SPARSE_PROPERTIES_v1](#)**missProp**[CUaccessPolicyWindow_v1](#)**N****name**[CUDA_EXTERNAL_MEMORY_HANDLE_DESC_v1](#)[CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC_v1](#)**num_bytes**[CUaccessPolicyWindow_v1](#)**numChannels**[CUDA_RESOURCE_DESC_v1](#)[CUeglFrame_v1](#)**NumChannels**[CUDA_ARRAY_DESCRIPTOR_v2](#)[CUDA_ARRAY3D_DESCRIPTOR_v2](#)**numExtSems**[CUDA_EXT_SEM_SIGNAL_NODE_PARAMS_v1](#)[CUDA_EXT_SEM_WAIT_NODE_PARAMS_v1](#)**numLevels**[CUDA_EXTERNAL_MEMORY_MIPMAPPED_ARRAY_DESC_v1](#)**nvSciBufObject**[CUDA_EXTERNAL_MEMORY_HANDLE_DESC_v1](#)**nvSciSync**[CUDA_EXTERNAL_SEMAPHORE_WAIT_PARAMS_v1](#)**nvSciSyncObj**[CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC_v1](#)

O

offset

[CUDA_EXTERNAL_MEMORY_BUFFER_DESC_v1](#)
[CUDA_EXTERNAL_MEMORY_MIPMAPPED_ARRAY_DESC_v1](#)
[CUarrayMapInfo_v1](#)

offsetX

[CUarrayMapInfo_v1](#)

offsetY

[CUarrayMapInfo_v1](#)

offsetZ

[CUarrayMapInfo_v1](#)

P

paramsArray

[CUDA_EXT_SEM_SIGNAL_NODE_PARAMS_v1](#)
[CUDA_EXT_SEM_WAIT_NODE_PARAMS_v1](#)

pArray

[CUeglFrame_v1](#)

pitch

[CUDA_MEMSET_NODE_PARAMS_v1](#)
[CUeglFrame_v1](#)

pitchInBytes

[CUDA_RESOURCE_DESC_v1](#)

planeCount

[CUeglFrame_v1](#)

pPitch

[CUeglFrame_v1](#)

R

regsPerBlock

[CUdevprop_v1](#)

requestedHandleTypes

[CUmemAllocationProp_v1](#)

reserved

[CUmemPoolProps_v1](#)
[CUarrayMapInfo_v1](#)

reserved0

[CUDA_MEMCPY3D_v2](#)

reserved1

[CUDA_MEMCPY3D_v2](#)

resourceType

[CUarrayMapInfo_v1](#)

resType[CUDA_RESOURCE_DESC_v1](#)**S****sharedMemBytes**[CUDA_KERNEL_NODE_PARAMS_v1](#)[CUDA_LAUNCH_PARAMS_v1](#)**sharedMemPerBlock**[CUdevprop_v1](#)**SIMDWidth**[CUdevprop_v1](#)**size**[CUDA_EXTERNAL_MEMORY_HANDLE_DESC_v1](#)[CUDA_EXTERNAL_MEMORY_BUFFER_DESC_v1](#)[CUarrayMapInfo_v1](#)**sizeInBytes**[CUDA_RESOURCE_DESC_v1](#)**srcArray**[CUDA_MEMCPY2D_v2](#)[CUDA_MEMCPY3D_v2](#)[CUDA_MEMCPY3D_PEER_v1](#)**srcContext**[CUDA_MEMCPY3D_PEER_v1](#)**srcDevice**[CUDA_MEMCPY2D_v2](#)[CUDA_MEMCPY3D_v2](#)[CUDA_MEMCPY3D_PEER_v1](#)**srcHeight**[CUDA_MEMCPY3D_v2](#)[CUDA_MEMCPY3D_PEER_v1](#)**srcHost**[CUDA_MEMCPY2D_v2](#)[CUDA_MEMCPY3D_v2](#)[CUDA_MEMCPY3D_PEER_v1](#)**srcLOD**[CUDA_MEMCPY3D_v2](#)[CUDA_MEMCPY3D_PEER_v1](#)**srcMemoryType**[CUDA_MEMCPY2D_v2](#)[CUDA_MEMCPY3D_v2](#)[CUDA_MEMCPY3D_PEER_v1](#)**srcPitch**[CUDA_MEMCPY3D_v2](#)

[CUDA_MEMCPY2D_v2](#)[CUDA_MEMCPY3D_PEER_v1](#)**srcXInBytes**[CUDA_MEMCPY2D_v2](#)[CUDA_MEMCPY3D_PEER_v1](#)[CUDA_MEMCPY3D_v2](#)**srcY**[CUDA_MEMCPY2D_v2](#)[CUDA_MEMCPY3D_PEER_v1](#)[CUDA_MEMCPY3D_v2](#)**srcZ**[CUDA_MEMCPY3D_PEER_v1](#)[CUDA_MEMCPY3D_v2](#)**subresourceType**[CUarrayMapInfo_v1](#)**syncPolicy**[CUstreamAttrValue_v1](#)**T****textureAlign**[CUdevprop_v1](#)**timeoutMs**[CUDA_EXTERNAL_SEMAPHORE_WAIT_PARAMS_v1](#)**totalConstantMemory**[CUdevprop_v1](#)**type**[CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC_v1](#)[CUDA_EXTERNAL_MEMORY_HANDLE_DESC_v1](#)[CUmemLocation_v1](#)[CUmemAllocationProp_v1](#)**U****usage**[CUmemAllocationProp_v1](#)**userData**[CUDA_HOST_NODE_PARAMS_v1](#)**V****value**[CUDA_MEMSET_NODE_PARAMS_v1](#)[CUDA_EXTERNAL_SEMAPHORE_WAIT_PARAMS_v1](#)[CUDA_EXTERNAL_SEMAPHORE_SIGNAL_PARAMS_v1](#)

W**width**

[CUDA_MEMSET_NODE_PARAMS_v1](#)
[CUDA_ARRAY_SPARSE_PROPERTIES_v1](#)
[CUDA_RESOURCE_VIEW_DESC_v1](#)
[CUeglFrame_v1](#)
[CUDA_RESOURCE_DESC_v1](#)

Width

[CUDA_ARRAY_DESCRIPTOR_v2](#)
[CUDA_ARRAY3D_DESCRIPTOR_v2](#)

WidthInBytes

[CUDA_MEMCPY2D_v2](#)
[CUDA_MEMCPY3D_v2](#)
[CUDA_MEMCPY3D_PEER_v1](#)

win32

[CUDA_EXTERNAL_MEMORY_HANDLE_DESC_v1](#)
[CUDA_EXTERNAL_SEMAPHORE_HANDLE_DESC_v1](#)

win32HandleMetaData

[CUmemAllocationProp_v1](#)

win32SecurityAttributes

[CUmemPoolProps_v1](#)

Chapter 9. Deprecated List

Global CU_CTX_BLOCKING_SYNC

This flag was deprecated as of CUDA 4.0 and was replaced with CU_CTX_SCHED_BLOCKING_SYNC.

Global CU_CTX_MAP_HOST

This flag was deprecated as of CUDA 11.0 and it no longer has any effect. All contexts as of CUDA 3.2 behave as though the flag is enabled.

Global CU_DEVICE_P2P_ATTRIBUTE_ACCESS_ACCESS_SUPPORTED

use CU_DEVICE_P2P_ATTRIBUTE_CUDA_ARRAY_ACCESS_SUPPORTED instead

Global CUDA_ERROR_PROFILER_NOT_INITIALIZED

This error return is deprecated as of CUDA 5.0. It is no longer an error to attempt to enable/disable the profiling via cuProfilerStart or cuProfilerStop without initialization.

Global CUDA_ERROR_PROFILER_ALREADY_STARTED

This error return is deprecated as of CUDA 5.0. It is no longer an error to call cuProfilerStart() when profiling is already enabled.

Global CUDA_ERROR_PROFILER_ALREADY_STOPPED

This error return is deprecated as of CUDA 5.0. It is no longer an error to call cuProfilerStop() when profiling is already disabled.

Global CUDA_ERROR_CONTEXT_ALREADY_CURRENT

This error return is deprecated as of CUDA 3.2. It is no longer an error to attempt to push the active context via cuCtxPushCurrent().

Global cuDeviceComputeCapability

Global cuDeviceGetProperties

Global cuCtxAttach

Global cuCtxDetach

Global cuLaunchCooperativeKernelMultiDevice

This function is deprecated as of CUDA 11.3.

Global cuFuncSetBlockShape

Global cuFuncSetSharedSize

Global cuLaunch

Global cuLaunchGrid

Global cuLaunchGridAsync

Global cuParamSetf

Global cuParamSeti

Global cuParamSetSize

Global cuParamSetTexRef

Global cuParamSetv

Global cuTexRefCreate

Global cuTexRefDestroy

Global cuTexRefGetAddress

Global cuTexRefGetAddressMode

Global cuTexRefGetArray

Global cuTexRefGetBorderColor

Global cuTexRefGetFilterMode

Global cuTexRefGetFlags

Global cuTexRefGetFormat

Global cuTexRefGetMaxAnisotropy

Global cuTexRefGetMipmapFilterMode

Global cuTexRefGetMipmapLevelBias

Global cuTexRefGetMipmapLevelClamp

Global cuTexRefGetMipmappedArray

Global cuTexRefSetAddress

Global cuTexRefSetAddress2D

Global cuTexRefSetAddressMode

Global cuTexRefSetArray

Global cuTexRefSetBorderColor

Global cuTexRefSetFilterMode

Global cuTexRefSetFlags

Global cuTexRefSetFormat

Global cuTexRefSetMaxAnisotropy

Global cuTexRefSetMipmapFilterMode

Global cuTexRefSetMipmapLevelBias

Global cuTexRefSetMipmapLevelClamp**Global cuTexRefSetMipmappedArray****Global cuSurfRefGetArray****Global cuSurfRefSetArray****Global cuProfilerInitialize****Global cuGLCtxCreate**

This function is deprecated as of Cuda 5.0.

Global cuGLInit

This function is deprecated as of Cuda 3.0.

Global cuGLMapBufferObject

This function is deprecated as of Cuda 3.0.

Global cuGLMapBufferObjectAsync

This function is deprecated as of Cuda 3.0.

Global cuGLRegisterBufferObject

This function is deprecated as of Cuda 3.0.

Global cuGLSetBufferObjectMapFlags

This function is deprecated as of Cuda 3.0.

Global cuGLUnmapBufferObject

This function is deprecated as of Cuda 3.0.

Global cuGLUnmapBufferObjectAsync

This function is deprecated as of Cuda 3.0.

Global cuGLUnregisterBufferObject

This function is deprecated as of Cuda 3.0.

Notice

This document is provided for information purposes only and shall not be regarded as a warranty of a certain functionality, condition, or quality of a product. NVIDIA Corporation ("NVIDIA") makes no representations or warranties, expressed or implied, as to the accuracy or completeness of the information contained in this document and assumes no responsibility for any errors contained herein. NVIDIA shall have no liability for the consequences or use of such information or for any infringement of patents or other rights of third parties that may result from its use. This document is not a commitment to develop, release, or deliver any Material (defined below), code, or functionality.

NVIDIA reserves the right to make corrections, modifications, enhancements, improvements, and any other changes to this document, at any time without notice.

Customer should obtain the latest relevant information before placing orders and should verify that such information is current and complete.

NVIDIA products are sold subject to the NVIDIA standard terms and conditions of sale supplied at the time of order acknowledgement, unless otherwise agreed in an individual sales agreement signed by authorized representatives of NVIDIA and customer ("Terms of Sale"). NVIDIA hereby expressly objects to applying any customer general terms and conditions with regards to the purchase of the NVIDIA product referenced in this document. No contractual obligations are formed either directly or indirectly by this document.

VESA DisplayPort

DisplayPort and DisplayPort Compliance Logo, DisplayPort Compliance Logo for Dual-mode Sources, and DisplayPort Compliance Logo for Active Cables are trademarks owned by the Video Electronics Standards Association in the United States and other countries.

HDMI

HDMI, the HDMI logo, and High-Definition Multimedia Interface are trademarks or registered trademarks of HDMI Licensing LLC.

OpenCL

OpenCL is a trademark of Apple Inc. used under license to the Khronos Group Inc.

Trademarks

NVIDIA and the NVIDIA logo are trademarks or registered trademarks of NVIDIA Corporation in the U.S. and other countries. Other company and product names may be trademarks of the respective companies with which they are associated.

Copyright

© 2007-2021 NVIDIA Corporation. All rights reserved.

