


SMTP configuration is required to set both the <u>Daily Reports Tab</u> and the Email-on-Events features.


1. In the SMTP Configuration dialogue window, enter the following information:



Attribute	Description
SMTP Server	The IP or host name of the SMTP server. Examples: o If mail service is installed, localhost is a valid value for this field, but usually it cannot send mails outside the local domain. o smtp.gmail.com
SMTP Port	Default value – 25
Sender Name	The name that will be displayed in the email header

Attribute	Description
Sender Address	A valid email address that will be displayed in the email header
Time Zone	The default time zone for receiving sent emails is the server time zone. Users have the option to specify a different preferable time zone
Use Authentic ation	By default, this field is unchecked. If checked, you must supply a username and password in the respective fields
Use SSL	Default value is false – not using SSL
Username	SMTP account username
Password	SMTP account password

2. Click "Save." All configuration of the SMTP server will be saved in the UFM Database. Click "Send Test Email" to test the configuration and the following model will appear:



Attribut e	Description
Recipien ts	User can choose email from event policy and daily report recipients or enter any email
Subject	Email subject
Message	Email message

The System Health window enables running and viewing reports and logs for monitoring and analyzing UFM server and fabric health through the following tabs: UFM Health, UFM Logs, UFM Snapshot, Fabric Health, Daily Reports and Topology Compare.

Copyright 2024. PDF Generated on 06/06/2024